

CDF

C# Reference Manual

Version 3.8.1, February 10, 2021

Space Physics Data Facility
NASA / Goddard Space Flight Center

Space Physics Data Facility
NASA/Goddard Space Flight Center
Greenbelt, Maryland 20771 (U.S.A.)

This software may be copied or redistributed as long as it is not sold for profit, but it can be incorporated into any other substantive product with or without modifications for profit or non-profit. If the software is modified, it must include the following notices:

- The software is not the original (for protection of the original author's reputations from any problems introduced by others)
- Change history (e.g. date, functionality, etc.)

This Copyright notice must be reproduced on each copy made. This software is provided as is without any express or implied warranties whatsoever.

Internet – nasa-cdf-support@nasa.onmicrosoft.com

Contents

1	Compiling	1
1.1	Namespaces	1
1.2	Base Classes	1
1.3	Compiling with Compiler Options	2
1.4	Sample programs	3
2	Programming Interface	5
2.1	Item Referencing	5
2.2	Compatible Types	5
2.3	CDFConstants	6
2.4	CDF status	6
2.5	CDF Formats	6
2.6	CDF Data Types	6
2.7	Data Encodings	8
2.8	Data Decodings	9
2.9	Variable Majorities	10
2.10	Record/Dimension Variances	11
2.11	Compressions	11
2.12	Sparseness	12
2.12.1	Sparse Records	12
2.12.2	Sparse Arrays	12
2.13	Attribute Scopes	12
2.14	Read-Only Modes	13
2.15	zModes	13
2.16	-0.0 to 0.0 Modes	13
2.17	Operational Limits	13
2.18	Limits of Names and Other Character Strings	14
2.19	Backward File Compatibility with CDF 2.7	14
2.20	Checksum	15
2.21	Data Validation	16
2.22	8-Byte Integer	17
2.23	Leap Seconds	17
3	Understanding the Application Interface	19
3.1	Unsafe Code and Pointers	19
3.2	Overloaded Methods and Arguments Passing	19
3.3	Multi-Dimensional Arrays	23
3.4	Data Type Equivalent	23
3.5	Fixed Statement	24
3.6	Exception Handling	24
3.7	Dimensional Limitations	25
4	Application Interface	27
4.1	Library Information	28
4.1.1	CDFgetDataTypeSize	28
4.1.2	CDFgetLibraryCopyright	29
4.1.3	CDFgetLibraryVersion	29
4.1.4	CDFgetStatusText	30

4.2	CDF	31
4.2.1	CDFclose.....	31
4.2.2	CDFcloseCDF	32
4.2.3	CDFcreate	33
4.2.4	CDFcreateCDF	34
4.2.5	CDFdelete	35
4.2.6	CDFdeleteCDF	36
4.2.7	CDFdoc	37
4.2.8	CDFerror	38
4.2.9	CDFgetCacheSize.....	38
4.2.10	CDFgetChecksum.....	39
4.2.11	CDFgetCompression.....	40
4.2.12	CDFgetCompressionCacheSize	41
4.2.13	CDFgetCompressionInfo	42
4.2.14	CDFgetCopyright	43
4.2.15	CDFgetDecoding.....	44
4.2.16	CDFgetEncoding	45
4.2.17	CDFgetFileBackward	45
4.2.18	CDFgetFormat.....	46
4.2.19	CDFgetLeapSecondLastUpdated	47
4.2.20	CDFgetLibraryCopyright.....	48
4.2.21	CDFgetLibraryVersion	49
4.2.22	CDFgetMajority	49
4.2.23	CDFgetName.....	50
4.2.24	CDFgetNegtoPosfp0Mode.....	51
4.2.25	CDFgetReadOnlyMode	52
4.2.26	CDFgetStageCacheSize	53
4.2.27	CDFgetValidate.....	54
4.2.28	CDFgetVersion.....	54
4.2.29	CDFgetzMode	55
4.2.30	CDFinquire.....	56
4.2.31	CDFinquireCDF	58
4.2.32	CDFopen	59
4.2.33	CDFopenCDF.....	60
4.2.34	CDFselect.....	61
4.2.35	CDFselectCDF	62
4.2.36	CDFsetCacheSize	63
4.2.37	CDFsetChecksum	64
4.2.38	CDFsetCompression.....	65
4.2.39	CDFsetCompressionCacheSize.....	66
4.2.40	CDFsetDecoding	66
4.2.41	CDFsetEncoding.....	67
4.2.42	CDFsetFileBackward.....	68
4.2.43	CDFsetFormat	69
4.2.44	CDFsetLeapSecondLastUpdated.....	70
4.2.45	CDFsetMajority	70
4.2.46	CDFsetNegtoPosfp0Mode	71
4.2.47	CDFsetReadOnlyMode	72
4.2.48	CDFsetStageCacheSize.....	73
4.2.49	CDFsetValidate	74
4.2.50	CDFsetzMode.....	74
4.3	Variables	75
4.3.1	CDFcloserVar.....	75
4.3.2	CDFclosezVar	76
4.3.3	CDFconfirmrVarExistence	77
4.3.4	CDFconfirmrVarPadValueExistence	78

4.3.5	CDFconfirmzVarExistence	79
4.3.6	CDFconfirmzVarPadValueExistence	79
4.3.7	CDFcreatorVar	80
4.3.8	CDFcreatezVar	82
4.3.9	CDFdeleterVar	84
4.3.10	CDFdeleterVarRecords	85
4.3.11	CDFdeletezVar	86
4.3.12	CDFdeletezVarRecords	86
4.3.13	CDFdeletezVarRecordsRenumber	87
4.3.14	CDFgetMaxWrittenRecNums	88
4.3.15	CDFgetNumrVars	89
4.3.16	CDFgetNumzVars	90
4.3.17	CDFgetrVarAllocRecords	91
4.3.18	CDFgetrVarBlockingFactor	92
4.3.19	CDFgetrVarCacheSize	93
4.3.20	CDFgetrVarCompression	94
4.3.21	CDFgetrVarData	95
4.3.22	CDFgetrVarDataType	96
4.3.23	CDFgetrVarDimVariances	97
4.3.24	CDFgetrVarInfo	98
4.3.25	CDFgetrVarMaxAllocRecNum	99
4.3.26	CDFgetrVarMaxWrittenRecNum	100
4.3.27	CDFgetrVarName	101
4.3.28	CDFgetrVarNumElements	102
4.3.29	CDFgetrVarNumRecsWritten	103
4.3.30	CDFgetrVarPadValue	103
4.3.31	CDFgetrVarRecordData	104
4.3.32	CDFgetrVarRecVariance	105
4.3.33	CDFgetrVarReservePercent	106
4.3.34	CDFgetrVarsDimSizes	107
4.3.35	CDFgetrVarSeqData	108
4.3.36	CDFgetrVarSeqPos	109
4.3.37	CDFgetrVarsMaxWrittenRecNum	110
4.3.38	CDFgetrVarsNumDims	111
4.3.39	CDFgetrVarSparseRecords	112
4.3.40	CDFgetVarNum	113
4.3.41	CDFgetzVarAllocRecords	114
4.3.42	CDFgetzVarBlockingFactor	115
4.3.43	CDFgetzVarCacheSize	116
4.3.44	CDFgetzVarCompression	117
4.3.45	CDFgetzVarData	118
4.3.46	CDFgetzVarDataType	119
4.3.47	CDFgetzVarDimSizes	120
4.3.48	CDFgetzVarDimVariances	121
4.3.49	CDFgetzVarInfo	122
4.3.50	CDFgetzVarMaxAllocRecNum	123
4.3.51	CDFgetzVarMaxWrittenRecNum	124
4.3.52	CDFgetzVarName	125
4.3.53	CDFgetzVarNumDims	125
4.3.54	CDFgetzVarNumElements	126
4.3.55	CDFgetzVarNumRecsWritten	127
4.3.56	CDFgetzVarPadValue	128
4.3.57	CDFgetzVarRecordData	129
4.3.58	CDFgetzVarRecVariance	130
4.3.59	CDFgetzVarReservePercent	131
4.3.60	CDFgetzVarSeqData	132

4.3.61	CDFgetzVarSeqPos	133
4.3.62	CDFgetzVarsMaxWrittenRecNum	134
4.3.63	CDFgetzVarSparseRecords.....	135
4.3.64	CDFhyperGetrVarData	136
4.3.65	CDFhyperGetzVarData.....	137
4.3.66	CDFhyperPutrVarData	139
4.3.67	CDFhyperPutzVarData	141
4.3.68	CDFinquirerVar.....	143
4.3.69	CDFinquirezVar	145
4.3.70	CDFputrVarData	146
4.3.71	CDFputrVarPadValue.....	147
4.3.72	CDFputrVarRecordData	148
4.3.73	CDFputrVarSeqData.....	149
4.3.74	CDFputzVarData	150
4.3.75	CDFputzVarPadValue	152
4.3.76	CDFputzVarRecordData.....	153
4.3.77	CDFputzVarSeqData	154
4.3.78	CDFrenamerVar	155
4.3.79	CDFrenamezVar.....	156
4.3.80	CDFsetrVarAllocBlockRecords.....	156
4.3.81	CDFsetrVarAllocRecords	157
4.3.82	CDFsetrVarBlockingFactor	158
4.3.83	CDFsetrVarCacheSize	159
4.3.84	CDFsetrVarCompression.....	160
4.3.85	CDFsetrVarDataSpec.....	161
4.3.86	CDFsetrVarDimVariances	162
4.3.87	CDFsetrVarInitialRecs.....	163
4.3.88	CDFsetrVarRecVariance	163
4.3.89	CDFsetrVarReservePercent	164
4.3.90	CDFsetrVarsCacheSize.....	165
4.3.91	CDFsetrVarSeqPos	166
4.3.92	CDFsetrVarSparseRecords	167
4.3.93	CDFsetzVarAllocBlockRecords.....	168
4.3.94	CDFsetzVarAllocRecords.....	169
4.3.95	CDFsetzVarBlockingFactor	170
4.3.96	CDFsetzVarCacheSize.....	170
4.3.97	CDFsetzVarCompression.....	171
4.3.98	CDFsetzVarDataSpec	172
4.3.99	CDFsetzVarDimVariances.....	173
4.3.100	CDFsetzVarInitialRecs	174
4.3.101	CDFsetzVarRecVariance	175
4.3.102	CDFsetzVarReservePercent	176
4.3.103	CDFsetzVarsCacheSize	176
4.3.104	CDFsetzVarSeqPos.....	177
4.3.105	CDFsetzVarSparseRecords	178
4.3.106	CDFvarClose	179
4.3.107	CDFvarCreate.....	180
4.3.108	CDFvarGet	182
4.3.109	CDFvarHyperGet.....	183
4.3.110	CDFvarHyperPut	184
4.3.111	CDFvarInquire.....	185
4.3.112	CDFvarNum	187
4.3.113	CDFvarPut.....	188
4.3.114	CDFvarRename	189
4.4	Attributes/Entries	190
4.4.1	CDFattrCreate	190

4.4.2	CDFattrEntryInquire.....	192
4.4.3	CDFattrGet.....	193
4.4.4	CDFattrInquire.....	194
4.4.5	CDFattrNum.....	196
4.4.6	CDFattrPut.....	196
4.4.7	CDFattrRename.....	198
4.4.8	CDFconfirmAttrExistence.....	199
4.4.9	CDFconfirmEntryExistence.....	200
4.4.10	CDFconfirmEntryExistence.....	200
4.4.11	CDFconfirmEntryExistence.....	201
4.4.12	CDFcreateAttr.....	202
4.4.13	CDFdeleteAttr.....	203
4.4.14	CDFdeleteAttrEntry.....	204
4.4.15	CDFdeleteAttrEntry.....	205
4.4.16	CDFdeleteAttrEntry.....	206
4.4.17	CDFgetAttrEntry.....	207
4.4.18	CDFgetAttrEntryDataType.....	208
4.4.19	CDFgetAttrEntryNumElements.....	209
4.4.20	CDFgetAttrMaxEntry.....	210
4.4.21	CDFgetAttrMaxEntry.....	211
4.4.22	CDFgetAttrMaxEntry.....	212
4.4.23	CDFgetAttrName.....	213
4.4.24	CDFgetAttrNum.....	213
4.4.25	CDFgetAttrEntry.....	214
4.4.26	CDFgetAttrEntryDataType.....	215
4.4.27	CDFgetAttrEntryNumElements.....	217
4.4.28	CDFgetAttrEntryNumStrings.....	218
4.4.29	CDFgetAttrEntryStrings.....	219
4.4.30	CDFgetAttrScope.....	220
4.4.31	CDFgetAttrEntry.....	221
4.4.32	CDFgetAttrEntryDataType.....	222
4.4.33	CDFgetAttrEntryNumElements.....	223
4.4.34	CDFgetAttrEntryNumStrings.....	224
4.4.35	CDFgetAttrEntryStrings.....	225
4.4.36	CDFgetNumAttrEntries.....	226
4.4.37	CDFgetNumAttributes.....	227
4.4.38	CDFgetNumAttrEntries.....	228
4.4.39	CDFgetNumAttrEntries.....	229
4.4.40	CDFgetNumAttributes.....	229
4.4.41	CDFgetNumAttributes.....	230
4.4.42	CDFinquireAttr.....	231
4.4.43	CDFinquireAttrEntry.....	233
4.4.44	CDFinquireAttrEntry.....	234
4.4.45	CDFinquireAttrEntry.....	235
4.4.46	CDFputAttrEntry.....	237
4.4.47	CDFputAttrEntry.....	238
4.4.48	CDFputAttrEntryStrings.....	239
4.4.49	CDFputAttrEntry.....	240
4.4.50	CDFputAttrEntryStrings.....	242
4.4.51	CDFrenameAttr.....	243
4.4.52	CDFsetAttrEntryDataSpec.....	243
4.4.53	CDFsetAttrEntryDataSpec.....	244
4.4.54	CDFsetAttrScope.....	245
4.4.55	CDFsetAttrEntryDataSpec.....	246
4.5	Read Functions.....	247
4.5.1	ReadCDF.....	247

4.5.2	ReadCDFGlobalAttributes.....	250
4.5.3	ReadCDFInfo	252
4.5.4	ReadCDFVariable	253
4.5.5	ReadCDFVariables	254
4.5.6	ReadCDFVariableAttributes	256
4.5.7	ReadCDFVariableData	257
4.5.8	ReadCDFVariableInfo	258
5	Interpreting CDF Status Codes.....	261
6	EPOCH Utility Routines.....	262
6.1	computeEPOCH.....	262
6.2	EPOCHbreakdown	263
6.3	toEncodeEPOCH.....	263
6.4	encodeEPOCH	264
6.5	encodeEPOCH1	264
6.6	encodeEPOCH2	264
6.7	encodeEPOCH3	265
6.8	encodeEPOCH4	265
6.9	encodeEPOCHx	265
6.10	toParseEPOCH.....	266
6.11	parseEPOCH	266
6.12	parseEPOCH1	266
6.13	parseEPOCH2	267
6.14	parseEPOCH3	267
6.15	parseEPOCH4	267
6.16	computeEPOCH16.....	267
6.17	EPOCH16breakdown	268
6.18	toEncodeEPOCH16.....	268
6.19	encodeEPOCH16	268
6.20	encodeEPOCH16_1.....	269
6.21	encodeEPOCH16_2.....	269
6.22	encodeEPOCH16_3.....	269
6.23	encodeEPOCH16_4.....	270
6.24	encodeEPOCH16_x.....	270
6.25	toParseEPOCH16.....	271
6.26	parseEPOCH16	271
6.27	parseEPOCH16_1	271
6.28	parseEPOCH16_2	271
6.29	parseEPOCH16_3	272
6.30	parseEPOCH16_4	272
6.31	EPOCHtoUnixTime	272
6.32	UnixTimetoEPOCH	273
6.33	EPOCH16toUnixTime.....	273
6.34	UnixTimetoEPOCH16.....	273
7	TT2000 Utility Routines	275
7.1	computeTT2000.....	275
7.2	TT2000breakdown	277
7.3	toEncodeTT2000.....	278
7.4	encodeTT2000	279
7.5	toParseTT2000	280
7.6	ParseTT2000	280
7.7	TT2000toUnixTime.....	281
7.8	UnixTimetoTT2000.....	281

7.9	CDFgetLastDateinLeapSecondsTable	281
8	CDF Utility Methods.....	283
8.1	CDFFileExists.....	283
8.2	CDFgetChecksumValue	283
8.3	CDFgetCompressionTypeValue	283
8.4	CDFgetDataTypeValue	284
8.5	CDFgetDecodingValue	284
8.6	CDFgetEncodingValue.....	285
8.7	CDFgetFormatValue	285
8.8	CDFgetMajorityValue	286
8.9	CDFgetSparseRecordValue	286
8.10	CDFgetStringChecksum	286
8.11	CDFgetStringCompressionType	286
8.12	CDFgetStringDataType	287
8.13	CDFgetStringDecoding	287
8.14	CDFgetStringEncoding	287
8.15	CDFgetStringFormat	287
8.16	CDFgetStringMajority.....	287
8.17	CDFgetStringSparseRecord.....	288
9	CDF Exception Methods.....	289
9.1	CDFgetCurrentStatus	289
9.2	CDFgetStatusMsg	289

Chapter 1

1 Compiling

C#-CDF distribution is packaged in a self-extracting installer. Once the installer is downloaded and run, all distributed files, i.e., APIs, test programs, batch files, help information and the document, will be placed into a directory of choice, and environment variables, **PATH** and **CsharpCDFDir**, are automatically set. If an older version already exists in the host machine, the installer will try to remove it before the new one is installed.

To C#, CDF library is unmanaged code distributed in the native DLL. The distributed .DLLs were built from a 32-bit (x86) Windows and they can be run on a 32-bit Windows via the x86-compatible Common Language Runtime (CLR), as well as a 64-bit Windows under WOW64.

1.1 Namespaces

Several classes are created for C# applications that facilitate the calls to the native **CDF .DLL**. The **CDF namespace** has been set up to include these CDF related classes: **CDFConstants**, **CDFException**, **CDFAPIs**, and **CDFUtils**. **CDFConstants** provides commonly used constants that mimic to those defined in the .DLL **CDFException** provides the exception handling when a failed CDF operation is detected. **CDFAPIs** provide all (static) public (and private) methods that C# applications can call to interact with the similar, underlining functions provided by the CDF Standard Interface in the .DLL. **CDFUtils** provides several small utility tools. These classes are distributed in the form of **signed assemblies**, as **.DLLs**. To facilitate the access to functions in DLL, each C# application must use the “**cdf**” namespace in order to call the C#-CDF APIs. The following namespaces should be included by C# applications that call CDF APIs:

```
using System;
using System.Runtime.InteropServices;
using CDF;
```

1.2 Base Classes

CDFAPIs is the main class that provides the C#-CDF APIs. Class **CDFAPIs** inherits from **CDFConstants** class, which defines all constants referenced by the CDF. A C# application, if inheriting from the **CDFAPIs** class, can call all

CDFAPIs methods and refer CDFConstants' constants directly, without specifying their class names. CDFException class inherits from C#'s Exception class and CDFUtils class inherits from CDFConstants class as well, .

1.3 Compiling with Compiler Options

If a test application, e.g., TestCDF.cs, resides in the same directory as all distributed .dll files, the following command can be used to create an executable

```
csc /unsafe /platform:x86 /r:CDFAPIs.dll,CDFException.dll,  
CDFConstants.dll,CDFUtils.dll TestCDF.cs
```

csc.exe, the C# compiler, can be called automatically from an IDE such as Visual Studio .NET, or run from the command line if the PATH environment variable is set properly. csc.exe can be found in the **Windows's .NET Framework** directory, <windows>\Microsoft.NET\Framework\v#. # (v#. # as v3.5 or in the latest release version).

/unsafe option is required as pointers are used by C# applications to communicate with the CDF APIs and .DLL.
/platform:x86 option is required for the Windows running 64-bit OS as C#-CDF is built on an **x86** (32-bit) platform.

When the C#-CDF package is installed, the **PATH** environment variable is automatically modified to include the installation directory so the native CDF .DLL, **dlldcfsharp.dll**, becomes available when a C# application calls CDF functions. Once the executable, TestCDF.exe, is created, it can be run from any directory.

If the C# applications that call CDF APIs reside in the directories other than the C#-CDF installation directory, the following compilation command can be used to create an executable (.exe):

```
csc /unsafe /platform:x86  
/lib:%CsharpCDFDir%  
/r:cdfapis.dll,cdfconstants.dll,cdfexception.dll,cdfutils.dll  
TestCDF.cs
```

where environment variable CsharpCDFDir, the installation directory for C#-CDF package, .is set when the installer is run.

When the executable is run, an exception of "**FileNotFoundException**" will be encountered as CDFAPIs could not be loaded. It's because the distributed CDF assemblies are considered **private** in the .NET environment. The .NET Framework's runtime, **Common Language Runtime (CLR)**, will not be able to locate the files if the application resides in a different directory from the called assemblies. To make these assemblies **global** so CLR can locate, they need to be placed in the **Global Assembly Cache (GAC)** repository. Use the following steps to do so:

```
gacutil /i CDFConstants.dll  
gacutil /i CDFException.dll  
gacutil /i CDFAPIs.dll  
gacutil /i CDFUtils.dll
```

gacutil.exe (Global Assembly Cache utility) is a **Microsoft Software Development Kits (SDKs)** utility that can insert, list and remove the assemblies to and from GAC. Gacutil.exe usually can be found at <Program Files>\Microsoft SDKs\Windows\v#. #\bin (v#. # as v6.0A or in the latest release version). Use "gacutil /u" to remove assemblies of older versions form GAC.

ildasm.exe is another SDKs utility that can be used to browse the assemblies for information as versions, keys, etc..

1.4 Sample programs

Several sample programs are included for distribution. **Qst2cs.cs** and **Qst2cs2.cs**, two quick test programs for C#, are similar and call the same APIs. The only significant difference between them is they use different overloaded methods when calling the same APIs: Qst2cs uses **pointers arguments**, if possible, while Qst2cs2 passes the base class **objects** for arguments, instead. Tests show that Qst2cs runs faster than Qst2cs2. **Qts2cEpoch.cs** and **Qst2cEpoch16.cs** are two sample programs that show how EPOCH-related functions are used. A batch file, **tocompile.bat**, is distributed along with the sample programs. Execute it from a Command Prompt window to compile the programs into executables (**.exe**). Run **totest.bat** to test the executables to make sure they all work fine.

Chapter 2

2 Programming Interface

2.1 Item Referencing

The following sections describe various aspects of the programming interface for C# applications.

For C# applications, all item numbers are referenced starting at zero (0). These include variable, attribute, and attribute entry numbers, record numbers, dimensions, and dimension indices. Note that both rVariables and zVariables are numbered starting at zero (0).

2.2 Compatible Types

As C# and CDF .DLL may have different sizes of the same data types, e.g. long, the size compatibility must be enforced when passing the data between the two. On 32-bit Windows, **4-byte long** has been used all over in the CDF .DLL. However, long in C# is defined as **8-byte**. So, to make the size compatible, 4-byte **int** is used, instead, in C# for each long type variable in the .DLL. For CDF data of CDF_CHAR, or CDF_UCHAR type, it is represented by a string in C#. They are not size compatible, so conversion, performed in the APIs, is needed between a character array in .DLL and string in C#.

The C#-CDF operations normally involve two variables: the operation status, status, and the CDF identifier, id:

status	All C#-CDF functions, except CDFvarNum, CDFgetVarNum, CDFattrNum and CDFgetAttrNum, return an operation status. This status is defined as an int in .DLL and C#. The CDFerror method can be used to inquire the meaning of any status code. Appendix A lists the possible status codes along with their explanations. Chapter 5 describes how to interpret status codes.
id	An identifier (or handle) for a CDF that must be used when referring to a CDF. This identifier has a type of void* in .DLL and C#. A new void* is established whenever a CDF is created or opened, establishing a connection to that CDF on disk. The void* is used in all subsequent operations on a particular CDF. The void* must not be altered by an application. With this pointer, C# applications are always declared as “unsafe” .

2.3 CDFConstants

CDF defines a set of constants that are used all over the .DLL. These constants are mimicked in CDFConstants class with compatible data types.

2.4 CDF status

These constants are of same type as the operation status, mentioned in 2.2.

CDF_OK	A status code indicating the normal completion of a CDF function.
CDF_WARN	Threshold constant for testing severity of non-normal CDF status codes.

Status less than CDF_OK normally indicate an error. For most cases, an exception will be thrown.

2.5 CDF Formats

SINGLE_FILE	The CDF consists of only one file. This is the default file format.
MULTI_FILE	The CDF consists of one header file for control and attribute data and one additional file for each variable in the CDF.

2.6 CDF Data Types

One of the following constants must be used when specifying a CDF data type for an attribute entry or variable.

CDF_BYTE	1-byte, signed integer.
CDF_CHAR	1-byte, signed character.
CDF_INT1	1-byte, signed integer.
CDF_UCHAR	1-byte, unsigned character.
CDF_UINT1	1-byte, unsigned integer.
CDF_INT2	2-byte, signed integer.
CDF_UINT2	2-byte, unsigned integer.

CDF_INT4	4-byte, signed integer.
CDF_UINT4	4-byte, unsigned integer.
CDF_INT8	8-byte, signed integer.
CDF_REAL4	4-byte, floating point.
CDF_FLOAT	4-byte, floating point.
CDF_REAL8	8-byte, floating point.
CDF_DOUBLE	8-byte, floating point.
CDF_EPOCH ¹	8-byte, floating point.
CDF_EPOCH16	two 8-byte, floating point.
CDF_TIME_TT2000 ²	8-byte, signed integer.

The following table depicts the equivalent data type between the CDF and C#:

<u>CDF Data Type</u>	<u>C# Data Type</u>
CDF_BYTE	sbyte
CDF_INT1	sbyte
CDF_UINT1	byte
CDF_INT2	short
CDF_UINT2	ushort
CDF_INT4	int
CDF_UINT4	uint
CDF_INT8	long
CDF_REAL4	float
CDF_FLOAT	float
CDF_REAL8	double
CDF_DOUBLE	double
CDF_EPOCH	double
CDF_EPOCH16	double[] ³
CDF_TIME_TT2000	long
CDF_CHAR	string
CDF_UCHAR	string

CDF_CHAR and CDF_UCHAR are considered character data types. These are significant because only variables of these data types may have more than one element per value (representing the length of the string, where each element is a character).

NOTE: Keep in mind that an long is 8 bytes and that an int is 4 bytes. Use int for CDF data types CDF_INT4 and CDF_UINT4, rather than long. Use long for CDF_INT8 and CDF_TIME_TT2000 data types.

¹ CDF_EPOCH, a double value, with milliseconds since 0000-01-01T00.00.000 as its integer portion and sub-milliseconds at fraction portion. Currently, methods, e.g., breakdown, encode, etc, only handle integer portion.

² CDF_TIME_TT2000, a long value, with nanoseconds since J2000.

³ CDF_EPOCH16 has two doubles, which corresponds to an array as double[] in C#.

2.7 Data Encodings

A CDF's data encoding affects how its attribute entry and variable data values are stored (on disk). Attribute entry and variable values passed into the CDF library (to be written to a CDF) should always be in the host machine's native encoding. Attribute entry and variable values read from a CDF by the CDF library and passed out to an application will be in the currently selected decoding for that CDF (see the Concepts chapter in the CDF User's Guide).

HOST_ENCODING	Indicates host machine data representation (native). This is the default encoding, and it will provide the greatest performance when reading/writing on a machine of the same type.
NETWORK_ENCODING	Indicates network transportable data representation (XDR).
VAX_ENCODING	Indicates VAX data representation. Double-precision floating-point values are encoded in Digital's D_FLOAT representation.
ALPHAVMSd_ENCODING	Indicates DEC Alpha running OpenVMS data representation. Double-precision floating-point values are encoded in Digital's D_FLOAT representation.
ALPHAVMSg_ENCODING	Indicates DEC Alpha running OpenVMS data representation. Double-precision floating-point values are encoded in Digital's G_FLOAT representation.
ALPHAVMSi_ENCODING	Indicates DEC Alpha running OpenVMS data representation. Double-precision floating-point values are encoded in IEEE representation.
ALPHAOSF1_ENCODING	Indicates DEC Alpha running OSF/1 data representation.
SUN_ENCODING	Indicates SUN data representation.
SGi_ENCODING	Indicates Silicon Graphics Iris and Power Series data representation.
DECSTATION_ENCODING	Indicates DECstation data representation.
IBMRS_ENCODING	Indicates IBMRS data representation (IBM RS6000 series).
HP_ENCODING	Indicates HP data representation (HP 9000 series).
IBMPC_ENCODING	Indicates Intel i386 data representation.
NeXT_ENCODING	Indicates NeXT data representation.
MAC_ENCODING	Indicates Macintosh data representation.
ARM_LITTLE_ENCODING	Indicates ARM architecture running little-endian data representation.
ARM_BIG_ENCODING	Indicates ARM architecture running big-endian data representation.
IA64VMSi_ENCODING	Indicates Itanium 64 running OpenVMS data representation. Double-precision floating-point values are encoded in IEEE representation.

IA64VMSd_ENCODING	Indicates Itanium 64 running OpenVMS data representation. Double-precision floating-point values are encoded in Digital's D_FLOAT representation.
IA64VMSg_ENCODING	Indicates Itanium 64 running OpenVMS data representation. Double-precision floating-point values are encoded in Digital's G_FLOAT representation.

When creating a CDF (via CDFcreate) or respecifying a CDF's encoding (via CDFsetEncoding), you may specify any of the encodings listed above. Specifying the host machine's encoding explicitly has the same effect as specifying HOST_ENCODING.

When inquiring the encoding of a CDF, either NETWORK_ENCODING or a specific machine encoding will be returned. (HOST_ENCODING is never returned.)

2.8 Data Decodings

A CDF's decoding affects how its attribute entry and variable data values are passed out to a calling application. The decoding for a CDF may be selected and reselected any number of times while the CDF is open. Selecting a decoding does not affect how the values are stored in the CDF file(s) - only how the values are decoded by the CDF library. Any decoding may be used with any of the supported encodings. The Concepts chapter in the CDF User's Guide describes a CDF's decoding in more detail.

HOST_DECODING	Indicates host machine data representation (native). This is the default decoding.
NETWORK_DECODING	Indicates network transportable data representation (XDR).
VAX_DECODING	Indicates VAX data representation. Double-precision floating-point values will be in Digital's D_FLOAT representation.
ALPHAVMSd_DECODING	Indicates DEC Alpha running OpenVMS data representation. Double-precision floating-point values will be in Digital's D_FLOAT representation.
ALPHAVMSg_DECODING	Indicates DEC Alpha running OpenVMS data representation. Double-precision floating-point values will be in Digital's G_FLOAT representation.
ALPHAVMSi_DECODING	Indicates DEC Alpha running OpenVMS data representation. Double-precision floating-point values will be in IEEE representation.
ALPHAOSF1_DECODING	Indicates DEC Alpha running OSF/1 data representation.
SUN_DECODING	Indicates SUN data representation.
SGi_DECODING	Indicates Silicon Graphics Iris and Power Series data representation.
DECSTATION_DECODING	Indicates DECstation data representation.
IBMRS_DECODING	Indicates IBMRS data representation (IBM RS6000 series).

HP_DECODING	Indicates HP data representation (HP 9000 series).
IBMPC_DECODING	Indicates Intel i386 data representation.
NeXT_DECODING	Indicates NeXT data representation.
MAC_DECODING	Indicates Macintosh data representation.
ARM_LITTLE_DECODING	Indicates ARM architecture running little-endian data representation.
ARM_BIG_DECODING	Indicates ARM architecture running big-endian data representation.
IA64VMSi_DECODING	Indicates Itanium 64 running OpenVMS data representation. Double-precision floating-point values are encoded in IEEE representation.
IA64VMSd_DECODING	Indicates Itanium 64 running OpenVMS data representation. Double-precision floating-point values are encoded in Digital's D_FLOAT representation.
IA64VMSg_DECODING	Indicates Itanium 64 running OpenVMS data representation. Double-precision floating-point values are encoded in Digital's G_FLOAT representation.

The default decoding is HOST_DECODING. The other decodings may be selected via the CDFsetDecoding method. The Concepts chapter in the CDF User's Guide describes those situations in which a decoding other than HOST_DECODING may be desired.

2.9 Variable Majorities

A CDF's variable majority determines the order in which variable values (within the variable arrays) are stored in the CDF file(s). The majority is the same for rVariables and zVariables.

ROW_MAJOR	C-like array ordering for variable storage. The first dimension in each variable array varies the slowest. This is the default.
COLUMN_MAJOR	Fortran-like array ordering for variable storage. The first dimension in each variable array varies the fastest.

Knowing the majority of a CDF's variables is necessary when performing hyper reads and writes. During a hyper read the CDF library will place the variable data values into the memory buffer in the same majority as that of the variables. The buffer must then be processed according to that majority. Likewise, during a hyper write, the CDF library will expect to find the variable data values in the memory buffer in the same majority as that of the variables.

The majority must also be considered when performing sequential reads and writes. When sequentially reading a variable, the values passed out by the CDF library will be ordered according to the majority. When sequentially writing a variable, the values passed into the CDF library are assumed (by the CDF library) to be ordered according to the majority.

As with hyper reads and writes, the majority of a CDF's variables affect multiple variable reads and writes. When performing a multiple variable write, the full-physical records in the buffer passed to the CDF library must have the

CDF's variable majority. Likewise, the full-physical records placed in the buffer by the CDF library during a multiple variable read will be in the CDF's variable majority.

For C applications the compiler-defined majority for arrays is row major. The first dimension of multi-dimensional arrays varies the slowest in memory.

2.10 Record/Dimension Variances

Record and dimension variances affect how variable data values are physically stored.

VARY True record or dimension variance.

NOVARY False record or dimension variance.

If a variable has a record variance of VARY, then each record for that variable is physically stored. If the record variance is NOVARY, then only one record is physically stored. (All of the other records are virtual and contain the same values.)

If a variable has a dimension variance of VARY, then each value/subarray along that dimension is physically stored. If the dimension variance is NOVARY, then only one value/subarray along that dimension is physically stored. (All other values/subarrays along that dimension are virtual and contain the same values.)

2.11 Compressions

The following types of compression for CDFs and variables are supported. For each, the required parameters are also listed. The Concepts chapter in the CDF User's Guide describes how to select the best compression type/parameters for a particular data set. Among the available types, GZIP provides the best result.

NO_COMPRESSION No compression.

RLE_COMPRESSION Run-length encoding compression. There is one parameter.

1. The style of run-length encoding. Currently, only the run-length encoding of zeros is supported. This parameter must be set to RLE_OF_ZEROS.

HUFF_COMPRESSION Huffman compression. There is one parameter.

1. The style of Huffman encoding. Currently, only optimal encoding trees are supported. An optimal encoding tree is determined for each block of bytes being compressed. This parameter must be set to OPTIMAL_ENCODING_TREES.

AHUFF_COMPRESSION Adaptive Huffman compression. There is one parameter.

1. The style of adaptive Huffman encoding. Currently, only optimal encoding trees are supported. An optimal encoding tree is determined

for each block of bytes being compressed. This parameter must be set to `OPTIMAL_ENCODING_TREES`.

`GZIP_COMPRESSION`

Gnu's "zip" compression.⁴ There is one parameter.

1. The level of compression. This may range from 1 to 9. 1 provides the least compression and requires less execution time. 9 provide the most compression but require the most execution time. Values in-between provide varying compromises of these two extremes. 6 normally provides a better balance between compression and execution.

2.12 Sparseness

2.12.1 Sparse Records

The following types of sparse records for variables are supported.

`NO_SPARSERECORDS`

No sparse records.

`PAD_SPARSERECORDS`

Sparse records - the variable's pad value is used when reading values from a missing record.

`PREV_SPARSERECORDS`

Sparse records - values from the previous existing record are used when reading values from a missing record. If there is no previous existing record the variable's pad value is used.

2.12.2 Sparse Arrays

The following types of sparse arrays for variables are supported by VFG.⁵

`NO_SPARSEARRAYS`

No sparse arrays.

Note: sparse array is not supported and will not be implmeneted.

2.13 Attribute Scopes

Attribute scopes are simply a way to explicitly declare the intended use of an attribute by user applications (and the CDF toolkit).

`GLOBAL_SCOPE`

Indicates that an attribute's scope is global (applies to the CDF as a whole).

⁴ Disabled for PC running 16-bit DOS/Windows 3.x.

⁵ The sparse arrays are not (and will not be) supported.

VARIABLE_SCOPE	Indicates that an attribute's scope is by variable. (Each rEntry or zEntry corresponds to an rVariable or zVariable, respectively.)
----------------	---

2.14 Read-Only Modes

Once a CDF has been opened, it may be placed into a read-only mode to prevent accidental modification (such as when the CDF is simply being browsed). Read-only mode is selected via CDFsetReadOnlyMode method. When read-only mode is set, all metadata is read into memory for future reference. This improves overall metadata access performance but is extra overhead if metadata is not needed. Note that if the CDF is modified while not in read-only mode, subsequently setting read-only mode in the same session will not prevent future modifications to the CDF.

READONLYon	Turns on read-only mode.
READONLYoff	Turns off read-only mode.

2.15 zModes

Once a CDF has been opened, it may be placed into one of two variations of zMode. zMode is fully explained in the Concepts chapter in the CDF User's Guide. A zMode is selected via CDFsetzMode method.

zMODEoff	Turns off zMode.
zMODEon1	Turns on zMode/1.
zMODEon2	Turns on zMode/2.

2.16 -0.0 to 0.0 Modes

Once a CDF has been opened, the CDF library may be told to convert -0.0 to 0.0 when read from or written to that CDF. This mode is selected via CDFsetNegtoPosfp0Mode method.

NEGtoPOSfp0on	Convert -0.0 to 0.0 when read from or written to a CDF.
NEGtoPOSfp0off	Do not convert -0.0 to 0.0 when read from or written to a CDF.

2.17 Operational Limits

These are limits within the CDF library. If you reach one of these limits, please contact CDF User Support.

CDF_MAX_DIMS	Maximum number of dimensions for the rVariables or a zVariable.
--------------	---

CDF_MAX_PARMS Maximum number of compression or sparseness parameters.

The CDF library imposes no limit on the number of variables, attributes, or attribute entries that a CDF may have. on the PC, however, the number of rVariables and zVariables will be limited to 100 of each in a multi-file CDF because of the 8.3 naming convention imposed by MS-DOS.

2.18 Limits of Names and Other Character Strings

CDF_PATHNAME_LEN Maximum length of a CDF file name. A CDF file name may contain disk and directory specifications that conform to the conventions of the operating systems being used (including logical names on OpenVMS systems and environment variables on UNIX systems).

CDF_VAR_NAME_LEN256 Maximum length of a variable name.

CDF_ATTR_NAME_LEN256 Maximum length of an attribute name.

CDF_COPYRIGHT_LEN Maximum length of the CDF Copyright text.

CDF_STATUSTEXT_LEN Maximum length of the explanation text for a status code.

2.19 Backward File Compatibility with CDF 2.7

By default, a CDF file created by CDF V3.0 or a later release is not readable by any of the CDF releases before CDF V3.0 (e.g. CDF 2.7.x, 2.6.x, 2.5.x, etc.). The file incompatibility is due to the 64-bit file offset used in CDF 3.0 and later releases (to allow for files greater than 2G bytes). Note that before CDF 3.0, 32-bit file offset was used.

There are two ways to create a file that's backward compatible with CDF 2.7 and 2.6, but not 2.5. A method, **CDFsetFileBackward**, can be called to control the backward compatibility from an application before a CDF file is created (i.e. CDFcreateCDF). This method takes an argument to control the backward file compatibility. Passing a flag value of **BACKWARDFILEon**, defined in **CDFConstants**, to the method will cause new files being created to be backward compatible. The created files are of version V2.7.2, not V3.*. This option is useful for those who wish to create and share files with colleagues who still use a CDF V2.7/V2.6 library. If this option is specified, the maximum file size is limited to 2G bytes. Passing a flag value of **BACKWARDFILEoff** will use the default file creation mode and newly created files will not be backward compatible with older libraries. The created files are of version 3.* and thus their file sizes can be greater than 2G bytes. Not calling this method has the same effect of calling the method with an argument value of **BACKWARDFILEoff**.

The following example creates two CDF files: "MY_TEST1.cdf" is a V3.* file while "MY_TEST2.cdf" a V2.7 file.

```
.
.
void*      id1, id2;           /* CDF identifier. */
int  status;                 /* Returned status code. */

try {
    status = CDFcreateCDF("MY_TEST1", &id1);
```

```

..
    CDFsetFileBackward(BACKWARDFILEon);
    status = CDFCreateCDF("MY_TEST2", &id2);

} catch (CDFException ex) {
}.
.

```

Another method is through an environment variable and no method call is needed (and thus no code change involved in any existing applications). The environment variable, **CDF_FILEBACKWARD** on Windows, is used to control the CDF file backward compatibility. If its value is set to “**TRUE**”, all new CDF files are backward compatible with CDF V2.7 and 2.6. This applies to any applications or CDF tools dealing with creation of new CDFs. If this environment variable is not set, or its value is set to anything other than “**TRUE**”, any files created will be of the CDF 3.* version and these files are not backward compatible with the CDF 2.7.2 or earlier versions .

Normally, only one method should be used to control the backward file compatibility. If both methods are used, the method call through **CDFsetFileBackward** will take the precedence over the environment variable.

You can use the **CDFgetFileBackward** method to check the current value of the backward-file-compatibility flag. It returns 1 if the flag is set (i.e. create files compatible with V2.7 and 2.6) or 0 otherwise.

```

.
.
int  flag;                                /* Returned status code. */
.
flag = CDFgetFileBackward();

```

2.20 Checksum

To ensure the data integrity while transferring CDF files from/to different platforms at different locations, the checksum feature was added in CDF V3.2 as an option for the single-file format CDF files (not for the multi-file format). By default, the checksum feature is not turned on for new files. Once the checksum bit is turned on for a particular file, the data integrity check of the file is performed every time it is open; and a new checksum is computed and stored when it is closed. This overhead (performance hit) may be noticeable for large files. Therefore, it is strongly encouraged to turn off the checksum bit once the file integrity is confirmed or verified.

If the checksum bit is turned on, a 16-byte signature message (a.k.a. message digest) is computed from the entire file and appended to the end of the file when the file is closed (after any create/write/update activities). Every time such file is open, other than the normal steps for opening a CDF file, this signature, serving as the authentic checksum, is used for file integrity check by comparing it to the re-computed checksum from the current file. If the checksums match, the file’s data integrity is verified. Otherwise, an error message is issued. Currently, the valid checksum modes are: **NO_CHECKSUM** and **MD5_CHECKSUM**, both defined in **CDFConstants** class. With **MD5_CHECKSUM**, the **MD5** algorithm is used for the checksum computation. The checksum operation can be applied to CDF files that were created with V2.7 or later.

There are several ways to add or remove the checksum bit. One way is to use the method call with a proper checksum mode. Another way is through the environment variable. Finally, **CDFedit** and **CDFconvert** (CDF tools included as part of the standard CDF distribution package) can be used for adding or removing the checksum bit. Through the Interface call, you can set the checksum mode for both new or existing CDF files while the environment variable method only allows to set the checksum mode for new files.

The environment variable **CDF_CHECKSUM** on Windows is used to control the checksum option. If its value is set to “**MD5**”, all new CDF files will have their checksum bit set with a signature message produced by the MD5 algorithm. If the environment variable is not set or its value is set to anything else, no checksum is set for the new files.

The following example set a new CDF file with the MD5 checksum and set another existing file's checksum to none.

```
.
.
.
void*      id1, id2;          /* CDF identifier. */
int  status;                /* Returned status code. */
int  checksum;              /* Checksum code. */
.
.
status = CDFCreateCDF("MY_TEST1", &id1);
.
status = CDFsetChecksum(id1, MD5_CHECKSUM);
.
status = CDFclose(id1);
.
status = CDFopen("MY_TEST2", &id2);
.
status = CDFsetChecksum(id2, NO_CHECKSUM);
.
status = CDFclose(id2);
.
.
```

2.21 Data Validation

To ensure the data integrity of CDF files and secure operation of CDF-based applications, a data validation feature has been added to the CDF opening logic. This process, as the default, performs sanity checks on the data fields in the CDF's internal data structures to make sure that the values are within valid ranges and consistent with the defined values/types/entries. It also ensures that the variable and attribute associations within the file are valid. Any compromised CDF files, if not validated properly, could cause applications to function unexpectedly, e.g., segmentation fault due to a buffer overflow. The main purpose of this feature is to safeguard the CDF operations, catch any bad data in the file and end the application gracefully if any bad data is identified. Using this feature, in most cases, will slow down the file opening process especially for large or very fragmented files. Therefore, it is recommended that this feature be turned off once a file's integrity is confirmed or verified. Or, the file in question may need a file conversion, which will consolidate the internal data structures and eliminate the fragmentations. Check the **cdconvert** tool program in the CDF User's Guide for further information.⁶

This validation feature is controlled by setting/unsetting the environment variable **CDF_VALIDATE** on Windows is not set or set to "yes", all CDF files are subjected to the data validation process. If the environment variable is set to "no", then no validation is performed. The environment variable can be set at logon or through the command line, which goes into effect during a terminal session, or within an application, which is good only while the application is running. Setting the environment variable, using C method **CDFsetValidate**, at application level will overwrite the setup from the command line. The validation is set to be on when **VALIDATEFILEon** is passed in as an argument. **VALIDATEFILEoff** will turn off the validation. The function, **CDFgetValidate**, will return the validation mode, **1** (one) means data being validated, **0** (zero) otherwise. If the environment variable is not set, the default is to validate the CDF file upon opening.

The following example sets the data validation on when the CDF file, "TEST", is open.

⁶ The data validation during the open process will not check the variable data. It is still possible that data could be corrupted, especially compression is involved. To fully validate a CDF file, use **cdfdump** tool with "--detect" switch.

```

.
.
void*      id          /* CDF identifier. */
int  status        /* Returned status code. */
.
.
CDFsetValidate (VALIDATEFILEon)
status = CDFopen("TEST", &id);
.
.

```

The following example turns off the data validation when the CDF file, "TEST" is open.

```

.
.
.
void*      id          /* CDF identifier. */
int  status        /* Returned status code. */
.
.
CDFsetValidate (VALIDATEFILEoff)
status = CDFopen("TEST", &id);
.
.

```

2.22 8-Byte Integer

Both data types of CDF_INT8 and CDF_TIME_TT2000 use 8-bytes signed integer. C#'s "long" type is the one that matches to these two types.

2.23 Leap Seconds

CDF's CDF_TIME_TT2000 is the epoch value in nanoseconds since **J2000** (2000-01-01T12:00:00.000000000) with leap seconds included. The CDF uses an external or internal table for computing the leap seconds. The external table, if present and properly pointed to by a predefined environment variable, will be used over the internal one. When the C# package is installed, the external table and environment variables are set so it can be used. If the external table is deleted or no longer pointed by the environment variable, the internal, hard-coded table in the library is used. When a new leap second is added, if the external table is updated accordingly, then the software does not need to be upgraded. Refer to CDF User's Guide for leap seconds.

A tool program, **CDFleapsecondsInfo** distributed with the CDFpackage, will show how the table is referred and when the last leap second was added. Optionally, it can dump the table contents.

Chapter 3

3 Understanding the Application Interface

This chapter provides some basic information about the C#'s Application Interfaces (APIs) to CDF, and the native CDF .DLL. The following chapter will describe each API in detail.

3.1 Unsafe Code and Pointers

To manipulate CDFs, pointers are used extensively in CDF APIs to interact with the CDF native .DLL. The CDF file structure object itself is presented as a pointer of void (**void***) once a CDF is opened or created. Data from CDF is read or written through the API calls via pointers directly or indirectly. All APIs for CDF operations and Epoch utilities are built as **unsafe** code. The C# applications, while calling CDF APIs, have to be declared as unsafe as well. Compilation of the applications needs to specify the “**unsafe**” option.

3.2 Overloaded Methods and Arguments Passing

Each CDF API has a sequence of parameters, which define the set of arguments that must be provided for that method in C# applications. Being a strongly typed language, C#'s APIs to CDF follow the same rules for the parameters. APIs that perform CDF data get, put or inquire operations are overloaded as different signatures for the output parameters would make method calls more flexible.

The input parameters in APIs such as the CDF identifier, variable number, attribute number, entry number, record number, record counts and record indices, etc, are always of fixed types as they must be a scalar of type **void*** for CDF identifier, **int** for variable/attribute/entry number and record number/count, or an array of ints, or an array of ints, **int[]**, for record indices or indices counts. Compilation error will occur if any one of the such arguments from the applications does not match to that defined in the API. The output parameters can be in one of the allowable forms defined by the overloaded API methods. For example, for a returned data, var, of type int, the passing argument in the calling application can be either “out var” or &var, a pointer to the declared int variable.

For example, **CDFsetEncoding** and **CDFgetEncoding** are used to set and get the data encoding of a CDF. Both APIs take two parameters, the CDF identifier, always a pointer as void*, and the encoding, an int. **CDFsetEncoding** take both parameters from applications for input, while **CDFgetEncoding** has the CDF identifier as input and the encoding for output. The following code shows how these methods can be used.

To set a CDF's encoding,

```
int status;
void* id;
int encoding;
...
encoding = IBMPC_ENCODING;
status = CDFsetEncoding(id, encoding);
```

The CDF identifier, `id`, is set when a CDF is open or created. The encoding is set to PC encoding, defined in `CDFConstants` class.

Similarly, to get the CDF's encoding:

```
status = CDFgetEncoding(id, out encoding);
```

The "out" argument modifier is specified in the call as it will get the encoding value from the API.

This data inquiry method is overloaded. Alternatively, it can be called by passing in the pointer of the encoding:

```
status = CDFgetEncoding(id, &encoding);
```

APIs that read or write CDF data, either variable's data (and their pad value) or metadata, are overloaded as they need to be more flexible when dealing with data of different pre-defined CDF types, e.g., `CDF_INT1`, `CDF_UINT1`, `CDF_FLOAT`, `CDF_CHAR`, `CDF_EPOCH`, etc. To pass the data value(s) to the APIs, one of the following forms can be used, depending on the data type: **pointer, string, an array of strings or object**. To use data pointers in the API calls, the data has to be of a **numeric type**, and **pre-allocated** if the parameter is a dimensional object. String or an array of strings involves data of `CDF_CHAR` or `CDF_UCHAR` type. As C#'s character/string has a different characteristic from the ASCII-based code in the CDF native DLL library, some manipulations are needed in APIs when dealing with such data. C# objects can be used, as a general form for all data value(s), when reading/writing data from CDF. The called APIs will handle the passed object and map it to its corresponding CDF data type. **Boxing/unboxing** the objects presented by the APIs and/or applications may be needed.

For example, overloaded methods: `CDFputzVarData` and `CDFgetzVarData` are used to write and read a **single data value** for an `zVariable` in a CDF. Both take five parameters: the first four, for input, are the CDF identifier, variable number, record number and indices with fixed types of: **void***, **int**, **int** and an **array of ints (int[])**, respectively, and the last parameter is for data value, as an input for `CDFputzVarData` or an output for `CDFgetzVarData`. To call `CDFputzVarData`, the data value can be passed in as is or use data value's pointer if the data is a numeric. To retrieve the data by `CDFgetzVarData`, either specify the "out" modifier for the value argument, or pass in the data value's pointer if the data is a numeric.

The following samples show how these arguments are set up to write a data value to record 1, indices [1,1] for `zVariable`, "zVar1", a 2-dimensional of `CDF_INT2`. The first one uses the data value as is:

```
int status;
void* id;
int varNum;
int recNum = 1;
int[] indices = new int[] {1,1};
short value = (short) 100;
...
varNum = CDFvarNum(id, "zVar1");
status = CDFputzVarData(id, varNum, recNum, indices, value);
```

Alternatively, the **pointer** to the value argument can be used:

```
...
status = CDFputzVarData(id, varNum, recNum, indices, &value);
```

To read the data value the same variable at the same record and indices: a **pointer** or “out” modifier can be used for the value argument:

short value;

```
...
status = CDFgetzVarData(id, varNum, recNum, indices, out value);
```

Alternatively, the **pointer** to the value argument can be used:

```
...
status = CDFgetzVarData(id, varNum, recNum, indices, &value);
```

If value is declared as an object, instead of its specific type short, use the proper **type casting** to unbox the object after the data is returned.

```
...
object value;
status = CDFgetzVarData(id, varNum, recNum, indices, out value);
short value1 = (short) value;
```

Overloaded APIs that handle the reads and writes of **multiple data values**, have the similar ways of passing arguments. **CDFputzVarRecordData** and **CDFgetzVarRecordData** are two APIs that are used to write and read a full data record, either a scalar or dimensional data, for an zVariable. They both take four parameters: the first three, as input, are the CDF identifier, variable number, record number of the fixed types: **void***, **int** and **int**, respectively, and the last one is data values as an input for CDFputzVarRecordData or output for CDFgetzVarRecordData. Calling CDFputzVarRecordData, the data values object can be passed in as is or use object’s pointer if the data are numeric. The values object parameter in CDFgetzVarRecordData can be declared with its data type and dimensionality, and is passed in with the “out” modifier as **out string**, **array of strings**, as **out string[]**, or **out object**. For numeric type data values, the argument can be passed in as a pointer, as **void***.

The following samples show how the arguments are set in CDFputzVarRecordData to write the full record 1 for zVariable, “zVar1”, a 2-dim [2,3] of type short. The first one passes the data value object as is, while the second one uses a pointer to the data values.

```
int status;
void* id;
int varNum;
int recNum = 1;
short[,] values = new short[2,3] {{1,2,3},{11,12,13}};
...
varNum = CDFvarNum(id, “zVar1”);
status = CDFputzVarRecordData(id, varNum, recNum, values);
```

Alternatively, a pointer to the array of numeric values can be used:

```
fixed (void* pvalues = values) {
    status = CDFputzVarRecordData(id, varNum, recNum, pvalues);
}
```

To use a pointer for the data values, its object needs to be pre-allocated. A **fixed** statement is required to pin the numeric data value array object to avoid garbage collector moving the object around during the call.

For CDFgetzVarRecordData to read back the same variable's record data, one can use "out" modifier for the data values, or pass in a pointer to the pre-allocated data array.

```
void* id;
int varNum;
int recNum = 1;
short[,] values ;
...
varNum = CDFvarNum(id, "zVar1");
status = CDFgetzVarRecordData(id, varNum, recNum, out values);
```

```
Console.WriteLine(values[0.0]+","+ values[0.1]+","+ values[0.2]+"\\n"+
    values[1.0]+","+ values[1.1]+","+ values[1.2]);
```

Alternatively, allocate the array with its type and dimensionality, and pass in the pointer:

```
short[,] values = new short[2,3];
...
fixed (void* pvalues = values) {
    status = CDFgetzVarRecordData(id, varNum, recNum, pvalues);
}
```

```
Console.WriteLine(values[0.0]+","+ values[0.1]+","+ values[0.2]+"\\n"+
    values[1.0]+","+ values[1.1]+","+ values[1.2]);
```

If the data values, in this case, is declared as a base class object, instead of a two-dimensional short, the API will determine the variable's data type and dimensionality and create the data object accordingly before the data values are read. Unboxing the object with a proper type and dimensionality casting is needed after the object is returned.

```
object values;
status = CDFgetzVarRecordData(id, varNum, recNum, out values);
```

```
Console.WriteLine(((short[,])values)[0.0]+","+ ((short[,])values)[0.1]+","+ ((short[,])values)[0.2]+"\\n"+
    ((short[,])values)[1.0]+","+ ((short[,])values)[1.1]+","+ ((short[,])values)[1.2]);
```

NOTE: Using the pointers to pass in the pre-allocated data objects is limited to numeric types. For data read/write operations, it should have a better performance than passing base class objects as APIs with pointers can directly interact with the CDF native .DLL. If a method returns multiple values, either use pointers for all those output arguments, or use "out" modifier for all of them. Mixing pointers and "out" modifier arguments in a call is not supported.,

Pointers can not be used for string data, being a CDF_CHAR or CDF_UCHAR type in a CDF, as different characteristics between the C# characters and the CDF ASCII based library. The data needs to be declared as a string or array of strings, or simply a base class object, if an output operation involve such type. Use base class object for read operations that involve string array data of more than one dimension.

For example, if variable zVar1 is a one dimensional of two elements, of type CDF_CHAR. This sample code will retrieve both strings from the second record from the variable:

```
int status;
void* id;
int varNum;
```

```

int recNum = 1;
string[] strings;
...
...
varNum = CDFvarNum(id, "zVar1");
status = CDFgetzVarRecordData(id, varNum, recNum, out strings);

Console.WriteLine(strings[0]+",""+ strings[1]);

```

If value strings is declared as an object, instead of an array of strings, then unboxing the object is needed when it is returned.

```

object strings;
status = CDFgetzVarRecordData(id, varNum, recNum, out strings);

Console.WriteLine(((string[])strings)[0]+",""+ ((string[])strings)[1]);

```

3.3 Multi-Dimensional Arrays

For data involved multidimensional arrays, CDF's native .DLL data structure is equivalent to the **rectangular array** in C#. Multidimensional arrays of jagged type are not supported by APIs. An extra dimension is added to the retrieved data if the operations involve multiple records. For example, to read two full records from a variable of two-dimensions, 3-by-4 by the hyper get method, the returned will be a three-dimensional, 2-by-3-by-4, object. Conversely, if the hyper read skips certain dimension(s) from an operation, the returned object's dimensionality will be reduced accordingly. For example, to read a row or column from a variable's two-dimensional record, the returned will be a single array of either column or row count.

3.4 Data Type Equivalent

The following list shows the data types used by CDF and their corresponding types in C#:

- CDF_INT1 sbyte
- CDF_INT2 short
- CDF_INT4 int
- CDF_INT8 long
- CDF_UINT1 byte
- CDF_UINT2 ushort
- CDF_UINT4 uint
- CDF_BYTE sbyte
- CDF_REAL float
- CDF_FLOAT float
- CDF_DOUBLE double
- CDF_REAL8 double
- CDF_EPOCH double
- CDF_EPOCH16 double[2]
- CDF_TIME_TT2000 long
- CDF_CHAR string (with manipulation)
- CDF_UCHAR string (with manipulation)

3.5 Fixed Statement

Fixed statement is required to pin C# managed data objects, mainly arrays of numeric data, so that pointers of the objects can be safely used and passed to the CDF APIs. By doing so, the objects' addresses in the heap won't be moved around by the garbage collector during the operation.

For example, `CDFhyperGetzVarData` method can be called to retrieve a number of data values for a `zVariable`. For instance, the following application code can be used to read the first four (4) records from a `zVariable` of 2-dim [2,3] of type `CDF_INT4`. The declared data buffer, a 3-dimensional of `int`, is blocked in the fixed statement when the call is made.

```
void* id;
void status;
int varNum;
int recNum = 0, recCount = 4, recInterval = 1;
int[,] indices = new int[,] {0, 0};
int[,] counts = new int[,] {2, 3};
int[,] intervals = new int[,] {1,1};
int [, ,] data = new int[4,2,3];          /* Dimension: record number, row, column */
...
...
fixed (void* pdata = data) {
    status = CDFhyperGetzVarData (id, varNum, recNum, recCount, recInterval, indices, counts, intervals, pdata);
}
...
.
```

3.6 Exception Handling

Except a few APIs, each call to a CDF method will return an operation status. If the status is abnormal, less than `CDF_OK`, an exception might be thrown. It is recommended that the code for the CDF-based application be surrounded by a try-catch block so an exception can be caught and handled. The methods to check the existence of a CDF entity, e.g., entry, attribute, variable, will not throw exception if that entity is not in the CDF. The returned, informational status will reflect so. Once an exception is thrown, the thrown object, if initiated from the CDF APIs, is a `CDFException` class object. There are a couple of class methods, **`GetCurrentStatus`** and **`GetStatusMsg`**, which can be used to acquire the status when an exception is thrown and the descriptive information about that exception.

```
void* id;
int status;
int encoding;
try {
    status = CDFopen("TEST", &id);
    ...
    status = CDFgetEncoding(id, &encoding);
}
```

```
.....
status = CDFclose(id);
} catch (CDFException ex) {
    Console.WriteLine("Exception: "+ex);
    Or,
    int status1 = ex.GetCurrentStatus();
    Console.WriteLine("Exception: "+ex.GetStatusMsg(status1));
}
```

3.7 Dimensional Limitations

The C# to CDF APIs follow the same dimensional restriction as in the CDF native DLL: a limit of **ten** (10) dimensions a CDF variable's numeric typed data record can have. For **string** typed data, represented in a CDF file with CDF_CHAR or CDF_UCHAR type, a limit of four (4) dimensions is applied.

Chapter 4

4 Application Interface

This chapter covers all Application Interfaces (APIs) that C# programs can interact with CDF. These APIs are based on the CDF native extended Standard Interface functions: they bear the same names with the similar calling arguments. They are easier to develop and use, and require a much shorter learning curve. All these APIs are defined as static methods in **CDFAPIs** class.

There are two types of variables (rVariable and zVariable) in CDF, and they can happily coexist in a CDF: Every rVariable in a CDF must have the same number of dimensions and dimension sizes while each zVariable can have its own dimensionality. Since all the rVariables in a CDF must have the same dimensions and dimension sizes, there'll be a lot of disk space wasted if a few variables need big arrays and many variables need small arrays. Since zVariable is more efficient in terms of storage and offers more functionality than rVariable, use of zVariable is strongly recommended. As a matter of fact, there's no reason to use rVariables at all if you are creating a CDF file from scratch. One may wonder why there are rVariables and zVariables, not just zVariables. When CDF was first introduced, only rVariables were available. The inefficiencies with rVariables were quickly realized and addressed with the introduction of zVariables in later CDF releases.

The description for each API will detail its parameters: their types, for input or output; and what the method returns. APIs that are **overloaded** use a special indicator, **TYPE** (and **TYPE2**, **TYPE3**, etc, if necessary), to specify the parameters that can have different signatures. The acceptable data types for each overloaded method are specified. For example, **CDFgetEncoding** method, returning a CDF's encoding, is described as:

```
int CDFgetEncoding (                                     /* out -- Completion status code. */
void* id,                                               /* in -- CDF identifier. */
TYPE encoding);                                       /* out -- CDF encoding. */
                                                    /* TYPE -- int* or "out int" */
```

TYPE can be a pointer to an int, ***int**, or an argument modifier "out" for an int object as "**out int**". The following application shows how the API is used:

```
int status;
int encoding;
void* id;
....
status = CDFgetEncoding(id,&encoding);
Or,
status = CDFgetEncoding(id, out encoding);
```

APIs are grouped based on the CDF entity they operate on. These groups are for general library information, CDF as a whole, variable and attribute/entry.

4.1 Library Information

The functions in this section are related to the current CDF library being used for the CDF operations, and they provide useful information such as the current library version number and Copyright notice.

4.1.1 CDFgetDataTypeSize

```
int CDFgetDataTypeSize (                                     /* out -- Completion status code. */
int dataType,                                             /* in -- CDF data type. */
TYPE numBytes);                                         /* out -- # of bytes for the given type. */
                                                         /* TYPE -- int* or out int */
```

CDFgetDataTypeSize returns the size (in bytes) of the specified CDF data type.

The arguments to CDFgetDataTypeSize are defined as follows:

dataType	The CDF supported data type.
numBytes	The size of dataType.

4.1.1.1. Example(s)

The following example returns the size of the data type CDF_INT4 that is 4 bytes.

```
.
.
.
int status;                                               /* Returned status code. */
int numBytes;                                           /* Number of bytes. */
.
.
try {
...
status = CDFgetDataTypeSize(CDF_INT4, &numBytes);
...
...
} catch (CDFException ex) {
...
}.
.
```

4.1.2 CDFgetLibraryCopyright

```
int CDFgetLibraryCopyright (                               /* out -- Completion status code. */  
out string copyright);                                   /* out -- Library copyright. */
```

CDFgetLibraryCopyright returns the Copyright notice of the CDF library being used.

The arguments to CDFgetLibraryCopyright are defined as follows:

Copyright	The Copyright notice.
-----------	-----------------------

4.1.2.1. Example(s)

The following example returns the Copyright of the CDF library being used.

```
.  
. .  
int status;                                             /* Returned status code. */  
string copyright;                                       /* CDF library copyright. */  
. .  
try {  
    ....  
    status = CDFgetLibraryCopyright(out copyright);  
    ...  
    ...  
} catch (CDFException ex) {  
    ...  
}. .
```

4.1.3 CDFgetLibraryVersion

```
int CDFgetLibraryVersion (                               /* out -- Completion status code. */  
TYPE version,                                           /* out -- Library version. */  
TYPE release,                                           /* out -- Library release. */  
TYPE increment,                                         /* out -- Library increment. */  
out string subIncrement);                               /* out -- Library sub-increment. */  
/* TYPE -- int* or "out int" */
```

CDFgetLibraryVersion returns the version and release information of the CDF library being used.

The arguments to CDFgetLibraryVersion are defined as follows:

version	The library version number.
release	The library release number.
increment	The library incremental number.

subIncrement The library sub-incremental string, a single character.

4.1.3.1. Example(s)

The following example returns the version and release information of the CDF library that is being used.

```
.
.
.
int  status;           /* Returned status code. */
int  version;         /* CDF library version number. */
int  release;        /* CDF library release number. */
int  increment;      /* CDF library incremental number. */
string  subIncrement; /* CDF library sub-incremental character. */
.
.
try {
    ....
    status = CDFgetLibraryVersion(&version, &release, &increment, out subIncrement);
..or,
    status = CDFgetLibraryVersion(out version, out release, out increment, out subIncrement);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
}
```

4.1.4 CDFgetStatusText

```
int CDFgetStatusText( /* out -- Completion status code. */
int status,          /* in -- The status code. */
out string message); /* out -- The status text description. */
```

CDFgetStatusText is identical to CDFError, a legacy CDF function, (see section 4.2.8), and the use of this method is strongly encouraged over CDFError as it might not be supported in the future. This method is used to inquire the text explanation of a given status code. Chapter 5 explains how to interpret status codes and Appendix A lists all of the possible status codes.

The arguments to CDFgetStatusText are defined as follows:

status	The status code to check.
message	The explanation of the status code.

4.1.4.1. Example(s)

The following example displays the explanation text for the error code that is returned from a call to CDFopenCDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
string    text;       /* Explanation text. */
.
.
try {
    ....
    status = CDFopenCDF ("giss_wet1", &id);
    ...
    status = CDFclose(id);
.
} catch (CDFException ex) {
    text = CDFgetStatusMsg(ex.CDFgetCurrentStatus());...
}.

```

4.2 CDF

The functions in this section provide CDF file-specific operations. Any operations involving variables or attributes are described in the following sections. This CDF has to be a newly created or opened from an existing one.

4.2.1 CDFclose

```

int CDFclose(          /* out -- Completion status code. */
void* id);           /* in -- CDF identifier. */

```

CDFclose closes the specified CDF. The CDF's cache buffers are flushed; the CDF's open file is closed (or files in the case of a multi-file CDF); and the CDF identifier is made available for reuse.

NOTE: You must close a CDF with CDFclose to guarantee that all modifications you have made will actually be written to the CDF's file(s). If your program exits, normally or otherwise, without a successful call to CDFclose, the CDF's cache buffers are left unflushed.

The arguments to CDFclose are defined as follows:

id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.

4.2.1.1. Example(s)

The following example will close an open CDF.

```

.
.

```



```

.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
.
.
try {
    ....
    status = CDFopen("...", &id);
    status = CDFclose (id);
} catch (CDFException ex) {
    ...
}.

```

4.2.2 CDFcloseCDF

```

int CDFcloseCDF (          /* out -- Completion status code. */
void* id);                /* in -- CDF identifier. */

```

CDFcloseCDF closes the specified CDF. This method is identical to CDFclose, a legacy CDF function. The use of this method is strongly encouraged over CDFclose as it might not be supported in the future. The CDF's cache buffers are flushed; the CDF's open file is closed (or files in the case of a multi-file CDF); and the CDF identifier is made available for reuse.

NOTE: You must close a CDF with CDFcloseCDF to guarantee that all modifications you have made will actually be written to the CDF's file(s). If your program exits, normally or otherwise, without a successful call to CDFcloseCDF, the CDF's cache buffers are left unflushed.

The arguments to CDFcloseCDF are defined as follows:

id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreateCDF or CDFopenCDF.

4.2.2.1. Example(s)

The following example will close an open CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
.
.
try {
    ....
    status = CDFopenCDF ("giss_wet1", &id);
    ...
    status = CDFcloseCDF (id);
} catch (CDFException ex) {
    ...
}

```

```
    }.
```

4.2.3 CDFcreate

```
int CDFcreate(                                     /* out -- Completion status code. */
string CDFname,                                  /* in -- CDF file name. */
int numDims,                                     /* in -- Number of dimensions, rVariables. */
int[] dimSizes,                                  /* in -- Dimension sizes, rVariables. */
int encoding,                                    /* in -- Data encoding. */
int majority,                                    /* in -- Variable majority. */
void* *id);                                       /* out -- CDF identifier. */
```

CDFcreate, a legacy CDF function, creates a CDF as defined by the arguments. A CDF cannot be created if it already exists. (The existing CDF will not be overwritten.) If you want to overwrite an existing CDF, you must first open it with CDFopenCDF, delete it with CDFdeleteCDF, and then recreate it with CDFcreate. If the existing CDF is corrupted, the call to CDFopen will fail. (An error code will be returned.) In this case you must delete the CDF at the command line. Delete the dotCDF file (having an extension of .cdf), and if the CDF has the multi-file format, delete all of the variable files (having extensions of .v0,.v1,. . . and .z0,.z1,. . .).

The arguments to CDFcreate are defined as follows:

CDFname	The file name of the CDF to create. (Do not specify an extension.) This may be at most CDF_PATHNAME_LEN characters. A CDF file name may contain disk and directory specifications that conform to the conventions of the operating system being used (including logical names on OpenVMS systems and environment variables on UNIX systems).
	UNIX: File names are case-sensitive.
numDims	Number of dimensions the rVariables in the CDF are to have. This may be as few as zero (0) and at most CDF_MAX_DIMS.
dimSizes	The size of each dimension. Each element of dimSizes specifies the corresponding dimension size. Each size must be greater than zero (0). For 0-dimensional rVariables this argument is ignored (but must be present).
encoding	The encoding for variable data and attribute entry data. Specify one of the encodings described in Section 2.7.
majority	The majority for variable data. Specify one of the majorities described in Section 2.9.
id	The identifier for the created CDF. This identifier must be used in all subsequent operations on the CDF.

When a CDF is created, both read and write access are allowed. The default format for a CDF created with CDFcreate is specified in the configuration file of your CDF distribution. Consult your system manager for this default.

NOTE: CDFclose must be used to close the CDF before your application exits to ensure that the CDF will be correctly written to disk.

4.2.3.1. Example(s)

The following example creates a CDF named “test1.cdf” with network encoding and row majority.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  numDims = 3;     /* Number of dimensions, rVariables. */
int[] dimSizes = new int[] {180,360,10}; /* Dimension sizes, rVariables. */
int  majority = ROW_MAJOR; /* Variable majority. */
.
.
try {
    status = CDFcreate ("test1", numDims, dimSizes, NETWORK_ENCODING, majority, &id);
.
} catch (CDFException ex) {
    ...
}.

```

4.2.4 CDFcreateCDF

```
int CDFcreateCDF(          /* out -- Completion status code. */
string cdfName,          /* in -- CDF file name. */
void* *id);             /* out -- CDF identifier. */
```

CDFcreateCDF creates a CDF file. This method is a simple form of CDFcreate without the number of dimensions, dimensional sizes, encoding and majority arguments. It is the better method if only zVariables are to be created in the CDF. The created CDF will use the default encoding (HOST_ENCODING) and majority (ROW_MAJOR). A CDF cannot be created if it already exists. (The existing CDF will not be overwritten.) If you want to overwrite an existing CDF, you can either manually delete the file or open it with CDFopenCDF ,delete it with CDFdeleteCDF, and then recreate it with CDFcreateCDF. If the existing CDF is corrupted, the call to CDFopenCDF will fail. (An error code will be returned.) In this case you must delete the CDF at the command line. Delete the dotCDF file (having an extension of .cdf), and if the CDF has the multi-file format, delete all of the variable files (having extensions of .v0,.v1,. . . and .z0,.z1,. . .).

Note that a CDF file created with CDFcreateCDF can only accept zVariables, not rVariables. But this is fine since zVariables are more flexible than rVariables. See the third paragraph of Chapter 3 for the differences between rVariables and zVariables.

The arguments to CDFcreateCDF are defined as follows:

- | | |
|---------|--|
| CDFname | The file name of the CDF to create. (Do not specify an extension.) This may be at most CDF_PATHNAME_LEN characters. A CDF file name may contain disk and directory specifications that conform to the conventions of the operating system being used (including logical names on OpenVMS systems and environment variables on UNIX systems). |
| | UNIX: File names are case-sensitive. |
| id | The identifier for the created CDF. This identifier must be used in all subsequent operations on the CDF. |

When a CDF is created, both read and write access are allowed. The default format for a CDF created with `CDFcreateCDF` is specified in the configuration file of your CDF distribution. Consult your system manager for this default.

NOTE: `CDFcloseCDF` must be used to close the CDF before your application exits to ensure that the CDF will be correctly written to disk.

4.2.4.1. Example(s)

The following example creates a CDF named “test1.cdf” with the default encoding and majority.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
.
.
try {
    ....
    status = CDFcreateCDF ("test1", &id);
    ...
    ...
    status = CDFclose (id);
} catch (CDFException ex) {
    ...
}
```

4.2.5 CDFdelete

```
int CDFdelete(          /* out -- Completion status code. */
void* id);             /* in -- CDF identifier. */
```

`CDFdelete`, a legacy CDF function, deletes the specified CDF. The CDF files deleted include the dotCDF file (having an extension of `.cdf`), and if a multi-file CDF, the variable files (having extensions of `.v0,v1,..` and `.z0,z1,..`).

You must open a CDF before you are allowed to delete it. If you have no privilege to delete the CDF files, they will not be deleted. If the CDF is corrupted and cannot be opened, the CDF file(s) must be deleted at the command line.

The arguments to `CDFdelete` are defined as follows:

`id` The identifier of the CDF. This identifier must have been initialized by a call to `CDFcreate` (or `CDFcreateCDF`) or `CDFopen`.

4.2.5.1. Example(s)

The following example will open and then delete an existing CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
.
.
try {
    ....
    status = CDFopen ("test2", &id);
    status = CDFdelete (id);
.
} catch (CDFException ex) {
    ...
}.

```

4.2.6 CDFdeleteCDF

```

int CDFdeleteCDF(          /* out -- Completion status code. */
void* id);                /* in -- CDF identifier. */

```

CDFdeleteCDF deletes the specified CDF. This method is identical to CDFdelete, and the use of this method is strongly encouraged over CDFdelete as it might not be supported in the future. The CDF files deleted include the dotCDF file (having an extension of .cdf), and if a multi-file CDF, the variable files (having extensions of .v0,.v1,. . . and .z0,.z1,. . .).

You must open a CDF before you are allowed to delete it. If you have no privilege to delete the CDF files, they will not be deleted. If the CDF is corrupted and cannot be opened, the CDF file(s) must be deleted at the command line.

The arguments to CDFdeleteCDF are defined as follows:

id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.

4.2.6.1. Example(s)

The following example will open and then delete an existing CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
.
.
try {
    ....
    status = CDFopenCDF ("test2", &id);
    ...
    status = CDFdeleteCDF(id);
.
}

```

```

...
} catch (CDFException ex) {
...
}.

```

4.2.7 CDFdoc

```

int CDFdoc(                                     /* out -- Completion status code. */
void* id,                                       /* in -- CDF identifier. */
TYPE version,                                  /* out -- Version number. */
TYPE release,                                  /* out -- Release number. */
out string copyright);                          /* out -- copyright. */
/* TYPE -- int* or "out int" */

```

CDFdoc is used to inquire general information about a CDF. The version/release of the CDF library that created the CDF is provided (e.g., CDF V3.1 is version 3, release 1) along with the CDF copyright notice. The copyright notice is formatted for printing without modification.

The arguments to CDFdoc are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.
version	The version number of the CDF library that created the CDF.
release	The release number of the CDF library that created the CDF.
copyright	The Copyright notice of the CDF library that created the CDF. This string will contain a newline character after each line of the Copyright notice.

4.2.7.1. Example(s)

The following example returns and displays the version/release and copyright notice.

```

.
.
void*      id;                                  /* CDF identifier. */
int  status;                                  /* Returned status code. */
int  version;                                  /* CDF version number. */
int  release;                                  /* CDF release number. */
string  copyright;                              /* Copyright notice. */
.
.
try {
....
status = CDFdoc (id, &version, &release, out copyright);
Or,
status = CDFdoc (id, out version, out release, out copyright);
.

```

```

} catch (CDFException ex) {
    ...
}.

```

4.2.8 CDFerror⁷

```

int CDFerror(                                     /* out -- Completion status code. */
int status,                                     /* in -- Status code. */
out string message);                             /* out -- Explanation text for the status. */

```

CDFerror, a legacy CDF function, is used to inquire the explanation of a given status code (not just error codes). Chapter 5 explains how to interpret status codes and Appendix A lists all of the possible status codes.

The arguments to CDFerror are defined as follows:

status	The status code to check.
message	The explanation of the status code.

4.2.8.1. Example(s)

The following example displays the explanation text if an error code is returned from a call to CDFopen.

```

.
.
.
void*      id;                                     /* CDF identifier. */
int        status;                               /* Returned status code. */
string     text;                                 /* Explanation text. */
.
.
try {
    ....
    status = CDFopen ("giss_wetl", &id);
.
} catch (CDFException ex) {
    int status1 = CDFerror(ex.GetCurrentStatus(), out text); ...
}.

```

4.2.9 CDFgetCacheSize

```

int CDFgetCacheSize (                             /* out -- Completion status code. */
void* id,                                         /* in -- CDF identifier. */
TYPE numBuffers);                                /* out -- CDF's cache buffers. */

```

⁷ A legacy CDF function. While it is still available in V3.1, CDFgetStatusText is the preferred function for it.

/ TYPE -- int* or "out int" */*

CDFgetCacheSize returns the number of cache buffers being used for the dotCDF file when a CDF is open. Refer to the CDF User's Guide for description of caching scheme used by the CDF library.

The arguments to CDFgetCacheSize are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreateCDF (or CDFcreate) or CDFopen.
numBuffers	The number of cache buffers.

4.2.9.1. Example(s)

The following example returns the cache buffers for the open CDF file.

```
.  
. .  
. .  
void*      id;          /* CDF identifier. */  
int  status;          /* Returned status code. */  
int  numBuffers;      /* CDF's cache buffers. */  
. .  
try {  
    ....  
    status = CDFgetCacheSize (id, &numBuffers);  
    Or,  
    status = CDFgetCacheSize (id, out numBuffers);  
    ...  
    ...  
} catch (CDFException ex) {  
    ...  
}.  
}
```

4.2.10 CDFgetChecksum

```
int CDFgetChecksum (          /* out -- Completion status code. */  
void* id,                   /* in -- CDF identifier. */  
TYPE checksum);            /* out -- CDF's checksum mode. */  
                          /* TYPE -- int* or "out int" */
```

CDFgetChecksum returns the checksum mode of a CDF. The CDF checksum mode is described in Section 2.20.

The arguments to CDFgetChecksum are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreateCDF (or CDFcreate) or CDFopen.
checksum	The checksum mode (NO_CHECKSUM or MD5_CHECKSUM).

4.2.10.1. Example(s)

The following example returns the checksum code for the open CDF file.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  checksum;        /* CDF's checksum. */
.
.
try {
    ....
    status = CDFgetChecksum (id, &checksum);
    Or,
    status = CDFgetChecksum (id, out checksum);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
}
```

4.2.11 CDFgetCompression

```
int CDFgetCompression (          /* out -- Completion status code. */
void* id,                      /* in -- CDF identifier. */
TYPE compressionType,        /* out -- CDF's compression type. */
TYPE2 compressionParms,     /* out -- CDF's compression parameters. */
TYPE compressionPercentage); /* out -- CDF's compressed percentage. */
/* TYPE -- int* or "out int" */
/* TYPE2 -- int* or "out int[]" */
```

CDFgetCompression gets the compression information of the CDF. It returns the compression type (method) and, if compressed, the compression parameters and compression rate. CDF compression types/parameters are described in Section 2.11. The compression percentage is the result of the compressed file size divided by its original, uncompressed file size.⁸

The arguments to CDFgetCompression are defined as follows:

- id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
- compressionType The type of the compression.
- compressionParms The parameters of the compression.

⁸ The compression ratio is (100 – compression percentage): the lower the compression percentage, the better the compression ratio.

compressionPercentage The compression rate.

4.2.11.1. Example(s)

The following example returns the compression information of the open CDF file.

```
.
.
.
void*      id;           /* CDF identifier. */
int  status;           /* Returned status code. */
int  compressionType;  /* CDF's compression type. */
int[] compressionParms /* CDF's compression parameters. */
int  compressionPercentage; /* CDF's compression rate. */
.
.
try {
    ....
    compressionParms = new int[1];
    fixed (int*pcompressionParms = compressionParms) {
        status = CDFgetCompression (id, &compression, pcompressionParms, &compressionPercentage);
    }
    Or,
    status = CDFgetCompression (id, out compression, out compressionParms, out compressionPercentage);
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.2.12 CDFgetCompressionCacheSize

```
int CDFgetCompressionCacheSize (           /* out -- Completion status code. */
void* id,                                  /* in -- CDF identifier. */
TYPE numBuffers);                         /* out -- CDF's compressed cache buffers. */
                                           /* TYPE -- int* or "out int" */
```

CDFgetCompressionCacheSize gets the number of cache buffers used for the compression scratch CDF file. Refer to the CDF User's Guide for description of caching scheme used by the CDF library.

The arguments to CDFgetCompressionCacheSize are defined as follows:

Id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
numBuffers	The number of cache buffers.

4.2.12.1. Example(s)

The following example returns the number of cache buffers used for the scratch file from the compressed CDF file.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  numBuffers;      /* CDF's compression cache buffers. */
.
.
try {
    ....
    status = CDFgetCompressionCacheSize (id, &numBuffers);
    Or,
    Status = CDFgetCompressionCacheSize (id, out numBuffers);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
}
```

4.2.13 CDFgetCompressionInfo

```
int CDFgetCompressionInfo (
string CDFname,          /* out -- Completion status code. */
TYPE cType,            /* in -- CDF name. */
TYPE2 cParms,         /* out -- CDF compression type. */
TYPE3 cSize,          /* out -- CDF compression parameters. */
TYPE3 uSize);        /* out -- CDF compressed size. */
                        /* out -- CDF decompressed size. */
                        /* TYPE -- int* or "out int" */
                        /* TYPE2 -- int* or "out int[]" */
                        /* TYPE3 -- long* or "out long" */
```

CDFgetCompressionInfo returns the compression type/parameters of a CDF without having to open the CDF. This refers to the compression of the CDF - not of any compressed variables.

The arguments to CDFgetCompressionInfo are defined as follows:

CDFname	The pathname of a CDF file without the .cdf file extension.
cType	The CDF compression type.
cParms	The CDF compression parameters.
cSize	The compressed CDF file size.
uSize	The size of CDF when decompress the originally compressed CDF.

4.2.13.1. Example(s)

The following example returns the compression information from a “unopen” CDF named “MY_TEST.cdf”.

```
.
.
.
int  status;           /* Returned status code. */
int  cType;           /* Compression type. */
int[] cParms;         /* Compression parameters. */
long cSize;           /* Compressed file size. */
long uSize;           /* Decompressed file size. */
.
.
try {
    ....
    cParms = new int[1];
    fixed (int* pcParms = cParms) {
        status = CDFgetCompressionInfo("MY_TEST", &cType, pcParms, &cSize, &uSize);
    }
    Or,
    status = CDFgetCompressionInfo("MY_TEST", out cType, out cParms, out cSize, out uSize);
    ...
} catch (CDFException ex) {
    ...
}.

```

4.2.14 CDFgetCopyright

```
int CDFgetCopyright (           /* out -- Completion status code. */
void* id,                       /* in -- CDF identifier. */
out string copyright);         /* out -- Copyright notice. */
```

CDFgetCopyright gets the Copyright notice in a CDF.

The arguments to CDFgetCopyright are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
Copyright	CDF Copyright.

4.2.14.1. Example(s)

The following example returns the Copyright in a CDF.

```
.
.
```

```

.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
string     copyright;  /* CDF's copyright. */
.
.
try {
....
    status = CDFgetCopyright (id, out copyright);
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.2.15 CDFgetDecoding

```

int CDFgetDecoding (          /* out -- Completion status code. */
void* id,                   /* in -- CDF identifier. */
TYPE decoding);           /* out -- CDF decoding. */
                          /* TYPE -- int* or "out int" */

```

CDFgetDecoding returns the decoding code for the data in a CDF. The decodings are described in Section 2.8.

The arguments to CDFgetDecoding are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
decoding	The decoding of the CDF.

4.2.15.1. Example(s)

The following example returns the decoding for the CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  decoding;        /* Decoding. */
.
.
try {
....
    status = CDFgetDecoding(id, &decoding);
    Or,
    status = CDFgetDecoding(id, out decoding);
    ...
    ...
}

```


CDFgetFileBackward returns the backward mode information dealing with the creation of a new CDF file. A mode of value 1 indicates when a new CDF file is created, it will be a backward version of V2.7, not the current library version.

The arguments to CDFgetFileBackward are defined as follows:

N/A

4.2.17.1. Example(s)

In the following example, the CDF's file backward mode is acquired.

```
.
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  mode;            /* Backward mode. */
.
.
try {
    ....
    mode = CDFgetFileBackward ();
    if(mode == BACKWARDFILEon) {
        .
    }

} catch (CDFException ex) {
    ...
}.

```

4.2.18 CDFgetFormat

```
int CDFgetFormat (          /* out -- Completion status code. */
void* id,                 /* in -- CDF identifier. */
TYPE format);           /* out -- CDF format. */
                        /* TYPE -- int* or "out int" */
```

CDFgetFormat returns the file format, single or multi-file, of the CDF. The formats are described in Section 2.5.

The arguments to CDFgetFormat are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
format	The format of the CDF.

4.2.18.1. Example(s)

The following example returns the file format of the CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  format;         /* Format. */
.
.
try {
    status = CDFgetFormat(id, &format);
    Or,
    status = CDFgetFormat(id, &format);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
.
```

4.2.19 CDFgetLeapSecondLastUpdated

```
int CDFgetLeapSecondLastUpdated (          /* out -- Completion status code. */
void* id,                                  /* in -- CDF identifier. */
TYPE lastUpdated);                       /* out -- Leap second last updated date. */
                                          /* TYPE -- int* or "out int" */
```

CDFgetLeapSecondLastUpdated returns the leap second last updated from the CDF. This value indicates what/if the leap second table this CDF is based on. It is of YYYYMMDD form. The value can also be negative 1 (-1), the field not set (for older CDFs), or zero (0) if the leap second table is not being accessed. This field is only relevant to TT2000 data in the CDF.

The arguments to CDFgetLeapSecondLastUpdated are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
lastUpdated	The date that the latest leap second was added to the leap second table.

4.2.19.1. Example(s)

The following example returns the date that the last leap second was added to the leap second table from the CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
```



```

int status; /* Returned status code. */
int lastUpdated; /* Date of the last updated. */
.
.
try {
    status = CDFgetLeapSecondLastUpdated (id, &lastUpdated);
    Or,
    status = CDFgetLeapSecondLastUpdated (id, out lastUpdated);
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.2.20 CDFgetLibraryCopyright

```

int CDFgetLibraryCopyright ( /* out -- Completion status code. */
out String copyRight); /* out -- The copyright note. */

```

CDFgetLibraryCopyright returns the CDF copy right statements.

The arguments to CDFgetLeapSecondLastUpdated are defined as follows:

copyRight The copy right statements.

4.2.20.1. Example(s)

The following example returns the copy right note from the CDF library.

```

.
.
.
void* id; /* CDF identifier. */
int status; /* Returned status code. */
String copyRight; /* Copy right note. */
.
.
try {
    status = CDFgetLibraryCopyright (out copyRight);
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.2.21 CDFgetLibraryVersion

```
int CDFgetLibraryVersion (                                /* out -- Completion status code. */
    TYPE version;                                       /* out -- The version of the library. */
    TYPE release;                                       /* out -- The release of the library. */
    TYPE increment;                                     /* out -- The increment of the library. */
    /* TYPE -- int* or "out int" */
    out string subIncrement);                          /* out -- The subincrement of the library. */
```

CDFgetLibraryVersion returns the CDF library version/release/increment/subincrement information.

The arguments to CDFgetLeapSecondLastUpdated are defined as follows:

version	The version
release	The release
increment	The increment
subincrement	The subincrement.

4.2.21.1. Example(s)

The following example returns the library version information from the CDF library.

```
.
.
.
void*    id;                                           /* CDF identifier. */
int      status;                                       /* Returned status code. */
int      version, release, increment;                 /* version/release/increment. */
string   subincrement;                                /* Copy right note. */
.
.
try {
    status = CDFgetLibraryVersion (&version, &release, &increment, out subincrement);
    or,
    status = CDFgetLibraryVersion (out version, out release, out increment, out subincrement);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
}
```

4.2.22 CDFgetMajority

```
int CDFgetMajority (                                /* out -- Completion status code. */
    void* id,                                         /* in -- CDF identifier. */
    TYPE majority);                                  /* out -- Variable majority. */
    /* TYPE -- int* or "out int" */
```

CDFgetMajority returns the variable majority, row or column-major, of the CDF. The majorities are described in Section 2.9.

The arguments to CDFgetMajority are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
majority	The variable majority of the CDF.

4.2.22.1. Example(s)

The following example returns the majority of the CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  majority;        /* Majority. */
.
.
try {
    status = CDFgetMajority (id, &majority);
    Or,
    status = CDFgetMajority (id, out majority);

    ...
    ...
} catch (CDFException ex) {
    ...
}.
}
```

4.2.23 CDFgetName

```
int CDFgetName (          /* out -- Completion status code. */
void* id,                /* in -- CDF identifier. */
out string name);        /* out -- CDF name. */
```

CDFgetName returns the file name of the specified CDF.

The arguments to CDFgetName are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
name	The file name of the CDF.

4.2.23.1. Example(s)

The following example returns the name of the CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
string    name;       /* Name of the CDF. */
.
.
try {
    ....
    status = CDFgetName (id, out name);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
.
```

4.2.24 CDFgetNegtoPosfp0Mode

```
int CDFgetNegtoPosfp0Mode (          /* out -- Completion status code. */
void* id,                          /* in -- CDF identifier. */
TYPE negtoPosfp0);                /* out -- -0.0 to 0.0 mode. */
                                     /* TYPE -- int* or "out int" */
```

CDFgetNegtoPosfp0Mode returns the -0.0 to 0.0 mode of the CDF. You can use CDFsetNegtoPosfp0 method to set the mode. The -0.0 to 0.0 modes are described in Section 2.16.

The arguments to CDFgetNegtoPosfp0Mode are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
negtoPosfp0	The -0.0 to 0.0 mode of the CDF.

4.2.24.1. Example(s)

The following example returns the -0.0 to 0.0 mode of the CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  negtoPosfp0;     /* -0.0 to 0.0 mode. */
.
.
```

```

.
try {
    ....
    status = CDFgetNegtoPosfp0Mode (id, &negtoPosfp0);
    Or,
    status = CDFgetNegtoPosfp0Mode (id, out negtoPosfp0);

    ...
    ....
} catch (CDFException ex) {
    ...
}.

```

4.2.25 CDFgetReadOnlyMode

```

int CDFgetReadOnlyMode(                                     /* out -- Completion status code. */
void* id,                                                 /* in -- CDF identifier. */
TYPE readOnlyMode);                                     /* out -- CDF read-only mode. */
                                                         /* TYPE -- int* or "out int" */

```

CDFgetReadOnlyMode returns the read-only mode for a CDF. You can use CDFsetReadOnlyMode to set the mode of readOnlyMode. The read-only modes are described in Section 2.14.

The arguments to CDFgetReadOnlyMode are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
readOnlyMode	The read-only mode (READONLYon or READONLYoff).

4.2.25.1. Example(s)

The following example returns the read-only mode for the given CDF.

```

.
.
.
void* id;                                                 /* CDF identifier. */
int readMode;                                           /* CDF read-only mode. */
.
.
try {
    ....
    status = CDFgetReadOnlyMode (id, &readMode);
    Or,
    status = CDFgetReadOnlyMode (id, out readMode);

    ...
    ...
} catch (CDFException ex) {

```

```
...
}.
```

4.2.26 CDFgetStageCacheSize

```
int CDFgetStageCacheSize(                                /* out -- Completion status code. */
void* id,                                                /* in -- CDF identifier. */
TYPE numBuffers);                                     /* out -- The stage cache size. */
                                                    /* TYPE -- int* or "out int" */
```

CDFgetStageCacheSize returns the number of cache buffers being used for the staging scratch file a CDF. Refer to the CDF User's Guide for the description of the caching scheme used by the CDF library.

The arguments to CDFgetStageCacheSize are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
numBuffers	The number of cache buffers.

4.2.26.1. Example(s)

The following example returns the number of cache buffers used in a CDF.

```
.
.
.
void*      id;                                         /* CDF identifier. */
int  numBuffers;                                     /* The number of cache buffers. */
.
.
try {
    ....
    status = CDFgetStageCacheSize (id, &numBuffers);
    Or,
    status = CDFgetStageCacheSize (id,  out numBuffers);

    ...
    ...
.
} catch (CDFException ex) {
    ...
}.
}
```

4.2.27 CDFgetValidate

```
int CDFgetValidate(); /* out – CDF validation mode. */
```

CDFgetValidate returns the data validation mode. This information reflects whether when a CDF is open, its certain data fields are subjected to a validation process. 1 is returned if the data validation is to be performed, 0 otherwise.

The arguments to CDFgetVersion are defined as follows:

N/A

4.2.27.1. Example(s)

In the following example, it gets the data validation mode.

```
.  
. .  
. .  
void*      id; /* CDF identifier. */  
int  status; /* Returned status code. */  
int  validate; /* Data validation flag. */  
. .  
try {  
    ....  
    validate = CDFgetValidate ();  
    ...  
    ...  
} catch (CDFException ex) {  
    ...  
}.  
}
```

4.2.28 CDFgetVersion

```
int CDFgetVersion( /* out -- Completion status code. */  
void* id, /* in -- CDF identifier. */  
TYPE version, /* out -- CDF version. */  
TYPE release, /* out -- CDF release. */  
TYPE increment); /* out -- CDF increment. */  
/* TYPE -- int* or "out int" */
```

CDFgetVersion returns the version/release information for a CDF file. This information reflects the CDF library that was used to create the CDF file.

The arguments to CDFgetVersion are defined as follows:

id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.

version	The CDF version number.
release	The CDF release number.
increment	The CDF increment number.

4.2.28.1. Example(s)

In the following example, a CDF's version/release is acquired.

```

.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  version;        /* CDF version. */
int  release;        /* CDF release */
int  increment;      /* CDF increment. */
.
.
try {
    ....
    status = CDFgetVersion (id, &version, &release, &increment);
    Or,
    status = CDFgetVersion (id, out version, out release, out increment);
    ...
} catch (CDFException ex) {
    ...
}.

```

4.2.29 CDFgetzMode

```

int CDFgetzMode(          /* out -- Completion status code. */
void* id,                /* in -- CDF identifier. */
TYPE zMode);           /* out -- CDF zMode. */
                        /* TYPE -- int* or "out int" */

```

CDFgetzMode returns the zMode for a CDF file. The zModes are described in Section 2.15.

The arguments to CDFgetzMode are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
zMode	The CDF zMode.

4.2.29.1. Example(s)

In the following example, a CDF's zMode is acquired.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  zMode;          /* CDF zMode. */
.
.
try {
    ....
    status = CDFgetzMode (id, &zMode);
    Or,
    status = CDFgetzMode (id, out zMode);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
.
```

4.2.30 CDFinquire

```
int CDFinquire(          /* out -- Completion status code. */
void* id,              /* in -- CDF identifier */
TYPE numDims,         /* out -- Number of dimensions, rVariables. */
TYPE2 dimSizes,      /* out -- Dimension sizes, rVariables. */
TYPE encoding,       /* out -- Data encoding. */
TYPE majority,       /* out -- Variable majority. */
TYPE maxRec,         /* out -- Maximum record number in the CDF, rVariables. */
TYPE numVars,        /* out -- Number of rVariables in the CDF. */
TYPE numAttrs);     /* out -- Number of attributes in the CDF. */
/* TYPE -- int* or "out int" */
/* TYPE2 -- int* or "out int[]" */
```

CDFinquire returns the basic characteristics of a CDF. An application needs to know the number of rVariable dimensions and their sizes before it can access rVariable data (since all rVariables' dimension and dimension size are the same). Knowing the variable majority can be used to optimize performance and is necessary to properly use the variable hyper functions (for both rVariables and zVariables).

The arguments to CDFinquire are defined as follows:

- | | |
|----------|---|
| id | The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen. |
| numDims | The number of dimensions for the rVariables in the CDF. |
| dimSizes | The dimension sizes of the rVariables in the CDF. dimSizes is a 1-dimensional array containing one element per dimension. Each element of dimSizes receives the |

corresponding dimension size. For 0-dimensional rVariables this argument is ignored (but must be present).

encoding	The encoding of the variable data and attribute entry data. The encodings are defined in Section 2.7.
majority	The majority of the variable data. The majorities are defined in Section 2.9.
maxRec	The maximum record number written to an rVariable in the CDF. Note that the maximum record number written is also kept separately for each rVariable in the CDF. The value of maxRec is the largest of these. Some rVariables may have fewer records actually written. Use CDFrVarMaxWrittenRecNum to inquire the maximum record written for an individual rVariable.
numVars	The number of rVariables in the CDF.
numAttrs	The number of attributes in the CDF.

4.2.30.1. Example(s)

The following example returns the basic information about a CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  numDims;        /* Number of dimensions, rVariables. */
int[] dimSizes;      /* Dimension sizes, rVariables (allocate to
allow the
                        allow the maximum # of dimensions). */
int  encoding;       /* Data encoding. */
int  majority;       /* Variable majority. */
int  maxRec;         /* Maximum record number, rVariables. */
int  numVars;        /* Number of rVariables in CDF. */
int  numAttrs;       /* Number of attributes in CDF. */
.
.
try {
    ....
    dimSizes = new int[CDF_MAX_DIMS];
    fixed (int* pdimSizes = dimSizes) {
        status = CDFinquire (id, &numDims, pdimSizes, &encoding, &majority,
                            &maxRec, &numVars, &numAttrs);
    }
    Or,
    status = CDFinquire (id, out numDims, out dimSizes, out encoding, out majority,
                        out maxRec, out numVars, out numAttrs);
.
} catch (CDFException ex) {
    ...
}.
.
```

4.2.31 CDFinquireCDF

```
int CDFinquireCDF(                                /* out -- Completion status code. */
void* id,                                         /* in -- CDF identifier */
TYPE numDims,                                    /* out -- Number of dimensions for rVariables. */
TYPE2 dimSizes,                                 /* out -- Dimension sizes for rVariables. */
TYPE encoding,                                  /* out -- Data encoding. */
TYPE majority,                                  /* out -- Variable majority. */
TYPE maxrRec,                                    /* out -- Maximum record number among rVariables in the CDF. */
TYPE numrVars,                                  /* out -- Number of rVariables in the CDF. */
TYPE maxzRec,                                    /* out -- Maximum record number among zVariables in the CDF. */
TYPE numzVars,                                  /* out -- Number of zVariables in the CDF. */
TYPE numAttrs);                                /* out -- Number of attributes in the CDF. */
                                                /* TYPE -- int* or "out int" */
                                                /* TYPE2 -- int* or "out int[]" */
```

CDFinquireCDF returns the basic characteristics of a CDF. This method expands the method CDFinquire by acquiring extra information regarding the zVariables. Knowing the variable majority can be used to optimize performance and is necessary to properly use the variable hyper-get/put functions.

The arguments to CDFinquireCDF are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
numDims	The number of dimensions for the rVariables in the CDF. Note that all the rVariables' dimensionality in the same CDF file must be the same.
dimSizes	The dimension sizes of the rVariables in the CDF (note that all the rVariables' dimension sizes in the same CDF file must be the same). dimSizes is a 1-dimensional array containing one element per dimension. Each element of dimSizes receives the corresponding dimension size. For 0-dimensional rVariables this argument is ignored (but must be present).
encoding	The encoding of the variable data and attribute entry data. The encodings are defined in Section 2.7.
majority	The majority of the variable data. The majorities are defined in Section 2.9.
maxrRec	The maximum record number written to an rVariable in the CDF. Note that the maximum record number written is also kept separately for each rVariable in the CDF. The value of maxRec is the largest of these.
numrVars	The number of rVariables in the CDF.
maxzRec	The maximum record number written to a zVariable in the CDF. Note that the maximum record number written is also kept separately for each zVariable in the CDF. The value of maxRec is the largest of these. Some zVariables may have fewer records than actually written. Use CDFgetzVarMaxWrittenRecNum to inquire the actual number of records written for an individual zVariable.

numzVars	The number of zVariables in the CDF.
numAttr	The number of attributes in the CDF.

4.2.31.1. Example(s)

The following example returns the basic information about a CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  numDims;        /* Number of dimensions, rVariables. */
int[] dimSizes;      /* Dimension sizes, rVariables (allocate to
                    /* allow the maximum # of dimensions). */

int  encoding;       /* Data encoding. */
int  majority;      /* Variable majority. */
int  maxrRec;       /* Maximum record number, rVariables. */
int  numrVars;     /* Number of rVariables in CDF. */
int  maxzRec;      /* Maximum record number, zVariables. */
int  numzVars;     /* Number of zVariables in CDF. */
int  numAttr;     /* Number of attributes in CDF. */
.
.
try {
    dimSizes = new int[CDF_MAX_DIMS];
    fixed (int* pdimSizes = dimSizes) {
        status = CDFInquireCDF (id, &numDims, pdimSizes, &encoding, &majority,
                                &maxrRec, &numrVars, &maxzRec, &numzVars, &numAttr);
    }
}
Or,
    status = CDFInquireCDF (id, out numDims, out dimSizes, out encoding, out majority,
                            out maxrRec, out numrVars, out maxzRec, out numzVars, out numAttr);
...
...
} catch (CDFException ex) {
    ...
}.

```

4.2.32 CDFopen

```

int CDFopen(          /* out -- Completion status code. */
string CDFname,     /* in -- CDF file name. */
void* *id);        /* out -- CDF identifier. */

```

CDFopen, a legacy CDF function, opens an existing CDF. The CDF is initially opened with only read access. This allows multiple applications to read the same CDF simultaneously. When an attempt to modify the CDF is made, it is

automatically closed and reopened with read/write access. (The method will fail if the application does not have or cannot get write access to the CDF.)

The arguments to CDFopen are defined as follows:

CDFname	The file name of the CDF to open. (Do not specify an extension.) This may be at most CDF_PATHNAME_LEN characters. A CDF file name may contain disk and directory specifications that conform to the conventions of the operating system being used (including logical names on OpenVMS systems and environment variables on UNIX systems).
	UNIX: File names are case-sensitive.
id	The identifier for the opened CDF. This identifier must be used in all subsequent operations on the CDF.

NOTE: CDFclose must be used to close the CDF before your application exits to ensure that the CDF will be correctly written to disk.

4.2.32.1. Example(s)

The following example will open a CDF named "NOAA1.cdf".

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
string  CDFname = "NOAA1"; /* file name of CDF. */
.
.
try {
    status = CDFopen (CDFname, &id);
.
} catch (CDFException ex) {
    ...
}.
.
```

4.2.33 CDFopenCDF

```
int CDFopenCDF(          /* out -- Completion status code. */
string CDFname,        /* in -- CDF file name. */
void* *id);           /* out -- CDF identifier. */
```

CDFopenCDF opens an existing CDF. This method is identical to CDFopen, and the use of this method is strongly encouraged over CDFopen as it might not be supported in the future. The CDF is initially opened with only read access. This allows multiple applications to read the same CDF simultaneously. When an attempt to modify the CDF is made, it is automatically closed and reopened with read/write access. The method will fail if the application does not have or cannot get write access to the CDF.

The arguments to CDFopenCDF are defined as follows:

CDFname The file name of the CDF to open. (Do not specify an extension.) This may be at most CDF_PATHNAME_LEN characters. A CDF file name may contain disk and directory specifications that conform to the conventions of the operating system being used (including logical names on OpenVMS systems and environment variables on UNIX systems).

UNIX: File names are case-sensitive.

id The identifier for the opened CDF. This identifier must be used in all subsequent operations on the CDF.

NOTE: CDFcloseCDF must be used to close the CDF before your application exits to ensure that the CDF will be correctly written to disk.

4.2.33.1. Example(s)

The following example will open a CDF named "NOAA1.cdf".

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
string    CDFname = "NOAA1"; /* file name of CDF. */
.
.
try {
    ....
    status = CDFopenCDF (CDFname, &id);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
.
```

4.2.34 CDFselect

```
int CDFselect(          /* out -- Completion status code. */
void* id);             /* in -- CDF identifier. */
```

CDFselect selects an opened CDF as the current CDF. Only one CDF is allowed to be current. To access data from a CDF, that CDF must be selected as the current. This method is no longer needed as the methods involved CDF operations always need the CDF identifier, as the first argument, so it can be set as current before other operations can be applied.

The arguments to CDFselect are defined as follows:

id The identifier for the opened CDF. This identifier must be used in all subsequent operations on the CDF.

NOTE: When a CDF is opened, it becomes the current. No CDF is current after CDFcloseCDF is called to close the file.

4.2.34.1. Example(s)

The following example will select a CDF named “NOAA1.cdf” as the current CDF while another file “NOAA2.cdf” is also opened.

```
.  
. .  
. .  
void*      id1, id2;          /* CDF identifier. */  
int  status;                 /* Returned status code. */  
string  CDFname1 = "NOAA1"; /* file name of CDF. */  
string  CDFname2 = "NOAA2"; /* file name of CDF. */  
. .  
try {  
    ....  
    status = CDFopenCDF (CDFname1, &id1);  
  
    status = CDFopenCDF (CDFname2, &id2);  
  
    status = CDFselect(id1);  
    ....  
    status = CDFclose(id1);  
    status = CDFclose(id2);  
} catch (CDFException ex) {  
    ...  
}...
```

4.2.35 CDFselectCDF

```
int CDFselectCDF(          /* out -- Completion status code. */  
void* id);                /* in -- CDF identifier. */
```

CDFselectCDF selects an opened CDF as the current CDF. Only one CDF is allowed to be current. To access data from a CDF, that CDF must be selected as the current. This method is no longer needed as the methods involved CDF operations always need the CDF identifier, as the first argument, so it can be set as current before other operations can be applied. This method is identical to CDFselect.

The arguments to CDFselectCDF are defined as follows:

id The identifier for the opened CDF. This identifier must be used in all subsequent operations on the CDF.

NOTE: When a CDF is opened, it becomes the current. No CDF is current after CDFcloseCDF is called to close the file.

4.2.35.1. Example(s)

The following example will select a CDF named “NOAA1.cdf” as the current CDF while another file “NOAA2.cdf” is also opened.

```
.
.
.
void*      id1, id2;          /* CDF identifier. */
int  status;                /* Returned status code. */
string    CDFname1 = "NOAA1"; /* file name of CDF. */
string    CDFname2 = "NOAA2"; /* file name of CDF. */
.
try {
    ....
    status = CDFopenCDF (CDFname1, &id1);

    status = CDFopenCDF (CDFname2, &id2);

    status = CDFselectCDF(id1);
    ....
    status = CDFclose(id1);
    status = CDFclose(id2);
} catch (CDFException ex) {
    ...
}...
```

4.2.36 CDFsetCacheSize

```
int CDFsetCacheSize (          /* out -- Completion status code. */
void* id,                    /* in -- CDF identifier. */
int numBuffers);             /* in -- CDF's cache buffers. */
```

CDFsetCacheSize specifies the number of cache buffers being used for the dotCDF file when a CDF is open. Refer to the CDF User’s Guide for the description of the cache scheme used by the CDF library.

The arguments to CDFsetCacheSize are defined as follows:

id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.

numBuffers The number of cache buffers.

4.2.36.1. Example(s)

The following example extends the number of cache buffers to 500 for the open CDF file. The default number is 300 for a single-file format CDF on Unix systems.

```
.
```



```

.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  cacheBuffers;    /* CDF's cache buffers. */
.
.
cacheBuffers = 500;
try {
    ....
    status = CDFsetCacheSize (id, cacheBuffers);
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.2.37 CDFsetChecksum

```

int CDFsetChecksum (          /* out -- Completion status code. */
void* id,                   /* in -- CDF identifier. */
int checksum);              /* in -- CDF's checksum mode. */

```

CDFsetChecksum specifies the checksum mode for the CDF. The CDF checksum mode is described in Section 2.20.

The arguments to CDFsetChecksum are defined as follows:

- id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
- checksum The checksum mode (NO_CHECKSUM or MD5_CHECKSUM).

4.2.37.1. Example(s)

The following example turns off the checksum flag for the open CDF file..

```

.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  checksum;        /* CDF's checksum. */
.
.
checksum= NO_CHECKSUM;
try {
    ....
    status = CDFsetChecksum (id, checksum);
    ...
    ...
}

```

```

} catch (CDFException ex) {
    ...
}.

```

4.2.38 CDFsetCompression

```

int CDFsetCompression (
void* id,
int compressionType,
TYPE compressionParms);

```

/ out -- Completion status code. */*
/ in -- CDF identifier. */*
/ in -- CDF's compression type. */*
/ in -- CDF's compression parameters. */*
/ **TYPE** -- int* or int[] */*

CDFsetCompression specifies the compression type and parameters for a CDF. This compression refers to the CDF, not of any variables. The compressions are described in Section 2.11.

The arguments to CDFsetCompression are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
compressionType	The compression type .
compressionParms	The compression parameters.

4.2.38.1. Example(s)

The following example uses GZIP.6 to compress the CDF file.

```

.
.
.
void*      id;
int  status;
int  compressionType;
int[] compressionParms = new int[1]

```

/ CDF identifier. */*
/ Returned status code. */*
/ CDF's compression type. */*
/ CDF's compression parameters. */*

```

.
.
compressionType = GZIP_COMPRESSION;
compressionParms[0] = 6;
try {
    ....
    fixed(int* pcompressionParms = compressionParms) {
        status = CDFsetCompression (id, compressionType, pcompressionParms);
    }
}
Or,
status = CDFsetCompression (id, compressionType, compressionParms); ...
...
} catch (CDFException ex) {
    ...
}.

```

4.2.39 CDFsetCompressionCacheSize

```
int CDFsetCompressionCacheSize (          /* out -- Completion status code. */
void* id,                                /* in -- CDF identifier. */
int compressionNumBuffers);              /* in -- CDF's compressed cache buffers. */
```

CDFsetCompressionCacheSize specifies the number of cache buffers used for the compression scratch CDF file. Refer to the CDF User's Guide for the description of the cache scheme used by the CDF library.

The arguments to CDFsetCompressionCacheSize are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
compressionNumBuffers	The number of cache buffers.

4.2.39.1. Example(s)

The following example extends the number of cache buffers used for the scratch file from the compressed CDF file to 100. The default cache buffers is 80 for Unix systems.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  compressionNumBuffers; /* CDF's compression cache buffers. */
.
.
compressionNumBuffers = 100;
try {
    ....
    status = CDFsetCompressionCacheSize (id, compressionNumBuffers);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
}
```

4.2.40 CDFsetDecoding

```
int CDFsetDecoding (          /* out -- Completion status code. */
void* id,                    /* in -- CDF identifier. */
int decoding);                /* in -- CDF decoding. */
```

CDFsetDecoding sets the decoding of a CDF. The decodings are described in Section 2.8.

The arguments to CDFsetDecoding are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
decoding	The decoding of a CDF.

4.2.40.1. Example(s)

The following example sets NETWORK_DECODING to be the decoding scheme in the CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  decoding;        /* Decoding. */
.
.
decoding = NETWORK_DECODING;
try {
    ....
    status = CDFsetDecoding (id, decoding);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
.
```

4.2.41 CDFsetEncoding

```
int CDFsetEncoding (          /* out -- Completion status code. */
void* id,                   /* in -- CDF identifier. */
int encoding);              /* in -- CDF encoding. */
```

CDFsetEncoding specifies the data encoding of the CDF. A CDF's encoding may not be changed after any variable values have been written. The encodings are described in Section 2.7.

The arguments to CDFsetEncoding are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
encoding	The encoding of the CDF.

4.2.41.1. Example(s)

The following example sets the encoding to HOST_ENCODING for the CDF.

```
.  
. .  
. .  
void*      id;          /* CDF identifier. */  
int  status;          /* Returned status code. */  
int  encoding;        /* Encoding. */  
. .  
encoding = HOST_ENCODING;  
try {  
    status = CDFsetEncoding(id, encoding);  
    ...  
    ...  
} catch (CDFException ex) {  
    ...  
}.  
}
```

4.2.42 CDFsetFileBackward

```
void CDFsetFileBackward(  
int mode)                /* in -- File backward Mode. */
```

CDFsetFileBackward sets the backward mode. When the mode is set as BACKWARDFILEon, any new CDF files created are of version 2.7, instead of the underlining library version. If mode BACKWARDFILEoff is used, the default for creating new CDF files, the library version is the version of the file.

The arguments to CDFsetFileBackward are defined as follows:

mode	The backward mode.
------	--------------------

4.2.42.1. Example(s)

In the following example, it sets the file backward mode to BACKWARDFILEoff, which means that any files to be created will be of version V3.*, the same as the library version.

```
.  
. .  
. .  
void*      id;          /* CDF identifier. */  
int  status;          /* Returned status code. */  
. .  
try {
```

```

.....
CDFsetFileBackward (BACKWARDFILEoff);
...
...
} catch (CDFException ex) {
...
}.
.

```

4.2.43 CDFsetFormat

```

int CDFsetFormat (                               /* out -- Completion status code. */
void* id,                                       /* in -- CDF identifier. */
int format);                                   /* in -- CDF format. */

```

CDFsetFormat specifies the file format, either single or multi-file format, of the CDF. A CDF's format may not be changed after any variable values have been written. The formats are described in Section 2.5.

The arguments to CDFsetFormat are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
format	The file format of the CDF.

4.2.43.1. Example(s)

The following example sets the file format to MULTI_FILE for the CDF. The default is SINGLE_FILE format.

```

.
.
.
void*      id;                                /* CDF identifier. */
int  status;                                  /* Returned status code. */
int  format;                                  /* Format. */
.
.
format = MULTI_FILE;
try {
.....
    status = CDFsetFormat(id, format);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
.

```

4.2.44 CDFsetLeapSecondLastUpdated

```
int CDFsetLeapSecondLastUpdated (          /* out -- Completion status code. */
void* id,                                  /* in -- CDF identifier. */
int lastUpdated);                          /* in -- CDF format. */
```

CDFsetLeapSecondLastUpdated respecifies the date that the leap second was last updated in the CDF. The date, in YYYYMMDD form, has to be either a valid entry in the currently used leap second table, or zero (0). This function is called usually for older CDFs that have not had that information set. This field is onlt relevant to TT2000 data in a CDF.

The arguments to CDFsetLeapSecondLastUpdated are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
lastUpdated	The leap second last updated date.

4.2.44.1. Example(s)

The following example resets the the leap second last updated date to 20150701 in the CDF. The field might not be set (an older CDF).

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  lastUpdated;     /* The last date the leap second was updated. */
.
.
lastUpdated = 20150701;
try {
    ....
    status = CDFsetLeapSecondLastUpdated (id, lastUpdated);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
}
```

4.2.45 CDFsetMajority

```
int CDFsetMajority (          /* out -- Completion status code. */
void* id,                    /* in -- CDF identifier. */
int majority);               /* in -- CDF variable majority. */
```

CDFsetMajority specifies the variable majority, either row or column-major, of the CDF. A CDF's majority may not be changed after any variable values have been written. The majorities are described in Section 2.9.

The arguments to CDFsetMajority are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
majority	The variable majority of the CDF.

4.2.45.1. Example(s)

The following example sets the majority to COLUMN_MAJOR for the CDF. The default is ROW_MAJOR.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  majority;        /* Majority. */
.
.
majority = COLUMN_MAJOR;
try {
    ....
    status = CDFsetMajority (id, majority);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
.
```

4.2.46 CDFsetNegtoPosfp0Mode

```
int CDFsetNegtoPosfp0Mode (          /* out -- Completion status code. */
void* id,                          /* in -- CDF identifier. */
int negtoPosfp0);                  /* in -- -0.0 to 0.0 mode. */
```

CDFsetNegtoPosfp0Mode specifies the -0.0 to 0.0 mode of the CDF. The -0.0 to 0.0 modes are described in Section 2.16.

The arguments to CDFsetNegtoPosfp0Mode are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
negtoPosfp0	The -0.0 to 0.0 mode of the CDF.

4.2.46.1. Example(s)

The following example sets the -0.0 to 0.0 mode to ON for the CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  negtoPosfp0;     /* -0.0 to 0.0 mode. */
.
.
negtoPosfp0 = NEGtoPOSfp0on;
try {
    ....
    status = CDFsetNegtoPosfp0Mode (id, negtoPosfp0);
    ...
} catch (CDFException ex) {
    ...
}.
```

4.2.47 CDFsetReadOnlyMode

```
int CDFsetReadOnlyMode(          /* out -- Completion status code. */
void* id,                       /* in -- CDF identifier. */
int readOnlyMode);             /* in -- CDF read-only mode. */
```

CDFsetReadOnlyMode specifies the read-only mode for a CDF. The read-only modes are described in Section 2.14.

The arguments to CDFsetReadOnlyMode are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
readOnlyMode	The read-only mode.

4.2.47.1. Example(s)

The following example sets the read-only mode to OFF for the CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  readMode;        /* CDF read-only mode. */
.
.
readMode = READONLYoff;
try {
    ....
    status = CDFsetReadOnlyMode (id, readMode);
    ...
}.
```

```

...
} catch (CDFException ex) {
...
}.

```

4.2.48 CDFsetStageCacheSize

```

int CDFsetStageCacheSize(          /* out -- Completion status code. */
void* id,                          /* in -- CDF identifier. */
int numBuffers);                  /* in -- The stage cache size. */

```

CDFsetStageCacheSize specifies the number of cache buffers being used for the staging scratch file a CDF. Refer to the CDF User's Guide for the description of the caching scheme used by the CDF library.

The arguments to CDFsetStageCacheSize are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
numBuffers	The number of cache buffers.

4.2.48.1. Example(s)

The following example sets the number of stage cache buffers to 10 for a CDF.

```

.
.
.
void*      id;                      /* CDF identifier. */
int  numBuffers;                    /* The number of cache buffers. */
.
.
numBuffers = 10;
try {
....
  status = CDFsetStageCacheSize (id, numBuffers);
  ...
  ...
} catch (CDFException ex) {
  ...
}.

```

4.2.49 CDFsetValidate

```
void CDFsetValidate(  
int mode); /* in -- File Validation Mode. */
```

CDFsetValidate sets the data validation mode. The validation mode dedicates whether certain data in an open CDF file will be validated. This mode should be set before the any files are opened. Refer to Data Validation Section 2.21.

The arguments to CDFgetVersion are defined as follows:

mode	The validation mode.
------	----------------------

4.2.49.1. Example(s)

In the following example, it sets the validation mode to be on, so any following CDF files are subjected to the data validation process when they are open.

```
.  
. .  
. .  
try {  
    ....  
    CDFsetValidate (VALIDATEFILEon);  
    ...  
} catch (CDFException ex) {  
    ...  
}
```

4.2.50 CDFsetzMode

```
int CDFsetzMode( /* out -- Completion status code. */  
void* id, /* in -- CDF identifier. */  
int zMode); /* in -- CDF zMode. */
```

CDFsetzMode specifies the zMode for a CDF file. The zModes are described in Section 2.15 and see the Concepts chapter in the CDF User's Guide for a more detailed information on zModes. zMode is used when dealing with a CDF file that contains 1) rVariables, or 2) rVariables and zVariables. If you want to treat rVariables as zVariables, it's highly recommended to set the value of zMode to zMODEon2.

The arguments to CDFsetzMode are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
zMode	The CDF zMode.

4.2.50.1. Example(s)

In the following example, a CDF's zMode is specified to zMODEon2: all rVariables are treated as zVariables with NOVARY dimensions being eliminated.

```

.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  zMode;          /* CDF zMode. */
.
.
zMode = zMODEon2;
try {
    ....
    status = CDFsetzMode (id, zMode);
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3 Variables

The methods in this section are all CDF variable-specific. A variable, either a rVariable or zVariable, is identified by its unique name in a CDF or a variable number. Before you can perform any operation on a variable, the CDF in which it resides in must be opened.

4.3.1 CDFcloserVar

```

int CDFcloserVar(          /* out -- Completion status code. */
void* id,                 /* in -- CDF identifier. */
int varNum)              /* in -- rVariable number. */

```

CDFcloserVar closes the specified rVariable file from a multi-file format CDF. Note that rVariables in a single-file CDF don't need to be closed. The variable's cache buffers are flushed before the variable's open file is closed. However, the CDF file is still open.

NOTE: For the multi-file CDF, you must close all open variable files to guarantee that all modifications you have made will actually be written to the CDF's file(s). If your program exits, normally or otherwise, without a successful call to CDFcloseCDF, the CDF's cache buffers are left unflushed.

The arguments to CDFcloserVar are defined as follows:

- id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
- varNum The variable number for the open rVariable's file. This identifier must have been initialized by a call to CDFcreaterVar or CDFgetVarNum.

4.3.1.1. Example(s)

The following example will close an open rVariable file from a multi-file CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  varNum;         /* rVariable number. */
.
.
try {
    ....
    varNum = CDFgetVarNum (id, "VAR_NAME1");
    .
    status = CDFcloserVar (id, varNum);
    ...
} catch (CDFException ex) {
    ...
}.
.
```

4.3.2 CDFclosezVar

```
int CDFclosezVar(      /* out -- Completion status code. */
void* id,             /* in -- CDF identifier. */
int varNum)           /* in -- zVariable number. */
```

CDFclosezVar closes the specified zVariable file from a multi-file format CDF. Note that zVariables in a single-file CDF don't need to be closed. The variable's cache buffers are flushed before the variable's open file is closed. However, the CDF file is still open.

NOTE: For the multi-file CDF, you must close all open variable files to guarantee that all modifications you have made will actually be written to the CDF's file(s). If your program exits, normally or otherwise, without a successful call to CDFcloseCDF, the CDF's cache buffers are left unflushed.

The arguments to CDFclosezVar are defined as follows:

- id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.

- varNum The variable number for the open zVariable's file. This identifier must have been initialized by a call to CDFcreatezVar or CDFgetVarNum.

4.3.2.1. Example(s)

The following example will close an open zVariable file from a multi-file CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  varNum;         /* zVariable number. */
.
.
try {
    ....
    varNum = CDFgetVarNum (id, "VAR_NAME1");
    .
    status = CDFclosezVar (id, varNum);
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.3 CDFconfirmrVarExistence

```

int CDFconfirmrVarExistence(          /* out -- Completion status code. */
void* id,                            /* in -- CDF identifier. */
string varName);                    /* in -- rVariable name. */

```

CDFconfirmrVarExistence confirms the existence of a rVariable with a given name in a CDF. If the rVariable does not exist, an error code will be returned. No exception is thrown if the variable is not found.

The arguments to CDFconfirmrEntryExistence are defined as follows:

- id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
- varName The rVariable name to check.

4.3.3.1. Example(s)

The following example checks the existence of rVariable "MY_VAR" in a CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
.
.
try {
    ....
    status = CDFconfirmrVarExistence (id, "MY_VAR");
    if (status != CDF_OK) UserStatusHandler (status);
    ...
}

```

```

...
} catch (CDFException ex) {
...
}.

```

4.3.4 CDFconfirmrVarPadValueExistence

```

int CDFconfirmrVarPadValueExistence(          /* out -- Completion status code. */
void* id,                                    /* in -- CDF identifier. */
int varNum)                                  /* in -- rVariable number. */

```

CDFconfirmrVarPadValueExistence confirms the existence of an explicitly specified pad value for the specified rVariable in a CDF. If an explicit pad value has not been specified, the informational status code NO_PADVALUE_SPECIFIED will be returned. No exception is thrown if the variable's pad value is not defined.

The arguments to CDFconfirmrVarPadValueExistence are defined as follows:

- id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
- varNum The rVariable number.

4.3.4.1. Example(s)

The following example checks the existence of the pad value of rVariable "MY_VAR" in a CDF.

```

.
.
.
void*      id;                                /* CDF identifier. */
int  status;                                  /* Returned status code. */
int  varNum;                                  /* rVariable number. */
.
.
try {
....
varNum = CDFgetVarNum(id, "MY_VAR");
status = CDFconfirmrVarPadValueExistence (id, varNum);
if (status != NO_PADVALUE_SPECIFIED) {
.
}
...
...
} catch (CDFException ex) {
...
}.

```

4.3.5 CDFconfirmzVarExistence

```
int CDFconfirmzVarExistence(          /* out -- Completion status code. */
void* id,                            /* in -- CDF identifier. */
string varName);                    /* in -- zVariable name. */
```

CDFconfirmzVarExistence confirms the existence of a zVariable with a given name in a CDF. If the zVariable does not exist, an error code will be returned. No exception is thrown if the variable is not found.

The arguments to CDFconfirmEntryExistence are defined as follows:

id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.

varName The zVariable name to check.

4.3.5.1. Example(s)

The following example checks the existence of zVariable “MY_VAR” in a CDF.

```
.
.
.
void*        id;                    /* CDF identifier. */
int    status;                    /* Returned status code. */
.
.
try {
....
  status = CDFconfirmzVarExistence (id, “MY_VAR”);
  if (status != CDF_OK) UserStatusHandler (status);
...
...
} catch (CDFException ex) {
...
}.
.
```

4.3.6 CDFconfirmzVarPadValueExistence

```
int CDFconfirmzVarPadValueExistence( /* out -- Completion status code. */
void* id,                            /* in -- CDF identifier. */
int varNum)                          /* in -- zVariable number. */
```

CDFconfirmzVarPadValueExistence confirms the existence of an explicitly specified pad value for the specified zVariable in a CDF. If an explicit pad value has not been specified, the informational status code NO_PADVALUE_SPECIFIED will be returned. No exception is thrown if the variable’s pad value is not defined.

The arguments to CDFconfirmzVarPadValueExistence are defined as follows:

id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.

varNum The zVariable number.

4.3.6.1. Example(s)

The following example checks the existence of the pad value of zVariable “MY_VAR” in a CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  varNum;         /* zVariable number. */
.
.
try {
    ....
    varNum = CDFgetVarNum(id, "MY_VAR");
    status = CDFconfirmzVarPadValueExistence (id, varNum);
    if (status != NO_PADVALUE_SPECIFIED) {
.
    }
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.7 CDFcreatorVar

```

int CDFcreatorVar(          /* out -- Completion status code. */
void* id,                  /* in -- CDF identifier. */
string varName,           /* in -- rVariable name. */
int dataType,            /* in -- Data type. */
int numElements,        /* in -- Number of elements (of the data type). */
int recVariance,        /* in -- Record variance. */
int[] dimVariances,     /* in -- Dimension variances. */
TYPE varNum);          /* out -- rVariable number. */
                          /* TYPE -- int* or "out int" */

```

CDFcreatorVar is used to create a new rVariable in a CDF. A variable (rVariable or rVariable) with the same name must not already exist in the CDF.

The arguments to CDFcreatorVar are defined as follows:

id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.


```

Or,
status = CDFcreatorVar (id, "EPOCH", CDF_EPOCH, 1, EPOCHrecVary,
                       EPOCHdimVarys, out EPOCHvarNum);
status = CDFcreatorVar (id, "LATITUDE", CDF_INT2, 1, LATrecVary, LATdimVarys,
                       out LATvarNum);
status = CDFcreatorVar (id, "INTITUDE", CDF_INT2, 1, LONrecVary, LONdimVarys,
                       out LONvarNum);
status = CDFcreatorVar (id, "TEMPERATURE", CDF_REAL4, 1, TMPrecVary,
                       TMPdimVarys, out TMPvarNum);

.
} catch (CDFException ex) {
    ...
}.

```

4.3.8 CDFcreatezVar

```

int CDFcreatezVar(                                     /* out -- Completion status code. */
void* id,                                           /* in -- CDF identifier. */
string varName,                                     /* in -- zVariable name. */
int dataType,                                       /* in -- Data type. */
int numElements,                                    /* in -- Number of elements (of the data type). */
int numDims,                                        /* in -- Number of dimensions. */
int[] dimSizes,                                    /* in -- Dimension sizes */
int recVariance,                                    /* in -- Record variance. */
int[] dimVariances,                                /* in -- Dimension variances. */
TYPE varNum);                                     /* out -- zVariable number. */
                                                    /* TYPE -- int* or "out int" */

```

CDFcreatezVar is used to create a new zVariable in a CDF. A variable (rVariable or zVariable) with the same name must not already exist in the CDF.

The arguments to CDFcreatezVar are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varName	The name of the zVariable to create. This may be at most CDF_VAR_NAME_LEN256 characters. Variable names are case-sensitive.
dataType	The data type of the new zVariable. Specify one of the data types defined in Section 2.6.
numElements	The number of elements of the data type at each value. For character data types (CDF_CHAR and CDF_UCHAR), this is the number of characters in the string (each value consists of the entire string). For all other data types this must always be one (1) - multiple elements at each value are not allowed for non-character data types.
numDims	Number of dimensions the zVariable. This may be as few as zero (0) and at most CDF_MAX_DIMS.

dimSizes	The size of each dimension. Each element of dimSizes specifies the corresponding dimension size. Each size must be greater than zero (0). For 0-dimensional zVariables this argument is ignored (but must be present).
recVariance	The zVariable's record variance. Specify one of the variances defined in Section 2.10.
dimVariances	The zVariable's dimension variances. Each element of dimVariances specifies the corresponding dimension variance. For each dimension specify one of the variances defined in Section 2.10. For 0-dimensional zVariables this argument is ignored (but must be present).
varNum	The number assigned to the new zVariable. This number must be used in subsequent CDF function calls when referring to this zVariable. An existing zVariable's number may be determined with the CDFgetVarNum function.

4.3.8.1. Example(s)

The following example will create several zVariables in a CDF. In this case EPOCH is a 0-dimensional, LAT and LON are 2-dimensional, and TMP is a 1-dimensional.

```

.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  EPOCHrecVary = VARY; /* EPOCH record variance. */
int  LATrecVary = NOVARY; /* LAT record variance. */
int  LONrecVary = NOVARY; /* LON record variance. */
int  TMPrecVary = VARY; /* TMP record variance. */
int[] EPOCHdimVarys = new int[] {NOVARY}; /* EPOCH dimension variances. */
int[] LATdimVarys = new int[] {VARY,VARY}; /* LAT dimension variances. */
int[] LONdimVarys = new int[] {VARY,VARY}; /* LON dimension variances. */
int[] TMPdimVarys = new int[] {VARY,VARY}; /* TMP dimension variances. */
int  EPOCHvarNum; /* EPOCH zVariable number. */
int  LATvarNum; /* LAT zVariable number. */
int  LONvarNum; /* LON zVariable number. */
int  TMPvarNum; /* TMP zVariable number. */
int[] EPOCHdimSizes = new int[] {3}; /* EPOCH dimension sizes. */
int[] LATLONdimSizes = new int[] {2,3} /* LAT/LON dimension sizes. */
int[] TMPdimSizes = new int[] {3}; /* TMP dimension sizes. */
.
.
try {
    status = CDFcreatezVar (id, "EPOCH", CDF_EPOCH, 1, 0, EPOCHdimSizes, EPOCHrecVary,
                           EPOCHdimVarys, &EPOCHvarNum);
    status = CDFcreatezVar (id, "LATITUDE", CDF_INT2, 1, 2, LATLONdimSizes, LATrecVary, LATdimVarys,
                           &LATvarNum);
    status = CDFcreatezVar (id, "INTITUDE", CDF_INT2, 1, 2, LATLONdimSizes, LONrecVary, LONdimVarys,
                           &LONvarNum);
    status = CDFcreatezVar (id, "TEMPERATURE", CDF_REAL4, 1, 1, TMPdimSizes, TMPrecVary,
                           TMPdimVarys, &TMPvarNum);
}

```

Or,

```

status = CDFcreatezVar (id, "EPOCH", CDF_EPOCH, 1, 0, EPOCHdimSizes, EPOCHrecVary,
                       EPOCHdimVarys, out EPOCHvarNum);
status = CDFcreatezVar (id, "LATITUDE", CDF_INT2, 1, 2, LATLONdimSizes, LATrecVary, LATdimVarys,
                       out LATvarNum);
status = CDFcreatezVar (id, "INTITUDE", CDF_INT2, 1, 2, LATLONdimSizes, LONrecVary, LONdimVarys,
                       out LONvarNum);
status = CDFcreatezVar (id, "TEMPERATURE", CDF_REAL4, 1, 1, TMPdimSizes, TMPrecVary,
                       TMPdimVarys, out TMPvarNum);

.
} catch (CDFException ex) {
  ...
}.

```

4.3.9 CDFdeleterVar

```

int CDFdeleterVar(                               /* out -- Completion status code. */
void* id,                                       /* in -- CDF identifier. */
int varNum);                                    /* in -- rVariable identifier. */

```

CDFdeleterVar deletes the specified rVariable from a CDF.

The arguments to CDFdeleterVar are defined as follows:

id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.

varNum The rVariable number to be deleted.

4.3.9.1. Example(s)

The following example deletes the rVariable named MY_VAR in a CDF.

```

.
.
.
void*        id;                               /* CDF identifier. */
int status;  /* Returned status code. */
int varNum;  /* rVariable number. */
.
.
try {
  ....
  varNum = CDFgetVarNum (id, "MY_VAR");
  status = CDFdeleterVar (id, varNum);
  ...
  ...
} catch (CDFException ex) {
  ...

```

```
    }.
```

4.3.10 CDFdeleterVarRecords

```
int CDFdeleterVarRecords(          /* out -- Completion status code. */  
void* id,                          /* in -- CDF identifier. */  
int varNum,                        /* in -- rVariable identifier. */  
int startRec,                      /* in -- Starting record number. */  
int endRec);                       /* in -- Ending record number. */
```

CDFdeleterVarRecords deletes a range of data records from the specified rVariable in a CDF.

The arguments to CDFdeleterVarRecords are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The identifier of the rVariable.
startRec	The starting record number to delete.
endRec	The ending record number to delete.

4.3.10.1. Example(s)

The following example deletes 11 records (from record numbered 11 to 21) from the rVariable “MY_VAR” in a CDF. Note: The first record is numbered as 0.

```
.  
. .  
. .  
void*      id;          /* CDF identifier. */  
int  status;          /* Returned status code. */  
int  varNum;          /* rVariable number. */  
int  startRec;        /* Starting record number. */  
int  endRec;          /* Ending record number. */  
. .  
try {  
    ....  
    varNum = CDFgetVarNum (id, “MY_VAR”);  
    startRec = 10;  
    endRec = 20;  
    status = CDFdeleterVarRecords (id, varNum, startRec, endRec);  
    ...  
    ...  
} catch (CDFException ex) {  
    ...  
}. .
```


CDFdeletezVarRecords deletes a range of data records from the specified zVariable in a CDF. If this is a variable with sparse records, the remaining records after deletion will not be renumbered.⁹

The arguments to CDFdeletezVarRecords are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The identifier of the zVariable.
startRec	The starting record number to delete.
endRec	The ending record number to delete.

4.3.12.1. Example(s)

The following example deletes 11 records (from record numbered 11 to 21) from the zVariable “MY_VAR” in a CDF. Note: The first record is numbered as 0.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  varNum;         /* zVariable number. */
int  startRec;       /* Starting record number. */
int  endRec;        /* Ending record number. */
.
.
try {
    ....
    varNum = CDFgetVarNum (id, "MY_VAR");
    startRec = 10;
    endRec = 20;
    status = CDFdeletezVarRecords (id, varNum, startRec, endRec);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
.
```

4.3.13 CDFdeletezVarRecordsRenumber

```
int CDFdeletezVarRecordsRenumber(          /* out -- Completion status code. */
void* id,                                /* in -- CDF identifier. */
int varNum,                              /* in -- zVariable identifier. */
int startRec,                            /* in -- Starting record number. */
```

⁹ Normal variables without sparse records have contiguous physical records. Once a section of the records get deleted, the remaining ones automatically fill the gap.


```
int endRec);                                /* in -- Ending record number. */
```

CDFdeletezVarRecordsRenumber deletes a range of data records from the specified zVariable in a CDF. If this is a variable with sparse records, the remaining records after deletion will be renumbered, just like non-sparse variable's records.

The arguments to CDFdeletezVarRecordsRenumber are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The identifier of the zVariable.
startRec	The starting record number to delete.
endRec	The ending record number to delete.

4.3.13.1. Example(s)

The following example deletes 11 records (from record numbered 11 to 21) from the zVariable "MY_VAR" in a CDF. Note: The first record is numbered as 0. If the last record number is 100, then after the deletion, the record will be 89.

```
.
.
.
void*      id;                                /* CDF identifier. */
int  status;                                /* Returned status code. */
int  varNum;                                /* zVariable number. */
int  startRec;                              /* Starting record number. */
int  endRec;                                /* Ending record number. */
.
.
try {
    ....
    varNum = CDFgetVarNum (id, "MY_VAR");
    startRec = 10;
    endRec = 20;
    status = CDFdeletezVarRecordsRenumber (id, varNum, startRec, endRec);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
.
```

4.3.14 CDFgetMaxWrittenRecNums

```
int CDFgetMaxWrittenRecNums (                /* out -- Completion status code. */
void* id,                                    /* in -- CDF identifier. */
TYPE rVarsMaxNum,                           /* out -- Maximum record number among all rVariables. */
```

```

TYPE zVarsMaxNum);           /* out -- Maximum record number among all zVariables. */
                             /* TYPE -- int* or "out int" */

```

CDFgetMaxWrittenRecNums returns the maximum written record number for the rVariables and zVariables in a CDF. The maximum record number for rVariables or zVariables is one less than the maximum number of records among all respective variables.

The arguments to CDFgetMaxWrittenRecNums are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
rVarsMaxNum	The maximum record number among all rVariables.
zVarsMaxNum	The maximum record number among all zVariables.

4.3.14.1. Example(s)

The following example returns the maximum written record numbers among all rVariables and zVariables of the CDF.

```

.
.
.
void*      id;           /* CDF identifier. */
int  status;           /* Returned status code. */
int  rVarsMaxNum;     /* Maximum record number among all rVariables. */
int  zVarsMaxNum;     /* Maximum record number among all zVariables. */
.
.
try {
    ....
    status = CDFgetMaxWrittenRecNums (id, &rVarsMaxNum, &zVarsMaxNum);
    Or,
    status = CDFgetMaxWrittenRecNums (id, out rVarsMaxNum, out zVarsMaxNum);
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.15 CDFgetNumrVars

```

int CDFgetNumrVars (           /* out -- Completion status code. */
void* id,                   /* in -- CDF identifier. */
TYPE numVars);             /* out -- Total number of rVariables. */
                             /* TYPE -- int* or "out int" */

```

CDFgetNumrVars returns the total number of rVariables in a CDF.

The arguments to CDFgetNumrVars are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
numVars	The number of rVariables.

4.3.15.1. Example(s)

The following example returns the total number of rVariables in a CDF.

```

.
.
int  status;           /* Returned status code. */
void* id;             /* CDF identifier. */
int  numVars;        /* Number of zVariables. */

.
.
try {
    ....
    status = CDFgetNumrVars (id, &numVars);
    Or,
    status = CDFgetNumrVars (id, out numVars);
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.16 CDFgetNumzVars

```

int CDFgetNumzVars (           /* out -- Completion status code. */
void* id,                   /* in -- CDF identifier. */
TYPE numVars);             /* out -- Total number of zVariables. */
                             /* TYPE -- int* or "out int". */

```

CDFgetNumzVars returns the total number of zVariables in a CDF.

The arguments to CDFgetNumzVars are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
numVars	The number of zVariables.

4.3.16.1. Example(s)

The following example returns the total number of zVariables in a CDF.

```
.
.
.
int  status;           /* Returned status code. */
void* id;             /* CDF identifier. */
int  numVars;        /* Number of zVariables. */

.
.
try {
    ....
    status = CDFgetNumzVars (id, &numVars);
    Or,
    status = CDFgetNumzVars (id, out numVars);

...
...
} catch (CDFException ex) {
    ...
}.

```

4.3.17 CDFgetrVarAllocRecords

```
int CDFgetrVarAllocRecords(           /* out -- Completion status code. */
void* id,                             /* in -- CDF identifier. */
int varNum,                           /* in -- Variable number. */
TYPE numRecs);                       /* out -- Allocated number of records. */
                                       /* TYPE -- int* or "out int". */
```

CDFgetrVarAllocRecords returns the number of records allocated for the specified rVariable in a CDF. Refer to the CDF User's Guide for a description of allocating variable records in a single-file CDF.

The arguments to CDFgetrVarAllocRecords are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
numRecs	The number of allocated records.

4.3.17.1. Example(s)

The following example returns the number of allocated records for rVariable "MY_VAR" in a CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  varNum;          /* rVariable number. */
int  numRecs;        /* The allocated records. */
.
.
try {
    ....
    varNum = CDFgetrVarNum (id, "MY_VAR");
.
    status = CDFgetrVarAllocRecords (id, varNum, &numRecs);
Or,
    status = CDFgetrVarAllocRecords (id, varNum, out numRecs);
...
...
} catch (CDFException ex) {
    ...
}.

```

4.3.18 CDFgetrVarBlockingFactor

```

int CDFgetrVarBlockingFactor(          /* out -- Completion status code. */
void* id,                             /* in -- CDF identifier. */
int varNum,                           /* in -- Variable number. */
TYPE bf);                             /* out -- Blocking factor. */
                                         /* TYPE -- int* or "out int". */

```

CDFgetrVarBlockingFactor returns the blocking factor for the specified rVariable in a CDF. Refer to the CDF User's Guide for a description of the blocking factor.

The arguments to CDFgetrVarBlockingFactor are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
bf	The blocking factor. A value of zero (0) indicates that the default blocking factor will be used.

4.3.18.1. Example(s)

The following example returns the blocking factor for the rVariable "MY_VAR" in a CDF.

```

.
.
.
void*      id;          /* CDF identifier. */

```

```

int  varNum;          /* rVariable number. */
int  bf;             /* The blocking factor. */
.
.
try {
    ....
    varNum = CDFgetVarNum (id, "MY_VAR");

    status = CDFgetrVarBlockingFactor (id, varNum, &bf);
..Or,
    status = CDFgetrVarBlockingFactor (id, varNum, out bf);
} catch (CDFException ex) {
    ...
}.

```

4.3.19 CDFgetrVarCacheSize

```

int CDFgetrVarCacheSize( /* out -- Completion status code. */
void* id,                /* in -- CDF identifier. */
int varNum,              /* in -- Variable number. */
TYPE numBuffers);      /* out -- Number of cache buffers. */
                        /* TYPE -- int* or "out int". */

```

CDFgetrVarCacheSize returns the number of cache buffers being for the specified rVariable in a CDF. This operation is not applicable to a single-file CDF. Refer to the CDF User's Guide for a description of caching scheme used by the CDF library.

The arguments to CDFgetrVarCacheSize are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
numBuffers	The number of cache buffers.

4.3.19.1. Example(s)

The following example returns the number of cache buffers for rVariable "MY_VAR" in a CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  varNum;          /* rVariable number. */
int  numBuffers;      /* The number of cache buffers. */
.
.
try {
    ....

```



```

int[] cParms;           /* The compression parameters. */
int cPct;              /* The compression percentage. */
.
.
try {
    ....
    varNum = CDFgetVarNum (id, "MY_VAR");
    cParms = new int[1];
    fixed (int* pcParms = cParms) {
        status = CDFgetVarCompression (id, varNum, &cType, pcParms, &cPct);
    }
    Or
    status = CDFgetVarCompression (id, varNum, out cType, out cParms, out cPct);
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.21 CDFgetVarData

```

int CDFgetVarData(      /* out -- Completion status code. */
void* id,              /* in -- CDF identifier. */
int varNum,            /* in -- Variable number. */
int recNum,            /* in -- Record number. */
int[] indices,         /* in -- Dimension indices. */
TYPE value);          /* out -- Data value. */
                        /* TYPE -- void*, "out string" or "out object". */

```

CDFgetVarData returns a data value from the specified indices, the location of the element, in the given record of the specified rVariable in a CDF.

The arguments to CDFgetVarData are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
recNum	The record number.
indices	The dimension indices within the record.
value	The data value.

4.3.21.1. Example(s)

The following example returns two data values, the first and the fifth element, in Record 0 from rVariable "MY_VAR", a 2-dimensional (2 by 3) CDF_DOUBLE type variable, in a row-major CDF.


```

.
.
.
void* id;          /* CDF identifier. */
int  varNum;      /* rVariable number. */
int  recNum;      /* The record number. */
int[] indices = new int[2]; /* The dimension indices. */
double value1, value2; /* The data values. */
.
.
try {
    ....
    varNum = CDFgetVarNum (id, "MY_VAR");
    recNum = 0;
    indices[0] = 0;
    indices[1] = 0;
    status = CDFgetrVarData (id, varNum, recNum, indices, &value1);
    indices[0] = 1;
    indices[1] = 1;
    object value2a;
    status = CDFgetrVarData (id, varNum, recNum, indices, out value2a);
    value2 = (double) value2a;
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.22 CDFgetrVarDataType

```

int CDFgetrVarDataType(          /* out -- Completion status code. */
void* id,                       /* in -- CDF identifier. */
int varNum,                     /* in -- Variable number. */
TYPE dataType);               /* out -- Data type. */
                                /* TYPE -- int* or "out int" */

```

CDFgetrVarDataType returns the data type of the specified rVariable in a CDF. Refer to Section 2.6 for a description of the CDF data types.

The arguments to CDFgetrVarDataType are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
dataType	The data type.

4.3.22.1. Example(s)

The following example returns the data type of rVariable “MY_VAR” in a CDF.

```
.  
. .  
. .  
void*      id;          /* CDF identifier. */  
int  varNum;          /* rVariable number. */  
int  dataType;       /* The data type. */  
. .  
try {  
    ....  
    varNum = CDFgetVarNum (id, “MY_VAR”);  
    status = CDFgetVarDataType (id, varNum, &dataType);  
    Or  
    status = CDFgetVarDataType (id, varNum, out dataType);  
    ...  
    ...  
} catch (CDFException ex) {  
    ...  
}.
```

4.3.23 CDFgetVarDimVariances

```
int CDFgetVarDimVariances(  
void* id,                /* out -- Completion status code. */  
int varNum,             /* in -- CDF identifier. */  
TYPE dimVarys);        /* in -- Variable number. */  
                        /* out -- Dimension variances. */  
                        /* TYPE -- int* or “out int[]”. */
```

CDFgetVarDimVariances returns the dimension variances of the specified rVariable in a CDF. For 0-dimensional rVariable, this operation is not applicable. The dimension variances are described in section 2.10.

The arguments to CDFgetVarDimVariances are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
dimVarys	The dimension variances.

4.3.23.1. Example(s)

The following example returns the dimension variances of the 2-dimensional rVariable “MY_VAR” in a CDF.

```
.
```

```

.
.
void*      id;          /* CDF identifier. */
int[] dimVarys;       /* The dimension variances. */
.
.
try {
    ....

    dimVarys = new int[2];
    fixed (int* pdimVarys = dimVarys) {
...   status = CDFgetrVarDimVariances (id, CDFgetrVarNum (id, "MY_VAR"), pdimVarys);
    }
    Or
    status = CDFgetrVarDimVariances (id, CDFgetrVarNum (id, "MY_VAR"), out dimVarys);

...
} catch (CDFException ex) {
    ...
}.

```

4.3.24 CDFgetrVarInfo

```

int CDFgetrVarInfo(          /* out -- Completion status code. */
void* id,                  /* in -- CDF identifier. */
int varNum,                /* in -- Variable number. */
TYPE dataType,           /* out -- Data type. */
TYPE numElems,          /* out -- Number of elements. */
TYPE numDims,          /* out -- Number of dimensions. */
TYPE2 dimSizes);       /* out -- Dimension sizes. */
                          /* TYPE -- int* or "out int". */
                          /* TYPE2 -- int* or "out int[]". */

```

CDFgetrVarInfo returns the basic information about the specified rVariable in a CDF.

The arguments to CDFgetrVarInfo are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
dataType	The data type of the variable.
numElems	The number of elements for the data type of the variable.
numDims	The number of dimensions.
dimSizes	The dimension sizes.

4.3.24.1. Example(s)

The following example returns the basic information of rVariable “MY_VAR” in a CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  dataType;        /* The data type. */
int  numElems;       /* The number of elements. */
int  numDims;        /* The number of dimensions. */
int[] dimSizes;      /* The dimension sizes. */
.
.
try {
    ....

    dimVarys = new int[CDF_MAX_DIMS];
    fixed (int* pdimVarys = dimVarys) {
...   status = CDFgetrVarInfo (id, CDFgetrVarNum (id, "MY_VAR"), &dataType, &numElems,
                                &numDims, pdimVarys);
    }
    Or
    status = CDFgetrVarInfo (id, CDFgetrVarNum (id, "MY_VAR"), out dataType, out numElems,
                            out numDims, out dimVarys);

    ...
} catch (CDFException ex) {
    ...
}.
```

4.3.25 CDFgetrVarMaxAllocRecNum

```
int CDFgetrVarMaxAllocRecNum(          /* out -- Completion status code. */
void* id,                             /* in -- CDF identifier. */
int varNum,                           /* in -- Variable number. */
TYPE maxRec);                        /* out -- Maximum allocated record #. */
/* TYPE -- int* or "out int". */
```

CDFgetrVarMaxAllocRecNum returns the number of records allocated for the specified rVariable in a CDF.

The arguments to CDFgetrVarMaxAllocRecNum are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
maxRec	The number of records allocated.

4.3.25.1. Example(s)

The following example returns the maximum allocated record number for the rVariable “MY_VAR” in a CDF.

```
.  
. .  
. .  
void*      id;          /* CDF identifier. */  
int  maxRec;          /* The maximum record number. */  
. .  
try {  
    ....  
    status = CDFgetrVarMaxAllocRecNum (id, CDFgetrVarNum (id, "MY_VAR"), &maxRec);  
    Or  
    status = CDFgetrVarMaxAllocRecNum (id, CDFgetrVarNum (id, "MY_VAR"), out maxRec);  
    ...  
    ...  
} catch (CDFException ex) {  
    ...  
}.  
}
```

4.3.26 CDFgetrVarMaxWrittenRecNum

```
int CDFgetrVarMaxWrittenRecNum (          /* out -- Completion status code. */  
void* id,                                /* in -- CDF identifier. */  
int varNum,                              /* in -- Variable number. */  
TYPE maxRec);                          /* out -- Maximum written record number. */  
                                          /* TYPE -- int* or "out int". */
```

CDFgetrVarMaxWrittenRecNum returns the maximum record number written for the specified rVariable in a CDF.

The arguments to CDFgetrVarMaxWrittenRecNum are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
maxRec	The maximum written record number.

4.3.26.1. Example(s)

The following example returns the maximum record number written for the rVariable “MY_VAR” in a CDF.

```
.  
. .  
. .  
void*      id;          /* CDF identifier. */
```

```

int maxRec;                                /* The maximum record number. */
.
.
try {
    ....
    status = CDFgetrVarMaxWrittenRecNum (id, CDFgetrVarNum (id, "MY_VAR"), &maxRec);
Or
    status = CDFgetrVarMaxWrittenRecNum (id, CDFgetrVarNum (id, "MY_VAR"), out maxRec);
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.27 CDFgetrVarName

```

int CDFgetrVarName(                          /* out -- Completion status code. */
void* id,                                    /* in -- CDF identifier. */
int varNum,                                  /* in -- Variable number. */
out string varName);                         /* out -- Variable name. */

```

CDFgetrVarName returns the name of the specified rVariable, by its number, in a CDF.

The arguments to CDFgetrVarName are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
varName	The name of the variable.

4.3.27.1. Example(s)

The following example returns the name of the rVariable whose variable number is 1.

```

.
.
.
void* id;                                    /* CDF identifier. */
int varNum;                                  /* rVariable number. */
string varName;                              /* The name of the variable. */
.
.
varNum = 1;
try {
    ....
    status = CDFgetrVarName (id, varNum, out varName);
    ...
    ...
}

```

```

} catch (CDFException ex) {
    ...
}.

```

4.3.28 CDFgetrVarNumElements

```

int CDFgetrVarNumElements(                                     /* out -- Completion status code. */
void* id,                                                    /* in -- CDF identifier. */
int varNum,                                                 /* in -- Variable number. */
TYPE numElems);                                           /* out -- Number of elements. */
                                                            /* TYPE -- int* or "out int". */

```

CDFgetrVarNumElements returns the number of elements for each data value of the specified rVariable in a CDF. For character data type (CDF_CHAR and CDF_UCHAR), the number of elements is the number of characters in the string. For other data types, the number of elements will always be one (1).

The arguments to CDFgetrVarNumElements are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
numElems	The number of elements.

4.3.28.1. Example(s)

The following example returns the number of elements for the data type from rVariable "MY_VAR" in a CDF.

```

.
.
.
void* id;                                                    /* CDF identifier. */
int numElems;                                              /* The number of elements. */
.
.
try {
    ....
    status = CDFgetrVarNumElements (id, CDFgetrVarNum (id, "MY_VAR"), &numElems);
    Or
    status = CDFgetrVarNumElements (id, CDFgetrVarNum (id, "MY_VAR"), out numElems);...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.29 CDFgetrVarNumRecsWritten

```
int CDFgetrVarNumRecsWritten(                                     /* out -- Completion status code. */
void* id,                                                         /* in -- CDF identifier. */
int varNum,                                                       /* in -- Variable number. */
TYPE numRecs);                                                  /* out -- Number of written records. */
                                                                /* TYPE -- int* or "out int". */
```

CDFgetrVarNumRecsWritten returns the number of records written for the specified rVariable in a CDF. This number may not correspond to the maximum record written if the rVariable has sparse records.

The arguments to CDFgetrVarNumRecsWritten are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
numRecs	The number of written records.

4.3.29.1. Example(s)

The following example returns the number of written records from rVariable "MY_VAR" in a CDF.

```
.
.
.
void*      id;           /* CDF identifier. */
int  numRecs;          /* The number of written records. */
.
.
try {
    ....
    status = CDFgetrVarNumRecsWritten (id, CDFgetrVarNum (id, "MY_VAR"), &numRecs);
    Or
    status = CDFgetrVarNumRecsWritten (id, CDFgetrVarNum (id, "MY_VAR"), out numRecs);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
.
```

4.3.30 CDFgetrVarPadValue

```
int CDFgetrVarPadValue(                                         /* out -- Completion status code. */
void* id,                                                         /* in -- CDF identifier. */
int varNum,                                                       /* in -- Variable number. */
TYPE value);                                                  /* out -- Pad value. */
                                                                /* TYPE -- void*, "out string" or "out object". */
```


CDFgetrVarPadValue returns the pad value of the specified rVariable in a CDF. If a pad value has not been explicitly specified for the rVariable through CDFsetrVarPadValue, the informational status code **NO_PADVALUE_SPECIFIED** will be returned. Since a variable's pad value is an optional, no exception is thrown while trying to get its value if its value is not set. It's recommended to check the returned status after the method is called.

The arguments to CDFgetrVarPadValue are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
value	The pad value.

4.3.30.1. Example(s)

The following example returns the pad value from rVariable "MY_VAR", a CDF_INT4 type variable, in a CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  padValue;        /* The pad value. */
.
.
try {
    ....
    status = CDFgetrVarPadValue (id, CDFgetVarNum (id, "MY_VAR"), &padValue);
    Or
    object padValue0;
    status = CDFgetrVarPadValue (id, CDFgetVarNum (id, "MY_VAR"), out padValue0);
    if (status != NO_PADVALUE_SPECIFIED) {
        padValue = (int) padValue0;
    }
    .
    }
. ....
...
} catch (CDFException ex) {
    ...
}.
}
```

4.3.31 CDFgetrVarRecordData

```
int CDFgetrVarRecordData(          /* out -- Completion status code. */
void* id,                          /* in -- CDF identifier. */
int varNum,                        /* in -- Variable number. */
```



```

void* id,                               /* in -- CDF identifier. */
int varNum,                             /* in -- Variable number. */
TYPE recVary);                         /* out -- Record variance. */
                                         /* TYPE -- int* or "out int". */

```

CDFgetrVarRecVariance returns the record variance of the specified rVariable in a CDF. The record variances are described in Section 2.10.

The arguments to CDFgetrVarRecVariance are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
recVary	The record variance.

4.3.32.1. Example(s)

The following example returns the record variance for the rVariable “MY_VAR” in a CDF.

```

.
.
.
void*      id;                            /* CDF identifier. */
int  recVary;                             /* The record variance. */
.
.
try {
....
    status = CDFgetrVarRecVariance (id, CDFgetVarNum (id, "MY_VAR"), &recVary);
Or
    status = CDFgetrVarRecVariance (id, CDFgetVarNum (id, "MY_VAR"), out recVary);...
...
} catch (CDFException ex) {
...
}.

```

4.3.33 CDFgetrVarReservePercent

```

int CDFgetrVarReservePercent(           /* out -- Completion status code. */
void* id,                              /* in -- CDF identifier. */
int varNum,                            /* in -- Variable number. */
TYPE percent);                       /* out -- Reserve percentage. */
                                         /* TYPE -- int* or "out int". */

```

CDFgetrVarReservePercent returns the compression reserve percentage being used for the specified rVariable in a CDF. This operation only applies to compressed rVariables. Refer to the CDF User’s Guide for a description of the reserve scheme used by the CDF library.

The arguments to `CDFgetrVarReservePercent` are defined as follows:

<code>id</code>	The identifier of the current CDF. This identifier must have been initialized by a call to <code>CDFcreate</code> (or <code>CDFcreateCDF</code>) or <code>CDFopenCDF</code> .
<code>varNum</code>	The rVariable number.
<code>percent</code>	The reserve percentage.

4.3.33.1. Example(s)

The following example returns the compression reserve percentage from the compressed rVariable “MY_VAR” in a CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  percent;         /* The compression reserve percentage. */
.
.
try {
    ....
    status = CDFgetrVarReservePercent (id, CDFgetVarNum (id, "MY_VAR"), &percent);
    Or
    status = CDFgetrVarReservePercent (id, CDFgetVarNum (id, "MY_VAR"), out percent);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
.
```

4.3.34 CDFgetrVarsDimSizes

```
int CDFgetrVarsDimSizes(          /* out -- Completion status code. */
void* id,                        /* in -- CDF identifier. */
TYPE dimSizes);                /* out -- Dimension sizes. */
                                /* TYPE -- int* or "out int[]". */
```

`CDFgetrVarsDimSizes` returns the size of each dimension for the rVariables in a CDF. (all rVariables have the same dimensional sizes.) For 0-dimensional rVariables, this operation is not applicable.

The arguments to `CDFgetrVarsDimSizes` are defined as follows:

<code>id</code>	The identifier of the current CDF. This identifier must have been initialized by a call to <code>CDFcreate</code> (or <code>CDFcreateCDF</code>) or <code>CDFopenCDF</code> .
<code>dimSizes</code>	The dimension sizes. Each element of <code>dimSizes</code> receives the corresponding dimension size.

4.3.34.1. Example(s)

The following example returns the dimension sizes for rVariables in a CDF.

```
.  
.br/>.br/>void*      id;                /* CDF identifier. */  
.int[]     dimSizes;         /* Dimensional sizes. */  
  
.try {  
    ....  
    dimSizes = new int[CDF_MAX_DIMS];  
    fixed (int* pdimSizes = dimSizes) {  
        status = CDFgetrVarsDimSizes (id, pdimSizes);  
    }  
    Or  
    status = CDFgetrVarsDimSizes (id, out dimSizes);  
    ...  
    ...  
} catch (CDFException ex) {  
    ...  
}.  
}
```

4.3.35 CDFgetrVarSeqData

```
int CDFgetrVarSeqData(                /* out -- Completion status code. */  
void* id,                            /* in -- CDF identifier. */  
int varNum,                          /* in -- Variable number. */  
TYPE value);                         /* out -- Data value. */  
/* TYPE -- void*, "out string" or "out object". */
```

CDFgetrVarSeqData reads one value from the specified rVariable in a CDF at the current sequential value (position). After the read, the current sequential value is automatically incremented to the next value. An error is returned if the current sequential value is past the last record of the rVariable. Use CDFsetrVarSeqPos method to set the current sequential value (position).

The arguments to CDFgetrVarSeqData are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number from which to read data.
value	The buffer to store the value.

4.3.35.1. Example(s)

The following example will read the first two data values from the beginning of record number 2 (from a 2-dimensional rVariable whose data type is CDF_INT4) in a CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  varNum;          /* The variable number from which to read data */
int  value1, value2;  /* The data value. */
int[] indices = new int[2]; /* The indices in a record. */
int  recNum;         /* The record number. */
.
.
recNum = 2;
indices[0] = 0;
indices[1] = 0;
try {
    ....
    status = CDFsetrVarSeqPos (id, varNum, recNum, indices);
    status = CDFgetrVarSeqData (id, varNum, &value1);
    object value2o;
    status = CDFgetrVarSeqData (id, varNum, out value2o);
    value2 = (int) value2o;
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.36 CDFgetrVarSeqPos

```

int CDFgetrVarSeqPos(          /* out -- Completion status code. */
void* id,                    /* in -- CDF identifier. */
int varNum,                  /* in -- Variable number. */
TYPE recNum,                /* out -- Record number. */
TYPE2 indices);            /* out -- Indices in a record. */
                                /* TYPE -- int* or "out int". */
                                /* TYPE2 -- int* or "out int[]". */

```

CDFgetrVarSeqPos returns the current sequential value (position) for sequential access for the specified rVariable in a CDF. Note that a current sequential value is maintained for each rVariable individually. Use CDFsetrVarSeqPos method to set the current sequential value.

The arguments to CDFgetrVarSeqPos are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
recNum	The rVariable record number.
indices	The dimension indices. Each element of indices receives the corresponding dimension index. For 0-dimensional rVariable, this argument is ignored, but must be presented.

4.3.36.1. Example(s)

The following example returns the location for the current sequential value (position), the record number and indices within it, from a 2-dimensional rVariable named MY_VAR in a CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  recNum;          /* The record number. */
int[] indices;        /* The indices. */
.
.
try {
    ....
    indices = new int[2];
    fixed (int* pindices = indices) {
        status = CDFgetrVarSeqPos (id, CDFgetrVarNum(id, "MY_VAR"), &recNum, pindices);
    }
    Or
    status = CDFgetrVarSeqPos (id, CDFgetrVarNum(id, "MY_VAR"), out recNum, out indices);
    ...
} catch (CDFException ex) {
    ...
}.
```

4.3.37 CDFgetrVarsMaxWrittenRecNum

```
int CDFgetrVarsMaxWrittenRecNum(          /* out -- Completion status code. */
void* id,                                /* in -- CDF identifier. */
TYPE recNum);                          /* out -- Maximum record number. */
                                          /* TYPE -- int* or "out int". */
```

CDFgetrVarsMaxWrittenRecNum returns the maximum record number among all of the rVariables in a CDF. Note that this is not the number of written records but rather the maximum written record number (that is one less than the number of records). A value of negative one (-1) indicates that rVariables contain no records. The maximum record number for an individual rVariable may be acquired using the CDFgetrVarMaxWrittenRecNum method call.

Suppose there are three rVariables in a CDF: Var1, Var2, and Var3. If Var1 contains 15 records, Var2 contains 10 records, and Var3 contains 95 records, then the value returned from CDFgetrVarsMaxWrittenRecNum would be 95.

The arguments to CDFgetrVarsMaxWrittenRecNum are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
recNum	The maximum written record number.

4.3.37.1. Example(s)

The following example returns the maximum record number for all of the rVariables in a CDF.

```
.
.
void*      id;          /* CDF identifier. */
int  recNum;          /* The maximum record number. */
.
.
try {
    ....
    status = CDFgetrVarsMaxWrittenRecNum (id, &recNum);
    Or
    status = CDFgetrVarsMaxWrittenRecNum (id, out recNum);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
.
```

4.3.38 CDFgetrVarsNumDims

```
int CDFgetrVarsNumDims(          /* out -- Completion status code. */
void* id,                       /* in -- CDF identifier. */
TYPE numDims);                 /* out -- Number of dimensions. */
                                /* TYPE -- int* or "out int". */
```

CDFgetrVarsNumDims returns the number of dimensions (dimensionality) for the rVariables in a CDF.

The arguments to CDFgetrVarsNumDims are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
numDims	The number of dimensions.

4.3.38.1. Example(s)

The following example returns the number of dimensions for rVariables in a CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  numDims;          /* The dimensionality of the variable. */
.
.
try {
```



```

....
status = CDFgetrVarsNumDims (id, &numDims);
Or
status = CDFgetrVarsNumDims (id, out numDims);
...
...
} catch (CDFException ex) {
...
}.

```

4.3.39 CDFgetrVarSparseRecords

```

int CDFgetrVarSparseRecords(                                     /* out -- Completion status code. */
void* id,                                                       /* in -- CDF identifier. */
int varNum,                                                    /* in -- The variable number. */
TYPE sRecordsType);                                           /* out -- The sparse records type. */
                                                             /* TYPE -- int* or "out int". */

```

CDFgetrVarSparseRecords returns the sparse records type of the rVariable in a CDF. Refer to Section 2.12.1 for the description of sparse records.

The arguments to CDFgetrVarSparseRecords are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The variable number.
sRecordsType	The sparse records type.

4.3.39.1. Example(s)

The following example returns the sparse records type of the rVariable “MY_VAR” in a CDF.

```

.
.
.
void* id;                                                       /* CDF identifier. */
int sRecordsType;                                             /* The sparse records type. */
.
.
try {
....
status = CDFgetrVarSparseRecords (id, CDFgetVarNum(id, "MY_VAR"), &sRecordsType);
Or
status = CDFgetrVarSparseRecords (id, CDFgetVarNum(id, "MY_VAR"), out sRecordsType);...
...
} catch (CDFException ex) {
...

```

```
    }.
```

4.3.40 CDFgetVarNum ¹⁰

```
int CDFgetVarNum(          /* out -- Variable number. */  
void* id,                /* in -- CDF identifier. */  
string varName);        /* in -- Variable name. */
```

CDFgetVarNum returns the variable number for the given variable name (rVariable or zVariable). If the variable is found, CDFgetVarNum returns its variable number - which will be equal to or greater than zero (0). If an error occurs (e.g., the variable does not exist in the CDF), an error code (of type int) is returned, and an exception is thrown. Error codes are less than zero (0). The returned variable number should be used in the functions of the same variable type, rVariable or zVariable. If it is an rVariable, functions dealing with rVariables should be used. Similarly, functions for zVariables should be used for zVariables.

The arguments to CDFgetVarNum are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varName	The name of the variable to search. This may be at most CDF_VAR_NAME_LEN256 characters. Variable names are case-sensitive.

CDFgetVarNum may be used as an embedded function call where an rVariable or zVariable number is needed.

4.3.40.1. Example(s)

In the following example CDFgetVarNum is used as an embedded function call when inquiring about a zVariable.

```
.  
. .  
. .  
void*      id;          /* CDF identifier. */  
int  status;          /* Returned status code. */  
string  varName;      /* Variable name. */  
int  dataType;       /* Data type of the zVariable. */  
int  numElements;    /* Number of elements (of the data type). */  
int  numDims;        /* Number of dimensions. */  
int[] dimSizes;      /* Dimension sizes. */  
int  recVariance;    /* Record variance. */  
int[] dimVariances;  /* Dimension variances. */  
. .  
. .  
try {  
    ....  
    dimSizes = new int[1];  
    dimVariances = new int[1];
```

¹⁰ Since no two variables, either rVariable or zVariable, can have the same name, this function now returns the variable number for the given rVariable or zVariable name (if the variable name exists in a CDF).


```

.
.
try {
....
    varNum = CDFgetzVarNum (id, "MY_VAR");
.
    status = CDFgetzVarAllocRecords (id, varNum, &numRecs);
Or,
    status = CDFgetzVarAllocRecords (id, varNum, out numRecs);
...
...
} catch (CDFException ex) {
....
}.

```

4.3.42 CDFgetzVarBlockingFactor

```

int CDFgetzVarBlockingFactor(                               /* out -- Completion status code. */
void* id,                                                  /* in -- CDF identifier. */
int varNum,                                               /* in -- Variable number. */
TYPE bf);                                                /* out -- Blocking factor. */
                                                         /* TYPE -- int* or "out int". */

```

CDFgetzVarBlockingFactor returns the blocking factor for the specified zVariable in a CDF. Refer to the CDF User's Guide for a description of the blocking factor.

The arguments to CDFgetzVarBlockingFactor are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
bf	The blocking factor. A value of zero (0) indicates that the default blocking factor will be used.

4.3.42.1. Example(s)

The following example returns the blocking factor for the zVariable "MY_VAR" in a CDF.

```

.
.
.
void*      id;                                           /* CDF identifier. */
int  varNum;                                           /* zVariable number. */
int  bf;                                               /* The blocking factor. */
.
.
try {
....

```

```

varNum = CDFgetVarNum (id, "MY_VAR");

status = CDFgetVarBlockingFactor (id, varNum, &bf);
..Or,
status = CDFgetVarBlockingFactor (id, varNum, out bf);
} catch (CDFException ex) {
...
}.

```

4.3.43 CDFgetVarCacheSize

```

int CDFgetVarCacheSize(                                     /* out -- Completion status code. */
void* id,                                                 /* in -- CDF identifier. */
int varNum,                                              /* in -- Variable number. */
TYPE numBuffers);                                       /* out -- Number of cache buffers. */
                                                         /* TYPE -- int* or "out int". */

```

CDFgetVarCacheSize returns the number of cache buffers being for the specified zVariable in a CDF. This operation is not applicable to a single-file CDF. Refer to the CDF User's Guide for a description of caching scheme used by the CDF library.

The arguments to CDFgetVarCacheSize are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
numBuffers	The number of cache buffers.

4.3.43.1. Example(s)

The following example returns the number of cache buffers for zVariable "MY_VAR" in a CDF.

```

.
.
.
void* id;                                                 /* CDF identifier. */
int varNum;                                              /* zVariable number. */
int numBuffers;                                         /* The number of cache buffers. */
.
.
try {
....
varNum = CDFgetVarNum (id, "MY_VAR");
.
status = CDFgetVarCacheSize (id, varNum, &numBuffers);
Or,
status = CDFgetVarCacheSize (id, varNum, out numBuffers);
...

```

```

...
} catch (CDFException ex) {
...
}.

```

4.3.44 CDFgetzVarCompression

```

int CDFgetzVarCompression(                                     /* out -- Completion status code. */
void* id,                                                    /* in -- CDF identifier. */
int varNum,                                                 /* in -- Variable number. */
TYPE cType,                                                /* out -- Compression type. */
TYPE2 cParms,                                             /* out -- Compression parameters. */
TYPE cPct);                                               /* out -- Compression percentage. */
                                                           /* TYPE -- int* or "out int". */
                                                           /* TYPE2 -- int* or "out int[]". */

```

CDFgetzVarCompression returns the compression type/parameters and compression percentage of the specified zVariable in a CDF. Refer to Section 2.11 for a description of the CDF supported compression types/parameters. The compression percentage is the result of the compressed size from all variable records divided by its original, uncompressed variable size.

The arguments to CDFgetzVarCompression are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
cType	The compression type.
cParms	The compression parameters.
cPct	The percentage of the uncompressed size of zVariable's data values needed to store the compressed values.

4.3.44.1. Example(s)

The following example returns the compression information for zVariable "MY_VAR" in a CDF.

```

.
.
.
void*      id;                                             /* CDF identifier. */
int  varNum;                                             /* zVariable number. */
int  cType;                                             /* The compression type. */
int[] cParms;                                           /* The compression parameters. */
int  cPct;                                             /* The compression percentage. */
.
.
try {

```



```

int   recNum;                /* The record number. */
int[] indices = new int[2];  /* The dimension indices. */
double value1, value2;      /* The data values. */
.
.
try {
    ....
    varNum = CDFgetVarNum (id, "MY_VAR");
    recNum = 0;
    indices[0] = 0;
    indices[1] = 0;
    status = CDFgetVarData (id, varNum, recNum, indices, &value1);
    indices[0] = 1;
    indices[1] = 1;
    object value2a;
    status = CDFgetVarData (id, varNum, recNum, indices, out value2a);
    value2 = (double) value2a;
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.46 CDFgetVarDataType

```

int CDFgetVarDataType(      /* out -- Completion status code. */
void* id,                  /* in -- CDF identifier. */
int varNum,                /* in -- Variable number. */
TYPE dataType);          /* out -- Data type. */
                          /* TYPE -- int* or "out int" */

```

CDFgetVarDataType returns the data type of the specified zVariable in a CDF. Refer to Section 2.6 for a description of the CDF data types.

The arguments to CDFgetVarDataType are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
dataType	The data type.

4.3.46.1. Example(s)

The following example returns the data type of zVariable "MY_VAR" in a CDF.

```

.
.

```



```

.
void*      id;          /* CDF identifier. */
int  varNum;          /* zVariable number. */
int  dataType;        /* The data type. */
.
.
try {
....
    varNum = CDFgetVarNum (id, "MY_VAR");
    status = CDFgetzVarDataType (id, varNum, &dataType);
Or
    status = CDFgetzVarDataType (id, varNum, out dataType);
...
...
} catch (CDFException ex) {
...
}.

```

4.3.47 CDFgetzVarDimSizes

```

int CDFgetzVarDimSizes(          /* out -- Completion status code. */
void* id,                      /* in -- CDF identifier. */
int varNum,                    /* in -- Variable number. */
TYPE dimSizes);              /* out -- Dimension sizes. */
                               /* TYPE -- int* or "out int[]". */

```

CDFgetzVarDimSizes returns the size of each dimension for the specified zVariable in a CDF. For 0-dimensional zVariables, this operation is not applicable.

The arguments to CDFgetzVarDimSizes are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number
dimSizes	The dimension sizes. Each element of dimSizes receives the corresponding dimension size.

4.3.47.1. Example(s)

The following example returns the dimension sizes for zVariable "MY_VAR" in a CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
.int[]    dimSizes;    /* Dimensional sizes. */
.
.try {
....

```

```

dimSizes = new int[CDF_MAX_DIMS];
fixed (int* pdimSizes = dimSizes) {
    status = CDFgetzVarDimSizes (id, CDFgetVarNum(id, "MY_VAR"), pdimSizes);
}
Or
    status = CDFgetzVarDimSizes (id, CDFgetVarNum(id, "MY_VAR"), out dimSizes);
...
...
} catch (CDFException ex) {
    ...
}.

```

4.3.48 CDFgetzVarDimVariances

```

int CDFgetzVarDimVariances(                                     /* out -- Completion status code. */
void* id,                                                       /* in -- CDF identifier. */
int varNum,                                                     /* in -- Variable number. */
TYPE dimVarys);                                               /* out -- Dimension variances. */
                                                                /* TYPE -- int* or "out int[]". */

```

CDFgetzVarDimVariances returns the dimension variances of the specified zVariable in a CDF. For 0-dimensional zVariable, this operation is not applicable. The dimension variances are described in section 2.10.

The arguments to CDFgetzVarDimVariances are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
dimVarys	The dimension variances.

4.3.48.1. Example(s)

The following example returns the dimension variances of the 2-dimensional zVariable "MY_VAR" in a CDF.

```

.
.
.
void*      id;                                                 /* CDF identifier. */
int[] dimVarys;                                               /* The dimension variances. */
.
.
try {
    ....

    dimVarys = new int[2];
    fixed (int* pdimVarys = dimVarys) {
...    status = CDFgetzVarDimVariances (id, CDFgetVarNum (id, "MY_VAR"), pdimVarys);
    }
}

```



```

.
.
try {
....

    dimVarys = new int[CDF_MAX_DIMS];
    fixed (int* pdimVarys = dimVarys) {
...    status = CDFgetzVarInfo (id, CDFgetVarNum (id, "MY_VAR"), &dataType, &numElems,
                                &numDims, pdimVarys);
    }
Or
    status = CDFgetzVarInfo (id, CDFgetVarNum (id, "MY_VAR"), out dataType, out numElems,
                            out numDims, out dimVarys);

...
} catch (CDFException ex) {
...
}.

```

4.3.50 CDFgetzVarMaxAllocRecNum

```

int CDFgetzVarMaxAllocRecNum(                                     /* out -- Completion status code. */
void* id,                                                         /* in -- CDF identifier. */
int varNum,                                                       /* in -- Variable number. */
TYPE maxRec);                                                  /* out -- Maximum allocated record #. */
                                                                /* TYPE -- int* or "out int". */

```

CDFgetzVarMaxAllocRecNum returns the number of records allocated for the specified zVariable in a CDF.

The arguments to CDFgetzVarMaxAllocRecNum are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
maxRec	The number of records allocated.

4.3.50.1. Example(s)

The following example returns the maximum allocated record number for the zVariable "MY_VAR" in a CDF.

```

.
.
.
void*      id;           /* CDF identifier. */
int  maxRec;           /* The maximum record number. */
.
.

```

```

try {
    ....
    status = CDFgetzVarMaxAllocRecNum (id, CDFgetzVarNum (id, "MY_VAR"), &maxRec);
    Or
    status = CDFgetzVarMaxAllocRecNum (id, CDFgetzVarNum (id, "MY_VAR"), out maxRec);
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.51 CDFgetzVarMaxWrittenRecNum

```

int CDFgetzVarMaxWrittenRecNum (                               /* out -- Completion status code. */
void* id,                                                       /* in -- CDF identifier. */
int varNum,                                                    /* in -- Variable number. */
TYPE maxRec);                                                /* out -- Maximum written record number. */
                                                                /* TYPE -- int* or "out int". */

```

CDFgetzVarMaxWrittenRecNum returns the maximum record number written for the specified zVariable in a CDF.

The arguments to CDFgetzVarMaxWrittenRecNum are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
maxRec	The maximum written record number.

4.3.51.1. Example(s)

The following example returns the maximum record number written for the zVariable "MY_VAR" in a CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  maxRec;          /* The maximum record number. */
.
.
try {
    ....
    status = CDFgetzVarMaxWrittenRecNum (id, CDFgetzVarNum (id, "MY_VAR"), &maxRec);
    Or
    status = CDFgetzVarMaxWrittenRecNum (id, CDFgetzVarNum (id, "MY_VAR"), out maxRec);
    ...
    ...
} catch (CDFException ex) {
    ...
}

```



```

int varNum,                               /* in -- Variable number. */
TYPE numDims);                          /* out -- Number of dimensions. */
                                           /* TYPE -- int* or "out int". */

```

CDFgetzVarNumDims returns the number of dimensions (dimensionality) for the specified zVariable in a CDF.

The arguments to CDFgetzVarNumDims are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number
numDims	The number of dimensions.

4.3.53.1. Example(s)

The following example returns the number of dimensions for zVariable "MY_VAR" in a CDF.

```

.
.
.
void*      id;                               /* CDF identifier. */
int  numDims;                              /* The dimensionality of the variable. */
.
.
try {
    ....
    status = CDFgetzVarNumDims (id, CDFgetzVarNum(id, "MY_VAR"), &numDims);
Or
    status = CDFgetzVarNumDims (id, CDFgetzVarNum(id, "MY_VAR"), out numDims);
...
...
} catch (CDFException ex) {
    ...
}.

```

4.3.54 CDFgetzVarNumElements

```

int CDFgetzVarNumElements(                 /* out -- Completion status code. */
void* id,                                 /* in -- CDF identifier. */
int varNum,                               /* in -- Variable number. */
TYPE numElems);                          /* out -- Number of elements. */
                                           /* TYPE -- int* or "out int". */

```

CDFgetzVarNumElements returns the number of elements for each data value of the specified zVariable in a CDF. For character data type (CDF_CHAR and CDF_UCHAR), the number of elements is the number of characters in the string. For other data types, the number of elements will always be one (1).

The arguments to CDFgetzVarNumElements are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
numElems	The number of elements.

4.3.54.1. Example(s)

The following example returns the number of elements for the data type from zVariable “MY_VAR” in a CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  numElems;        /* The number of elements. */
.
.
try {
    ....
    status = CDFgetzVarNumElements (id, CDFgetzVarNum (id, “MY_VAR”), &numElems);
    Or
    status = CDFgetzVarNumElements (id, CDFgetzVarNum (id, “MY_VAR”), out numElems);...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.55 CDFgetzVarNumRecsWritten

```

int CDFgetzVarNumRecsWritten(          /* out -- Completion status code. */
void* id,                             /* in -- CDF identifier. */
int varNum,                           /* in -- Variable number. */
TYPE numRecs);                       /* out -- Number of written records. */
                                         /* TYPE -- int* or “out int”. */

```

CDFgetzVarNumRecsWritten returns the number of records written for the specified zVariable in a CDF. This number may not correspond to the maximum record written if the zVariable has sparse records.

The arguments to CDFgetzVarNumRecsWritten are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
numRecs	The number of written records.

4.3.55.1. Example(s)

The following example returns the number of written records from zVariable “MY_VAR” in a CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  numRecs;         /* The number of written records. */
.
.
try {
    ....
    status = CDFgetzVarNumRecsWritten (id, CDFgetzVarNum (id, “MY_VAR”), &numRecs);
    Or
    status = CDFgetzVarNumRecsWritten (id, CDFgetzVarNum (id, “MY_VAR”), out numRecs);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
}
```

4.3.56 CDFgetzVarPadValue

```
int CDFgetzVarPadValue(          /* out -- Completion status code. */
void* id,                       /* in -- CDF identifier. */
int varNum,                     /* in -- Variable number. */
TYPE value);                   /* out -- Pad value. */
                                /* TYPE -- void*, “out string” or “out object”. */
```

CDFgetzVarPadValue returns the pad value of the specified zVariable in a CDF. If a pad value has not been explicitly specified for the zVariable through CDFsetzVarPadValue, the informational status code **NO_PADVALUE_SPECIFIED** will be returned. Since a variable’s pad value is an optional, no exception is thrown while trying to get its value if its value is not set. It’s recommended to check the returned status after the method is called.

The arguments to CDFgetzVarPadValue are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
value	The pad value.

4.3.56.1. Example(s)

The following example returns the pad value from zVariable “MY_VAR”, a CDF_INT4 type variable, in a CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  padValue;        /* The pad value. */
.
.
try {
    ....
    status = CDFgetzVarPadValue (id, CDFgetVarNum (id, “MY_VAR”), &padValue);
    Or
    Object padValueo;
    status = CDFgetzVarPadValue (id, CDFgetVarNum (id, “MY_VAR”), out padValueo);
    if (status != NO_PADVALUE_SPECIFIED) {
        padValue = (int) padValueo;
    }
    .
    }
. ....
...
} catch (CDFException ex) {
    ...
}.

```

4.3.57 CDFgetzVarRecordData

```

int CDFgetzVarRecordData(          /* out -- Completion status code. */
void* id,                          /* in -- CDF identifier. */
int varNum,                        /* in -- Variable number. */
int recNum,                        /* in -- Record number. */
TYPE buffer);                    /* out -- Record data. */
/* TYPE -- void*, “out string”, “out string[]” or “out object”. */
*/

```

CDFgetzVarRecordData returns an entire record at a given record number for the specified zVariable in a CDF. The buffer should be large enough to hold the entire data values form the variable.

The arguments to CDFgetzVarRecordData are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
recNum	The record number.
buffer	The buffer holding the entire record data.

4.3.57.1. Example(s)

The following example will read two full records (record numbers 2 and 5) from zVariable “MY_VAR”, a 2-dimension (2 by 3), CDF_INT4 type variable, in a CDF. The variable’s dimension variances are all VARY.

```
.
.
.
void*      id;          /* CDF identifier. */
int  varNum;          /* zVariable number. */
int[,] buffer1;       /* The data holding buffer – pre-allocation. */
int[,] buffer2;       /* The data holding buffer – API allocation. */
.
.
try {
    ....
    varNum = CDFgetVarNum (id, “MY_VAR”);
    buffer1 = new int[2,3];
    fixed (void* pBuffer1 = buffer1) {
        status = CDFgetzVarRecordData (id, varNum, 2, pBuffer1);
    }
    status = CDFgetzVarRecordData (id, varNum, 5, out buffer2);
    ...
} catch (CDFException ex) {
    ...
}.
```

4.3.58 CDFgetzVarRecVariance

```
int CDFgetzVarRecVariance(          /* out -- Completion status code. */
void* id,                          /* in -- CDF identifier. */
int varNum,                        /* in -- Variable number. */
TYPE recVary);                    /* out -- Record variance. */
                                     /* TYPE -- int* or “out int”. */
```

CDFgetzVarRecVariance returns the record variance of the specified zVariable in a CDF. The record variances are described in Section 2.10.

The arguments to CDFgetzVarRecVariance are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
recVary	The record variance.

4.3.58.1. Example(s)

The following example returns the record variance for the zVariable “MY_VAR” in a CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  recVary;         /* The record variance. */
.
.
try {
....
    status = CDFgetzVarRecVariance (id, CDFgetVarNum (id, “MY_VAR”), &recVary);
Or
    status = CDFgetzVarRecVariance (id, CDFgetVarNum (id, “MY_VAR”), out recVary);...
...
} catch (CDFException ex) {
....
}.
.
```

4.3.59 CDFgetzVarReservePercent

```
int CDFgetzVarReservePercent(          /* out -- Completion status code. */
void* id,                             /* in -- CDF identifier. */
int varNum,                           /* in -- Variable number. */
TYPE percent);                       /* out -- Reserve percentage. */
                                        /* TYPE -- int* or “out int”. */
```

CDFgetzVarReservePercent returns the compression reserve percentage being used for the specified zVariable in a CDF. This operation only applies to compressed zVariables. Refer to the CDF User’s Guide for a description of the reserve scheme used by the CDF library.

The arguments to CDFgetzVarReservePercent are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
percent	The reserve percentage.

4.3.59.1. Example(s)

The following example returns the compression reserve percentage from the compressed zVariable “MY_VAR” in a CDF.

```
.
.
```

```

.
void*      id;                /* CDF identifier. */
int  percent;                /* The compression reserve percentage. */
.
.
try {
....
    status = CDFgetzVarReservePercent (id, CDFgetVarNum (id, "MY_VAR"), &percent);
Or
    status = CDFgetzVarReservePercent (id, CDFgetVarNum (id, "MY_VAR"), out percent);
...
...
} catch (CDFException ex) {
....
}.

```

4.3.60 CDFgetzVarSeqData

```

int CDFgetzVarSeqData(        /* out -- Completion status code. */
void* id,                    /* in -- CDF identifier. */
int varNum,                  /* in -- Variable number. */
TYPE value);                /* out -- Data value. */
                             /* TYPE -- void*, "out string" or "out object". */

```

CDFgetzVarSeqData reads one value from the specified zVariable in a CDF at the current sequential value (position). After the read, the current sequential value is automatically incremented to the next value. An error is returned if the current sequential value is past the last record of the zVariable. Use CDFsetzVarSeqPos method to set the current sequential value's position.

The arguments to CDFgetzVarSeqData are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number from which to read data.
value	The buffer to store the value.

4.3.60.1. Example(s)

The following example will read the first two data values from the beginning of record number 2 (from a 2-dimensional zVariable whose data type is CDF_INT4) in a CDF.

```

.
.
.
void*      id;                /* CDF identifier. */
int  varNum;                /* The variable number from which to read data */
int  value1, value2;        /* The data value. */
int[] indices = new int[2]; /* The indices in a record. */
int  recNum;                /* The record number. */

```

```

.
.
recNum = 2;
indices[0] = 0;
indices[1] = 0;
try {
    ....
    status = CDFsetzVarSeqPos (id, varNum, recNum, indices);
    status = CDFgetzVarSeqData (id, varNum, &value1);
    object value2o;
    status = CDFgetzVarSeqData (id, varNum, out value2o);
    value2 = (int) value2o;
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.61 CDFgetzVarSeqPos

```

int CDFgetzVarSeqPos(                                     /* out -- Completion status code. */
void* id,                                                /* in -- CDF identifier. */
int varNum,                                             /* in -- Variable number. */
TYPE recNum,                                           /* out -- Record number. */
TYPE2 indices);                                       /* out -- Indices in a record. */
                                                         /* TYPE -- int* or "out int". */
                                                         /* TYPE2 -- int* or "out int[]". */

```

CDFgetzVarSeqPos returns the current sequential value (position) for sequential access for the specified zVariable in a CDF. Note that a current sequential value is maintained for each zVariable individually. Use CDFsetzVarSeqPos method to set the current sequential value.

The arguments to CDFgetzVarSeqPos are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
recNum	The zVariable record number.
indices	The dimension indices. Each element of indices receives the corresponding dimension index. For 0-dimensional zVariable, this argument is ignored, but must be presented.

4.3.61.1. Example(s)

The following example returns the location for the current sequential value (position), the record number and indices within it, from a 2-dimensional zVariable named MY_VAR in a CDF.

```

.
.

```

```

.
void*      id;          /* CDF identifier. */
int  recNum;          /* The record number. */
int[] indices;        /* The indices. */
.
.
try {
....
    indices = new int[2];
    fixed (int* pindices = indices) {
        status = CDFgetzVarSeqPos (id, CDFgetVarNum(id, "MY_VAR"), &recNum, pindices);
    }
    Or
    status = CDFgetzVarSeqPos (id, CDFgetVarNum(id, "MY_VAR"), out recNum, out indices);
...
} catch (CDFException ex) {
    ...
}.

```

4.3.62 CDFgetzVarsMaxWrittenRecNum

```

int CDFgetzVarsMaxWrittenRecNum(          /* out -- Completion status code. */
void* id,                                /* in -- CDF identifier. */
TYPE recNum);                          /* out -- Maximum record number. */
                                          /* TYPE -- int* or "out int". */

```

CDFgetzVarsMaxWrittenRecNum returns the maximum record number among all of the zVariables in a CDF. Note that this is not the number of written records but rather the maximum written record number (that is one less than the number of records). A value of negative one (-1) indicates that zVariables contain no records. The maximum record number for an individual zVariable may be acquired using the CDFgetzVarMaxWrittenRecNum method call.

Suppose there are three zVariables in a CDF: Var1, Var2, and Var3. If Var1 contains 15 records, Var2 contains 10 records, and Var3 contains 95 records, then the value returned from CDFgetzVarsMaxWrittenRecNum would be 95.

The arguments to CDFgetzVarsMaxWrittenRecNum are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
recNum	The maximum written record number.

4.3.62.1. Example(s)

The following example returns the maximum record number for all of the zVariables in a CDF.

```

.
.
void*      id;          /* CDF identifier. */
int  recNum;          /* The maximum record number. */
.

```

```

.
try {
....
    status = CDFgetzVarsMaxWrittenRecNum (id, &recNum);
    Or
    status = CDFgetzVarsMaxWrittenRecNum (id, out recNum);
...
...
} catch (CDFException ex) {
....
}.

```

4.3.63 CDFgetzVarSparseRecords

```

int CDFgetzVarSparseRecords(                                     /* out -- Completion status code. */
void* id,                                                       /* in -- CDF identifier. */
int varNum,                                                     /* in -- The variable number. */
TYPE sRecordsType);                                           /* out -- The sparse records type. */
                                                                /* TYPE -- int* or "out int". */

```

CDFgetzVarSparseRecords returns the sparse records type of the zVariable in a CDF. Refer to Section 2.12.1 for the description of sparse records.

The arguments to CDFgetzVarSparseRecords are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The variable number.
sRecordsType	The sparse records type.

4.3.63.1. Example(s)

The following example returns the sparse records type of the zVariable “MY_VAR” in a CDF.

```

.
.
.
void*      id;                                                 /* CDF identifier. */
int  sRecordsType;                                           /* The sparse records type. */
.
.
try {
....
    status = CDFgetzVarSparseRecords (id, CDFgetVarNum(id, “MY_VAR”), &sRecordsType);
    Or
    status = CDFgetzVarSparseRecords (id, CDFgetVarNum(id, “MY_VAR”), out sRecordsType);...
...

```



```

} catch (CDFException ex) {
    ...
}.

```

4.3.64 CDFhyperGetrVarData

```

int CDFhyperGetrVarData(                                /* out -- Completion status code. */
void* id,                                              /* in -- CDF identifier. */
int varNum,                                           /* in -- rVariable number. */
int recStart,                                         /* in -- Starting record number. */
int recCount,                                         /* in -- Number of records. */
int recInterval,                                     /* in -- Reading interval between records. */
int[] indices,                                       /* in -- Dimension indices of starting value. */
int[] counts,                                        /* in -- Number of values along each dimension. */
int[] intervals,                                    /* in -- Reading intervals along each dimension. */
TYPE buffer);                                       /* out -- Buffer of values. */
/* TYPE -- void*, "out string", "out string[]" or "out object" */

```

CDFhyperGetrVarData is used to read one or more values for the specified rVariable. It is important to know the variable majority of the CDF before using this method because the values placed into the data buffer will be in that majority. CDFinquireCDF can be used to determine the default variable majority of a CDF distribution. The Concepts chapter in the CDF User's Guide describes the variable majorities.

The record number starts at 0, not 1. For example, if you want to read the first 5 records, the starting record number (recStart), the number of records to read (recCount), and the record interval (recInterval) should be 0, 5, and 1, respectively. **Note:** you need to provide dummy arrays, with at least one (1) element, for indices, counts and intervals for scalar variables.

The arguments to CDFhyperGetrVarData are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number from which to read data. This number may be determined with a call to CDFgetVarNum.
recStart	The record number at which to start reading.
recCount	The number of records to read.
recInterval	The reading interval between records (e.g., an interval of 2 means read every other record).
indices	The dimension indices (within each record) at which to start reading. Each element of indices specifies the corresponding dimension index. For 0-dimensional rVariable, this argument is ignored (but must be present).
counts	The number of values along each dimension to read. Each element of counts specifies the corresponding dimension count. For 0-dimensional rVariable, this argument is ignored (but must be present).
intervals	For each dimension, the dimension interval between reading (e.g., an interval of 2 means read every other value). Each element of intervals specifies the corresponding dimension interval. For 0-dimensional rVariable, this argument is ignored (but must be present).

buffer The data holding buffer for the read values. The majority of the values in this buffer will be the same as that of the CDF. This buffer must be large to hold the values. CDFInquirerVar can be used to determine the rVariable's data type and number of elements (of that data type) at each value. If a dimensional array of strings is expected, then use **object** type.

4.3.64.1. Example(s)

The following example will read 3 records of data, starting at record number 13 (14th record), from a rVariable named Temperature. The variable is a 3-dimensional array with sizes [180,91,10] and the CDF's variable majority is ROW_MAJOR. The record variance is VARY, the dimension variances are [VARY,VARY,VARY], and the data type is CDF_REAL4. This example is similar to the CDFgetrVarData example except that it uses a single call to CDFHyperGetrVarData (rather than numerous calls to CDFgetrVarData).

```

.
.
.
void*      id;           /* CDF identifier. */
int  status;           /* Returned status code. */
float[,,]  tmp;        /* Temperature values. */
int  varN;            /* rVariable number. */
int  recStart = 13;    /* Start record number. */
int  recCount = 3;     /* Number of records to read */
int  recInterval = 1;  /* Record interval – read every record */
int[] indices = new int[] {0,0,0}; /* Dimension indices. */
int[] counts = new int[] {180,91,10}; /* Dimension counts. */
int[] intervals = new int[] {1,1,1}; /* Dimension intervals – read every value*/
.
.
try {
    varN = CDFgetrVarNum (id, "Temperature");
    tmp = new float[3,180,91,10];
    fixed (void* ptmp = tmp) {
        status = CDFHyperGetrVarData (id, varN, recStart, recCount, recInterval, indices, counts, intervals,
                                      ptmp);
    }
    Or
    status = CDFHyperGetrVarData (id, varN, recStart, recCount, recInterval, indices, counts, intervals,
                                  out tmp);
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

Note that if the CDF's variable majority had been COLUMN_MAJOR, the tmp array would have been declared float tmp[10,91,180,3] for proper indexing.

4.3.65 CDFHyperGetzVarData

```
int CDFHyperGetzVarData(           /* out -- Completion status code. */
```

```

void* id, /* in -- CDF identifier. */
int varNum, /* in -- zVariable number. */
int recStart, /* in -- Starting record number. */
int recCount, /* in -- Number of records. */
int recInterval, /* in -- Reading interval between records. */
int[] indices, /* in -- Dimension indices of starting value. */
int[] counts, /* in -- Number of values along each dimension. */
int[] intervals, /* in -- Reading intervals along each dimension. */
TYPE buffer); /* out -- Buffer of values. */
/* TYPE -- void*, "out string", "out string[]" or "out object".*/

```

CDFhyperGetzVarData is used to read one or more values for the specified zVariable. It is important to know the variable majority of the CDF before using this method because the values placed into the data buffer will be in that majority. CDFinquireCDF can be used to determine the default variable majority of a CDF distribution. The Concepts chapter in the CDF User's Guide describes the variable majorities.

The record number starts at 0, not 1. For example, if you want to read the first 5 records, the starting record number (recStart), the number of records to read (recCount), and the record interval (recInterval) should be 0, 5, and 1, respectively. **Note:** you need to provide dummy arrays, with at least one (1) element, for indices, counts and intervals for scalar variables.

The arguments to CDFhyperGetzVarData are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number from which to read data. This number may be determined with a call to CDFgetVarNum.
recStart	The record number at which to start reading.
recCount	The number of records to read.
recInterval	The reading interval between records (e.g., an interval of 2 means read every other record).
indices	The dimension indices (within each record) at which to start reading. Each element of indices specifies the corresponding dimension index. For 0-dimensional zVariable, this argument is ignored (but must be present).
counts	The number of values along each dimension to read. Each element of counts specifies the corresponding dimension count. For 0-dimensional zVariable, this argument is ignored (but must be present).
intervals	For each dimension, the dimension interval between reading (e.g., an interval of 2 means read every other value). Each element of intervals specifies the corresponding dimension interval. For 0-dimensional zVariable, this argument is ignored (but must be present).
buffer	The data holding buffer for the read values. The majority of the values in this buffer will be the same as that of the CDF. This buffer must be large to hold the values. CDFinquirezVar can be used to determine the zVariable's data type and number of elements (of that data type) at each value. If a dimensional array of strings is expected, then use object type.

4.3.65.1. Example(s)

The following example will read 3 records of data, starting at record number 13 (14th record), from a zVariable named Temperature. The variable is a 3-dimensional array with sizes [180,91,10] and the CDF's variable majority is ROW_MAJOR. The record variance is VARY, the dimension variances are [VARY,VARY,VARY], and the data type is CDF_REAL4. This example is similar to the CDFgetzVarData example except that it uses a single call to CDFhyperGetzVarData (rather than numerous calls to CDFgetzVarData).

```

.
.
.
void*      id;                /* CDF identifier. */
int  status;                 /* Returned status code. */
float[,,,] tmp;             /* Temperature values. */
int  varN;                  /* zVariable number. */
int  recStart = 13;         /* Start record number. */
int  recCount = 3;         /* Number of records to read */
int  recInterval = 1;      /* Record interval – read every record */
int[] indices = new int[] {0,0,0}; /* Dimension indices. */
int[] counts = new int[] {180,91,10}; /* Dimension counts. */
int[] intervals = new int[] {1,1,1}; /* Dimension intervals – read every value*/
.
.
try {
    varN = CDFgetzVarNum (id, "Temperature");
    tmp = new float[3,180,91,10];
    fixed (void* ptmp = tmp) {
        status = CDFhyperGetzVarData (id, varN, recStart, recCount, recInterval, indices, counts, intervals,
                                      ptmp);
    }
}
Or
    status = CDFhyperGetzVarData (id, varN, recStart, recCount, recInterval, indices, counts, intervals,
                                  out tmp);
...
...
} catch (CDFException ex) {
    ...
}.

```

Note that if the CDF's variable majority had been COLUMN_MAJOR, the tmp array would have been declared float tmp[10,91,180,3] for proper indexing.

4.3.66 CDFhyperPutrVarData

```

int CDFhyperPutrVarData(
void* id,
int varNum,
int recStart,
int recCount,
int recInterval,
int[] indices,
int[] counts,
int[] intervals,
TYPE buffer);
/* out -- Completion status code. */
/* in -- CDF identifier. */
/* in -- rVariable number. */
/* in -- Starting record number. */
/* in -- Number of records. */
/* in -- Writing interval between records. */
/* in -- Dimension indices of starting value. */
/* in -- Number of values along each dimension. */
/* in -- Writing intervals along each dimension. */
/* in -- Buffer of values. */

```

/* **TYPE** -- void*, string or object. */

CDFhyperPutrVarData is used to write one or more values from the data holding buffer to the specified rVariable. It is important to know the variable majority of the CDF before using this method because the values in the data buffer will be written using that majority. CDFinquireCDF can be used to determine the default variable majority of a CDF distribution. The Concepts chapter in the CDF User's Guide describes the variable majorities.

The record number starts at 0, not 1. For example, if you want to write 2 records (10th and 11th record), the starting record number (recStart), the number of records to write (recCount), and the record interval (recInterval) should be 9, 2, and 1, respectively. **Note:** you need to provide dummy arrays, with at least one (1) element, for indices, counts and intervals for scalar variables.

The arguments to CDFhyperPutrVarData are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number to which write data. This number may be determined with a call to CDFgetVarNum.
recStart	The record number at which to start writing.
recCount	The number of records to write.
recInterval	The interval between records for writing (e.g., an interval of 2 means write every other record).
indices	The indices (within each record) at which to start writing. Each element of indices specifies the corresponding dimension index. For 0-dimensional rVariable this argument is ignored (but must be present).
counts	The number of values along each dimension to write. Each element of counts specifies the corresponding dimension count. For 0-dimensional rVariable this argument is ignored (but must be present).
intervals	For each dimension, the interval between values for writing (e.g., an interval of 2 means write every other value). Each element of intervals specifies the corresponding dimension interval. For 0-dimensional rVariable this argument is ignored (but must be present).
buffer	The data holding buffer of values to write. The majority of the values in this buffer must be the same as that of the CDF. The values starting at memory address buffer are written to the CDF.

4.3.66.1. Example(s)

The following example writes 2 records to a rVariable named LATITUDE that is a 1-dimensional array with dimension sizes [181]. The dimension variances are [VARY], and the data type is CDF_INT2. This example is similar to the CDFputrVarData example except that it uses a single call to CDFhyperPutrVarData rather than numerous calls to CDFputrVarData.

```
.  
. .  
. . .  
void*      id;          /* CDF identifier. */  
int  status;          /* Returned status code. */
```

```

short lat; /* Latitude value. */
short[,] lats = new short[2,181]; /* Buffer of latitude values. */
int varN; /* rVariable number. */
int recStart = 0; /* Record number. */
int recCount = 2; /* Record counts. */
int recInterval = 1; /* Record interval. */
int indices = new int[] {0}; /* Dimension indices. */
int counts = new int[] {181}; /* Dimension counts. */
int intervals = new int[] {1}; /* Dimension intervals. */

.
.
try {
....
varN = CDFgetVarNum (id, "LATITUDE");
for (int i=0; i < 2; i++)
for (lat = -90; lat <= 90; lat++)
lats[i][90+lat] = (short) lat;

fixed (void* plats = lats) {
status = CDFHyperPutrVarData (id, varN, recStart, recCount, recInterval, indices, counts, intervals,
plats);
}
Or
...status = CDFHyperPutrVarData (id, varN, recStart, recCount, recInterval, indices, counts, intervals, lats);

...
} catch (CDFException ex) {
...
}.

```

4.3.67 CDFHyperPutzVarData

```

int CDFHyperPutzVarData( /* out -- Completion status code. */
void* id, /* in -- CDF identifier. */
int varNum, /* in -- zVariable number. */
int recStart, /* in -- Starting record number. */
int recCount, /* in -- Number of records. */
int recInterval, /* in -- Writing interval between records. */
int[] indices, /* in -- Dimension indices of starting value. */
int[] counts, /* in -- Number of values along each dimension. */
int[] intervals, /* in -- Writing intervals along each dimension. */
TYPE buffer); /* in -- Buffer of values. */
/* TYPE -- void*, string or object. */

```

CDFHyperPutzVarData is used to write one or more values from the data holding buffer to the specified zVariable. It is important to know the variable majority of the CDF before using this method because the values in the data buffer will be written using that majority. CDFInquireCDF can be used to determine the default variable majority of a CDF distribution. The Concepts chapter in the CDF User's Guide describes the variable majorities.

The record number starts at 0, not 1. For example, if you want to write 2 records (10th and 11th record), the starting record number (recStart), the number of records to write (recCount), and the record interval (recInterval) should be 9, 2,

and 1, respectively. **Note:** you need to provide dummy arrays, with at least one (1) element, for indices, counts and intervals for scalar variables.

The arguments to CDFhyperPutzVarData are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number to which write data. This number may be determined with a call to CDFgetVarNum.
recStart	The record number at which to start writing.
recCount	The number of records to write.
recInterval	The interval between records for writing (e.g., an interval of 2 means write every other record).
indices	The indices (within each record) at which to start writing. Each element of indices specifies the corresponding dimension index. For 0-dimensional zVariable this argument is ignored (but must be present).
counts	The number of values along each dimension to write. Each element of counts specifies the corresponding dimension count. For 0-dimensional zVariable this argument is ignored (but must be present).
intervals	For each dimension, the interval between values for writing (e.g., an interval of 2 means write every other value). Each element of intervals specifies the corresponding dimension interval. For 0-dimensional zVariable this argument is ignored (but must be present).
buffer	The data holding buffer of values to write. The majority of the values in this buffer must be the same as that of the CDF. The values starting at memory address buffer are written to the CDF.

4.3.67.1. Example(s)

The following example writes 2 records to a zVariable named LATITUDE that is a 1-dimensional array with dimension sizes [181]. The dimension variances are [VARY], and the data type is CDF_INT2. This example is similar to the CDFputzVarData example except that it uses a single call to CDFhyperPutzVarData rather than numerous calls to CDFputzVarData.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
short lat;           /* Latitude value. */
short[,] lats = new short[2,181]; /* Buffer of latitude values. */
int  varN;           /* zVariable number. */
int  recStart = 0;   /* Record number. */
int  recCount = 2;  /* Record counts. */
int  recInterval = 1; /* Record interval. */
int  indices = new int[] {0}; /* Dimension indices. */
int  counts = new int[] {181}; /* Dimension counts. */
int  intervals = new int[] {1}; /* Dimension intervals. */
```

```

.
.
try {
....
    varN = CDFgetVarNum (id, "LATITUDE");
    for (int i= 0; i < 2; i++)
        for (lat = -90; lat <= 90; lat++)
            lats[i][90+lat] = (short) lat;

    fixed (void* plats = lats) {
        status = CDFHyperPutzVarData (id, varN, recStart, recCount, recInterval, indices, counts, intervals,
                                     plats);
    }
} Or
...status = CDFHyperPutzVarData (id, varN, recStart, recCount, recInterval, indices, counts, intervals, lats);

...
} catch (CDFException ex) {
    ...
}.

```

4.3.68 CDFInquirerVar

```

int CDFInquirezVar(
void* id,
int varNum,
out string varName,
TYPE dataType,
TYPE numElements,
TYPE numDims,
TYPE2 dimSizes,
TYPE recVariance,
TYPE2 dimVariances);

```

/ out -- Completion status code. */*
/ in -- CDF identifier. */*
/ in -- rVariable number. */*
/ out -- rVariable name. */*
/ out -- Data type. */*
/ out -- Number of elements (of the data type). */*
/ out -- Number of dimensions. */*
/ out -- Dimension sizes */*
/ out -- Record variance. */*
/ out -- Dimension variances. */*
/ TYPE -- int* or "out int". */*
/ TYPE2 -- int* or "out int[]". */*

CDFInquirerVar is used to inquire about the specified rVariable. This method would normally be used before reading rVariable values (with CDFgetrVarData or CDFHyperGetrVarData) to determine the data type and number of elements of that data type.

The arguments to CDFInquirezVar are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The number of the rVariable to inquire. This number may be determined with a call to CDFgetVarNum (see Section 4.3.40).
varName	The rVariable's name.
dataType	The data type of the rVariable. The data types are defined in Section 2.6.

numElements	The number of elements of the data type at each rVariable value. For character data types (CDF_CHAR and CDF_UCHAR), this is the number of characters in the string. (Each value consists of the entire string.) For all other data types, this will always be one (1) - multiple elements at each value are not allowed for non-character data types.
numDims	The number of dimensions.
dimSizes	The dimension sizes. It is a 1-dimensional array, containing one element per dimension. Each element of dimSizes receives the corresponding dimension size. For 0-dimensional zVariables this argument is ignored (but must be present).
recVariance	The record variance. The record variances are defined in Section 2.10.
dimVariances	The dimension variances. Each element of dimVariances receives the corresponding dimension variance. The dimension variances are described in Section 2.10. For 0-dimensional zVariables this argument is ignored (but a placeholder is necessary).

4.3.68.1. Example(s)

The following example returns information about a rVariable named HEAT_FLUX in a CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
string     varName;    /* rVariable name. */
int  dataType;       /* Data type of the rVariable. */
int  numElems;       /* Number of elements (of data type). */
int  recVary;        /* Record variance. */
int  numDims;        /* Number of dimensions. */
int[] dimSizes;      /* Dimension sizes */
int[] dimVarys;      /* Dimension variances */
.
.
try {
....
    dimSizes = new int[CDF_MAX_DIMS];
    dimVarys = new int[CDF_MAX_DIMS];
    fixed (int* pdimSizes = dimSizes, pdimVarys = dimVarys) {
        status = CDFinquirerVar(id, CDFgetVarNum(id,"HEAT_FLUX"), out varName, &dataType,
                                &numElems, &numDims, pdimSizes, &recVary, pdimVarys);
    }
    Or
    status = CDFinquirerVar(id, CDFgetVarNum(id,"HEAT_FLUX"), out varName, out dataType,
                            out numElems, out numDims, out dimSizes, out recVary, out dimVarys);
....
} catch (CDFException ex) {
....
}.

```

4.3.69 CDFinquirezVar

```
int CDFinquirezVar(                                     /* out -- Completion status code. */
void* id,                                              /* in -- CDF identifier. */
int varNum,                                           /* in -- zVariable number. */
out string varName,                                   /* out -- zVariable name. */
TYPE dataType,                                       /* out -- Data type. */
TYPE numElements,                                    /* out -- Number of elements (of the data type). */
TYPE numDims,                                        /* out -- Number of dimensions. */
TYPE2 dimSizes,                                     /* out -- Dimension sizes */
TYPE recVariance,                                   /* out -- Record variance. */
TYPE2 dimVariances);                               /* out -- Dimension variances. */
                                                    /* TYPE -- int* or "out int". */
                                                    /* TYPE2 -- int* or "out int[]". */
```

CDFinquirezVar is used to inquire about the specified zVariable. This method would normally be used before reading zVariable values (with CDFgetzVarData or CDFhyperGetzVarData) to determine the data type and number of elements of that data type.

The arguments to CDFinquirezVar are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The number of the zVariable to inquire. This number may be determined with a call to CDFgetVarNum (see Section 4.3.40).
varName	The zVariable's name.
dataType	The data type of the zVariable. The data types are defined in Section 2.6.
numElements	The number of elements of the data type at each zVariable value. For character data types (CDF_CHAR and CDF_UCHAR), this is the number of characters in the string. (Each value consists of the entire string.) For all other data types, this will always be one (1) - multiple elements at each value are not allowed for non-character data types.
numDims	The number of dimensions.
dimSizes	The dimension sizes. It is a 1-dimensional array, containing one element per dimension. Each element of dimSizes receives the corresponding dimension size. For 0-dimensional zVariables this argument is ignored (but must be present).
recVariance	The record variance. The record variances are defined in Section 2.10.
dimVariances	The dimension variances. Each element of dimVariances receives the corresponding dimension variance. The dimension variances are described in Section 2.10. For 0-dimensional zVariables this argument is ignored (but a placeholder is necessary).

4.3.69.1. Example(s)

The following example returns information about an zVariable named HEAT_FLUX in a CDF.

```

.
.
.
void*      id;                /* CDF identifier. */
int  status;                 /* Returned status code. */
string    varName;          /* zVariable name. */
int  dataType;              /* Data type of the zVariable. */
int  numElems;              /* Number of elements (of data type). */
int  recVary;               /* Record variance. */
int  numDims;               /* Number of dimensions. */
int[] dimSizes;             /* Dimension sizes */
int[] dimVarys;             /* Dimension variances */
.
.
try {
    ....
    dimSizes = new int[CDF_MAX_DIMS];
    dimVarys = new int[CDF_MAX_DIMS];
    fixed (int* pdimSizes = dimSizes, pdimVarys = dimVarys) {
        status = CDFinquirezVar(id, CDFgetVarNum(id,"HEAT_FLUX"), out varName, &dataType,
                                &numElems, &numDims, pdimSizes, &recVary, pdimVarys);
    }
    Or
    status = CDFinquirezVar(id, CDFgetVarNum(id,"HEAT_FLUX"), out varName, out dataType,
                            out numElems, out numDims, out dimSizes, out recVary, out dimVarys);
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.70 CDFputrVarData

```

int CDFputrVarData(          /* out -- Completion status code. */
void* id,                   /* in -- CDF identifier. */
int varNum,                 /* in -- Variable number. */
int recNum,                 /* in -- Record number. */
int[] indices,              /* in -- Dimension indices. */
TYPE value);               /* in -- Data value. */
                             /* TYPE -- void*, string or object. */

```

CDFputrVarData writes a single data value to the specified index, the location of the element, in the given record of the specified rVariable in a CDF.

The arguments to CDFputrVarData are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.

recNum	The record number.
indices	The dimension indices within the record.
value	The data value.

4.3.70.1. Example(s)

The following example will write two data values, the first and the fifth element, in Record 0 from rVariable “MY_VAR”, a 2-dimensional (2 by 3), CDF_DOUBLE type variable, in a row-major CDF. The first put operation passes the pointer of the data value, while the second operation passes the data value as an object.

```

.
.
.
void*      id;          /* CDF identifier. */
int  varNum;          /* rVariable number. */
int  recNum;          /* The record number. */
int[] indices = new int[2]; /* The dimension indices. */
double  value1, value2; /* The data values. */
.
.
try {
    ....
    varNum = CDFgetVarNum (id, “MY_VAR”);
    recNum = 0;
    indices[0] = 0;
    indices[1] = 0;
    value1 = 10.1;
    status = CDFputrVarData (id, varNum, recNum, indices, &value1);
    indices[0] = 1;
    indices[1] = 1;
    value2 = 20.2;
    status = CDFputrVarData (id, varNum, recNum, indices, value2);
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.71 CDFputrVarPadValue

```

int CDFputrVarPadValue(          /* out -- Completion status code. */
void* id,                       /* in -- CDF identifier. */
int varNum,                     /* in -- Variable number. */
TYPE value);                   /* in -- Pad value. */
/* TYPE -- void*, string or object */

```

CDFputrVarPadValue specifies the pad value for the specified rVariable in a CDF. A rVariable's pad value may be specified (or respecified) at any time without affecting already written values (including where pad values were used). The Concepts chapter in the CDF User's Guide describes variable pad values.

The arguments to CDFputrVarPadValue are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
value	The pad value.

4.3.71.1. Example(s)

The following example sets the pad value to -9999 for rVariable "MY_VAR", a CDF_INT4 type variable, and "*****" for another rVariable "MY_VAR2", a CDF_CHAR type with a number of elements of five (5), in a CDF.

```
.
.
.
void*      id;                /* CDF identifier. */
int  padValue1 = -9999;      /* An int pad value. */
string  padValue2 = "*****"; /* A string pad value. */
.
.
try {
    ....
    status = CDFputrVarPadValue (id, CDFgetVarNum (id, "MY_VAR"), padValue1);
    Or
    status = CDFputrVarPadValue (id, CDFgetVarNum (id, "MY_VAR"), &padValue1);

    status = CDFputrVarPadValue (id, CDFgetVarNum (id, "MY_VAR2"), padValue2);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
.
```

4.3.72 CDFputrVarRecordData

```
int CDFputrVarRecordData(                /* out -- Completion status code. */
void* id,                                /* in -- CDF identifier. */
int varNum,                              /* in -- Variable number. */
int recNum,                              /* in -- Record number. */
TYPE buffer);                            /* in -- Record data. */
/* TYPE -- void*, string, string[] or object.*/"
```

CDFputrVarRecordData writes an entire record at a given record number for the specified rVariable in a CDF. The buffer should hold the entire data values for the variable. The data values in the buffer should be in the order that corresponds to the variable majority defined for the CDF.

The arguments to CDFputrVarRecordData are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
recNum	The record number.
buffer	The buffer holding the entire record values.

4.3.72.1. Example(s)

The following example will write one full record (numbered 2) from rVariable “MY_VAR”, a 2-dimension (2 by 3), CDF_INT4 type variable, in a CDF. The variable’s dimension variances are all VARY.

```

.
.
.
void*      id;          /* CDF identifier. */
int  varNum;          /* rVariable number. */
int[,] buffer = new[2,3] {{1,2,3},{4,5,6}}; /* The data holding buffer. */
.
.
try {
....
    varNum = CDFvarNum(id,"MY_VAR");
    status = CDFputrVarRecordData (id, varNum, 2, buffer);
Or
    fixed (void* pBuffer = buffer) {
        status = CDFputrVarRecordData (id, varNum, 2, pBuffer);
    }
...
...
} catch (CDFException ex) {
...
}.

```

4.3.73 CDFputrVarSeqData

```

int CDFputrVarSeqData( /* out -- Completion status code. */
void* id,             /* in -- CDF identifier. */
int varNum,          /* in -- Variable number. */
TYPE value);        /* in -- Data value. */
/* TYPE -- void*, string or object. */

```

CDFputrVarSeqData writes one value to the specified rVariable in a CDF at the current sequential value (position) for that variable. After the write, the current sequential value is automatically incremented to the next value. Use CDFsetrVarSeqPos method to set the current sequential value (position).

The arguments to CDFputrVarSeqData are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
value	The buffer holding the data value.

4.3.73.1. Example(s)

The following example will write two data values starting at record number 2 from a 2-dimensional rVariable whose data type is CDF_INT4. The first write will pass in a pointer from the data value, while the second write will pass in the data value object directly.

```

.
.
.
void*      id;           /* CDF identifier. */
int  varNum;           /* The variable number. */
int  value1, value2;   /* The data value. */
int[] indices = new int[2]; /* The indices in a record. */
int  recNum;          /* The record number. */
.
.
recNum = 2;
indices[0] = 1;
indices[1] = 2;
try {
    ....
    value1 = 10;
    value2 = -20.
    status = CDFsetrVarSeqPos (id, varNum, recNum, indices);
    status = CDFputrVarSeqData (id, varNum, &value1);
    status = CDFputrVarSeqData (id, varNum, value2);
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.74 CDFputzVarData

```

int CDFputzVarData(           /* out -- Completion status code. */
void* id,                   /* in -- CDF identifier. */
int varNum,                 /* in -- Variable number. */

```

```

int recNum,                               /* in -- Record number. */
int[] indices,                             /* in -- Dimension indices. */
TYPE value);                             /* in -- Data value. */
                                           /* TYPE -- void*, string or object. */

```

CDFputzVarData writes a single data value to the specified index, the location of the element, in the given record of the specified zVariable in a CDF.

The arguments to CDFputzVarData are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
recNum	The record number.
indices	The dimension indices within the record.
value	The data value.

4.3.74.1. Example(s)

The following example will write two data values, the first and the fifth element, in Record 0 from zVariable “MY_VAR”, a 2-dimensional (2 by 3), CDF_DOUBLE type variable, in a row-major CDF. The first put operation passes the pointer of the data value, while the second operation passes the data value as an object.

```

.
.
.
void*      id;                               /* CDF identifier. */
int  varNum;                               /* zVariable number. */
int  recNum;                               /* The record number. */
int[] indices = new int[2];                /* The dimension indices. */
double  value1, value2;                    /* The data values. */
.
.
try {
    ....
    varNum = CDFgetVarNum (id, "MY_VAR");
    recNum = 0;
    indices[0] = 0;
    indices[1] = 0;
    value1 = 10.1;
    status = CDFputzVarData (id, varNum, recNum, indices, &value1);
    indices[0] = 1;
    indices[1] = 1;
    value2 = 20.2;
    status = CDFputzVarData (id, varNum, recNum, indices, value2);
    ...
    ...
} catch (CDFException ex) {
    ...

```



```
}.
```

4.3.75 CDFputzVarPadValue

```
int CDFputzVarPadValue(                                     /* out -- Completion status code. */  
void* id,                                                 /* in -- CDF identifier. */  
int varNum,                                              /* in -- Variable number. */  
TYPE value);                                           /* in -- Pad value. */  
/* TYPE -- void*, string or object */
```

CDFputzVarPadValue specifies the pad value for the specified zVariable in a CDF. A zVariable's pad value may be specified (or respecified) at any time without affecting already written values (including where pad values were used). The Concepts chapter in the CDF User's Guide describes variable pad values.

The arguments to CDFputzVarPadValue are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
value	The pad value.

4.3.75.1. Example(s)

The following example sets the pad value to -9999 for zVariable "MY_VAR", a CDF_INT4 type variable, and "*****" for another zVariable "MY_VAR2", a CDF_CHAR type with a number of elements of five (5), in a CDF.

```
.  
. .  
void* id; /* CDF identifier. */  
int padValue1 = -9999; /* An int pad value. */  
string padValue2 = "*****"; /* A string pad value. */  
. .  
try {  
    ....  
    status = CDFputzVarPadValue (id, CDFgetVarNum (id, "MY_VAR"), padValue1);  
    Or  
    status = CDFputzVarPadValue (id, CDFgetVarNum (id, "MY_VAR"), &padValue1);  
  
    status = CDFputzVarPadValue (id, CDFgetVarNum (id, "MY_VAR2"), padValue2);  
    ...  
    ...  
} catch (CDFException ex) {  
    ...  
}.
```

4.3.76 CDFputzVarRecordData

```
int CDFputzVarRecordData(                                     /* out -- Completion status code. */
void* id,                                                    /* in -- CDF identifier. */
int varNum,                                                 /* in -- Variable number. */
int recNum,                                                 /* in -- Record number. */
TYPE buffer);                                              /* in -- Record data. */
                                                         /* TYPE -- void*, string, string[] or object. */
```

CDFputzVarRecordData writes an entire record at a given record number for the specified zVariable in a CDF. The buffer should hold the entire data values for the variable. The data values in the buffer should be in the order that corresponds to the variable majority defined for the CDF.

The arguments to CDFputzVarRecordData are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
recNum	The record number.
buffer	The buffer holding the entire record values.

4.3.76.1. Example(s)

The following example will write one full record (numbered 2) from zVariable “MY_VAR”, a 2-dimension (2 by 3), CDF_INT4 type variable, in a CDF. The variable’s dimension variances are all VARY.

```
.
.
.
void*      id;                                           /* CDF identifier. */
int  varNum;                                           /* zVariable number. */
int[,] buffer = new[2,3] {{1,2,3},{4,5,6}};           /* The data holding buffer. */
.
.
try {
    ....
    varNum = CDFvarNum(id,"MY_VAR");
    status = CDFputzVarRecordData (id, varNum, 2, buffer);
Or
    fixed (void* pBuffer = buffer) {
        status = CDFputzVarRecordData (id, varNum, 2, pBuffer);
    }
    ...
} catch (CDFException ex) {
    ...
}.
```

4.3.77 CDFputzVarSeqData

```
int CDFputzVarSeqData(                                     /* out -- Completion status code. */
void* id,                                                 /* in -- CDF identifier. */
int varNum,                                              /* in -- Variable number. */
TYPE value);                                           /* in -- Data value. */
                                                    /* TYPE -- void*, string or object. */
```

CDFputzVarSeqData writes one value to the specified zVariable in a CDF at the current sequential value (position) for that variable. After the write, the current sequential value is automatically incremented to the next value. Use CDFsetzVarSeqPos method to set the current sequential value (position).

The arguments to CDFputzVarSeqData are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
value	The buffer holding the data value.

4.3.77.1. Example(s)

The following example will write two data values starting at record number 2 from a 2-dimensional zVariable whose data type is CDF_INT4. The first write will pass in a pointer from the data value, while the second write will pass in the data value object directly.

```
.
.
.
void*      id;                                           /* CDF identifier. */
int  varNum;                                           /* The variable number. */
int  value1, value2;                                    /* The data value. */
int[] indices = new int[2];                             /* The indices in a record. */
int  recNum;                                           /* The record number. */
.
.
recNum = 2;
indices[0] = 1;
indices[1] = 2;
try {
    ....
    value1 = 10;
    value2 = -20.
    status = CDFsetzVarSeqPos (id, varNum, recNum, indices);
    status = CDFputzVarSeqData (id, varNum, &value1);
    status = CDFputzVarSeqData (id, varNum, value2);
    ...
    ...
} catch (CDFException ex) {
```

```
...
}.
```

4.3.78 CDFrenamerVar

```
int CDFrenamerVar(                                     /* out -- Completion status code. */
void* id,                                             /* in -- CDF identifier. */
int varNum,                                          /* in -- rVariable number. */
string varName);                                    /* in -- New name. */
```

CDFrenamerVar is used to rename an existing rVariable. A variable (rVariable or zVariable) with the same name must not already exist in the CDF.

The arguments to CDFrenamerVar are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The number of the rVariable to rename. This number may be determined with a call to CDFgetVarNum.
varName	The new rVariable name. This may be at most CDF_VAR_NAME_LEN256 characters. Variable names are case-sensitive.

4.3.78.1. Example(s)

In the following example the rVariable named TEMPERATURE is renamed to TMP (if it exists). Note that if CDFgetVarNum returns a value less than zero (0) then that value is not an rVariable number but rather an error code.

```
.
.
.
void* id;                                           /* CDF identifier. */
int status;                                        /* Returned status code. */
int varNum;                                        /* zVariable number. */
.
.
try {
...
varNum = CDFgetVarNum (id, "TEMPERATURE");
status = CDFrenamerVar (id, varNum, "TMP");
...
...
} catch (CDFException ex) {
...
}.
```



```

int firstRec,          /* in -- First record number. */
int lastRec);        /* in -- Last record number. */

```

CDFsetrVarAllocBlockRecords specifies a range of records to be allocated (not written) for the specified rVariable in a CDF. This operation is only applicable to uncompressed rVariable in single-file CDFs. Refer to the CDF User’s Guide for the descriptions of allocating variable records.

The arguments to CDFsetrVarAllocBlockRecords are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
firstRec	The first record number to allocate.
lastRec	The last record number to allocate.

4.3.80.1. Example(s)

The following example allocates 10 records, from record numbered 10 to 19, for rVariable “MY_VAR” in a CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  firstRec, lastRec; /* The first/last record numbers. */
.
.
firstRec = 10;
lastRec = 19;
try {
    ....
    status = CDFsetrVarAllocBlockRecords (id, CDFgetVarNum(id, "MY_VAR"), firstRec, lastRec);
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.81 CDFsetrVarAllocRecords

```

int CDFsetrVarAllocRecords(          /* out -- Completion status code. */
void* id,                            /* in -- CDF identifier. */
int varNum,                          /* in -- Variable number. */
int numRecs);                       /* in -- Number of records. */

```

CDFsetrVarAllocRecords specifies a number of records to be allocated (not written) for the specified rVariable in a CDF. The records are allocated beginning at record number zero (0). This operation is only applicable to uncompressed rVariable in single-file CDFs. Refer to the CDF User’s Guide for the descriptions of allocating variable records.

The arguments to CDFsetrVarAllocRecords are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
numRecs	The number of records to allocate.

4.3.81.1. Example(s)

The following example allocates 100 records, from record numbered 0 to 99, for rVariable “MY_VAR” in a CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  numRecs;         /* The number of records. */
.
.
numRecs = 100;
try {
  ....
  status = CDFsetrVarAllocRecords (id, CDFgetVarNum(id, "MY_VAR"), numRecs);
  ...
  ...
} catch (CDFException ex) {
  ...
}.
.
```

4.3.82 CDFsetrVarBlockingFactor

```
int CDFsetrVarBlockingFactor(          /* out -- Completion status code. */
void* id,                             /* in -- CDF identifier. */
int varNum,                           /* in -- Variable number. */
int bf);                              /* in -- Blocking factor. */
```

CDFsetrVarBlockingFactor specifies the blocking factor (number of records allocated) for the specified rVariable in a CDF. Refer to the CDF User’s Guide for a description of the blocking factor.

The arguments to CDFsetrVarBlockingFactor are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
bf	The blocking factor. A value of zero (0) indicates that the default blocking factor is being used.

4.3.82.1. Example(s)

The following example sets the blocking factor to 100 records for rVariable “MY_VAR” in a CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  bf;        /* The blocking factor. */
.
.
bf = 100;
try {
    ....
    status = CDFsetrVarBlockingFactor (id, CDFgetVarNum(id, “MY_VAR”), bf);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
.
```

4.3.83 CDFsetrVarCacheSize

```
int CDFsetrVarCacheSize(          /* out -- Completion status code. */
void* id,                        /* in -- CDF identifier. */
int varNum,                      /* in -- Variable number. */
int numBuffers);                /* in -- Number of cache buffers. */
```

CDFsetrVarCacheSize specifies the number of cache buffers being for the rVariable in a CDF. This operation is not applicable to a single-file CDF. Refer to the CDF User’s Guide for description about caching scheme used by the CDF library.

The arguments to CDFsetrVarCacheSize are defined as follows:

- | | |
|------------|---|
| id | The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF. |
| varNum | The rVariable number. |
| numBuffers | The number of cache buffers. |

4.3.83.1. Example(s)

The following example sets the number of cache buffers to 10 for rVariable “MY_VAR” in a CDF.

```
.
```



```

.
.
void*      id;          /* CDF identifier. */
int  numBuffers;      /* The number of cache buffers. */
.
.
numBuffers = 10;
try {
    ....
    status = CDFsetrVarCacheSize (id, CDFgetVarNum(id, "MY_VAR"), numBuffers);
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.84 CDFsetrVarCompression

```

int CDFsetrVarCompression( /* out -- Completion status code. */
void* id,                 /* in -- CDF identifier. */
int varNum,               /* in -- Variable number. */
int cType,                /* in -- Compression type. */
int[] cParms);           /* in -- Compression parameters. */

```

CDFsetrVarCompression specifies the compression type/parameters for the specified rVariable in a CDF. Refer to Section 2.11 for a description of the CDF supported compression types/parameters.

The arguments to CDFsetrVarCompression are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
cType	The compression type.
cParms	The compression parameters.

4.3.84.1. Example(s)

The following example sets the compression to GZIP.6 for rVariable "MY_VAR" in a CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  cType;           /* The compression type. */
int[] cParms = new int[1]; /* The compression parameters. */
.
.

```

```

cType = GZIP_COMPRESSION;
cParms[0] = 6;
try {
    ....
    status = CDFsetrVarCompression (id, CDFgetVarNum (id, "MY_VAR"), cType, cParms);
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.85 CDFsetrVarDataSpec

```

int CDFsetrVarDataSpec(                                     /* out -- Completion status code. */
void* id,                                                  /* in -- CDF identifier. */
int varNum,                                               /* in -- Variable number. */
int dataType)                                             /* in -- Data type. */

```

CDFsetrVarDataSpec respecifies the data type of the specified rVariable in a CDF. The variable's data type cannot be changed if the new data type is not equivalent (type having a different data size) to the old data type and any values (including the pad value) have been written. Data specifications are considered equivalent if the data types are equivalent. Refer to the CDF User's Guide for equivalent data types.

The arguments to CDFsetrVarDataSpec are defined as follows:

- | | |
|----------|---|
| id | The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF. |
| varNum | The rVariable number. |
| dataType | The new data type. |

4.3.85.1. Example(s)

The following example respecifies the data type to CDF_INT2 (from its original CDF_UINT2) for rVariable "MY_VAR" in a CDF.

```

.
.
.
void* id;          /* CDF identifier. */
int dataType;     /* The data type. */
.
.
dataType = CDF_INT2;
try {
    ....
    status = CDFsetrVarDataSpec (id, CDFgetVarNum (id, "MY_VAR"), dataType);
    ...
}

```

```

...
} catch (CDFException ex) {
...
}.

```

4.3.86 CDFsetrVarDimVariances

```

int CDFsetrVarDimVariances(                                     /* out -- Completion status code. */
void* id,                                                       /* in -- CDF identifier. */
int varNum,                                                    /* in -- Variable number. */
int[] dimVarys);                                              /* in -- Dimension variances. */

```

CDFsetrVarDimVariances respecifies the dimension variances of the specified rVariable in a CDF. For 0-dimensional rVariable, this operation is not applicable. The dimension variances are described in Section 2.10.

The arguments to CDFsetrVarDimVariances are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
dimVarys	The dimension variances.

4.3.86.1. Example(s)

The following example resets the dimension variances to true (VARY) and true (VARY) for rVariable “MY_VAR”, a 2-dimensional variable, in a CDF.

```

.
.
.
void* id;                                                       /* CDF identifier. */
int varNum;                                                    /* rVariable number. */
int[] dimVarys = new int[] {VARY, VARY};                      /* The dimension variances. */
.
.
try {
...
varNum = CDFgetVarNum (id, “MY_VAR”);
status = CDFsetrVarDimVariances (id, varNum, dimVarys);
...
...
} catch (CDFException ex) {
...
}.

```



```
int varNum,          /* in -- Variable number. */
int recVary);       /* in -- Record variance. */
```

CDFsetrVarRecVariance specifies the record variance of the specified rVariable in a CDF. The record variances are described in Section 2.10.

The arguments to CDFsetrVarRecVariance are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
recVary	The record variance.

4.3.88.1. Example(s)

The following example sets the record variance to VARY (from NOVARY) for rVariable “MY_VAR” in a CDF.

```
.
.
.
void* id;          /* CDF identifier. */
int recVary;      /* The record variance. */
.
.
recVary = VARY;
try {
    ....
    status = CDFsetrVarRecVariance (id, CDFgetVarNum (id, "MY_VAR"), recVary);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
.
```

4.3.89 CDFsetrVarReservePercent

```
int CDFsetrVarReservePercent( /* out -- Completion status code. */
void* id,                    /* in -- CDF identifier. */
int varNum,                  /* in -- Variable number. */
int percent);                /* in -- Reserve percentage. */
```

CDFsetrVarReservePercent specifies the compression reserve percentage being used for the specified rVariable in a CDF. This operation only applies to compressed rVariables. Refer to the CDF User’s Guide for a description of the reserve scheme used by the CDF library.

The arguments to CDFsetrVarReservePercent are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
percent	The reserve percentage.

4.3.89.1. Example(s)

The following example sets the reserve percentage to 10 for rVariable “MY_VAR” in a CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  percent;         /* The reserve percentage. */
.
.
percent = 10;
try {
    ....
    status = CDFsetrVarReservePercent (id, CDFgetVarNum (id, “MY_VAR”), percent);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
.

```

4.3.90 CDFsetrVarsCacheSize

```

int CDFsetrVarsCacheSize(          /* out -- Completion status code. */
void* id,                          /* in -- CDF identifier. */
int numBuffers);                  /* in -- Number of cache buffers. */

```

CDFsetrVarsCacheSize specifies the number of cache buffers to be used for all of the rVariable files in a CDF. This operation is not applicable to a single-file CDF. The Concepts chapter in the CDF User's Guide describes the caching scheme used by the CDF library.

The arguments to CDFsetrVarsCacheSize are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
numBuffers	The number of buffers.

4.3.90.1. Example(s)

The following example sets the number of cache buffers to 10 for all rVariables in a CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  numBuffers;      /* The number of cache buffers. */
.
.
numBuffers = 10;
try {
    ....
    status = CDFsetrVarsCacheSize (id, numBuffers);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
.
```

4.3.91 CDFsetrVarSeqPos

```
int CDFsetrVarSeqPos(          /* out -- Completion status code. */
void* id,                    /* in -- CDF identifier. */
int varNum,                  /* in -- Variable number. */
int recNum,                  /* in -- Record number. */
int[] indices);              /* in -- Indices in a record. */
```

CDFsetrVarSeqPos specifies the current sequential value (position) for sequential access for the specified rVariable in a CDF. Note that a current sequential value is maintained for each rVariable individually. Use CDFgetrVarSeqPos method to get the current sequential value.

The arguments to CDFsetrVarSeqPos are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
recNum	The rVariable record number.
indices	The dimension indices. Each element of indices receives the corresponding dimension index. For 0-dimensional rVariable, this argument is ignored, but must be presented.

4.3.91.1. Example(s)

The following example sets the current sequential value to the first value element in record number 2 for a rVariable, a 2-dimensional variable, in a CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  varNum;          /* The variable number. */
int  recNum;          /* The record number. */
int[] indices = new int[2]; /* The indices. */
.
.
recNum = 2;
indices[0] = 0;
indices[1] = 0;
try {
    status = CDFsetrVarSeqPos (id, varNum, recNum, indices);
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.92 CDFsetrVarSparseRecords

```

int CDFsetrVarSparseRecords( /* out -- Completion status code. */
void* id,                  /* in -- CDF identifier. */
int varNum,                /* in -- The variable number. */
int sRecordsType);        /* in -- The sparse records type. */

```

CDFsetrVarSparseRecords specifies the sparse records type of the specified rVariable in a CDF. Refer to Section 2.12.1 for the description of sparse records.

The arguments to CDFsetrVarSparseRecords are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The rVariable number.
sRecordsType	The sparse records type.

4.3.92.1. Example(s)

The following example sets the sparse records type to PAD_SPARSERECORDS from its original type for rVariable “MY_VAR” in a CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  sRecordsType;     /* The sparse records type. */
.

```



```

.
sRecordsType = PAD_ SPARSERECORDS;
try {
    status = CDFsetzVarSparseRecords (id, CDFgetVarNum(id, "MY_VAR"), sRecordsType);
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.93 CDFsetzVarAllocBlockRecords

```

int CDFsetzVarAllocBlockRecords(          /* out -- Completion status code. */
void* id,                                /* in -- CDF identifier. */
int varNum,                              /* in -- Variable number. */
int firstRec,                            /* in -- First record number. */
int lastRec);                            /* in -- Last record number. */

```

CDFsetzVarAllocBlockRecords specifies a range of records to be allocated (not written) for the specified zVariable in a CDF. This operation is only applicable to uncompressed zVariable in single-file CDFs. Refer to the CDF User's Guide for the descriptions of allocating variable records.

The arguments to CDFsetzVarAllocBlockRecords are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
firstRec	The first record number to allocate.
lastRec	The last record number to allocate.

4.3.93.1. Example(s)

The following example allocates 10 records, from record numbered 10 to 19, for zVariable "MY_VAR" in a CDF.

```

.
.
.
void* id;                                /* CDF identifier. */
int firstRec, lastRec;                  /* The first/last record numbers. */
.
.
firstRec = 10;
lastRec = 19;
try {
    ....
    status = CDFsetzVarAllocBlockRecords (id, CDFgetVarNum(id, "MY_VAR"), firstRec, lastRec);
    ...
}

```

```

...
} catch (CDFException ex) {
...
}.

```

4.3.94 CDFsetzVarAllocRecords

```

int CDFsetzVarAllocRecords(                                     /* out -- Completion status code. */
void* id,                                                       /* in -- CDF identifier. */
int varNum,                                                    /* in -- Variable number. */
int numRecs);                                                 /* in -- Number of records. */

```

CDFsetzVarAllocRecords specifies a number of records to be allocated (not written) for the specified zVariable in a CDF. The records are allocated beginning at record number zero (0). This operation is only applicable to uncompressed zVariable in single-file CDFs. Refer to the CDF User’s Guide for the descriptions of allocating variable records.

The arguments to CDFsetzVarAllocRecords are defined as follows:

- | | |
|---------|---|
| id | The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF. |
| varNum | The zVariable number. |
| numRecs | The number of records to allocate. |

4.3.94.1. Example(s)

The following example allocates 100 records, from record numbered 0 to 99, for zVariable “MY_VAR” in a CDF.

```

.
.
.
void* id;                                                       /* CDF identifier. */
int numRecs;                                                  /* The number of records. */
.
.
numRecs = 100;
try {
...
status = CDFsetzVarAllocRecords (id, CDFgetVarNum(id, “MY_VAR”), numRecs);
...
...
} catch (CDFException ex) {
...
}.

```

4.3.95 CDFsetzVarBlockingFactor

```
int CDFsetzVarBlockingFactor(          /* out -- Completion status code. */
void* id,                             /* in -- CDF identifier. */
int varNum,                           /* in -- Variable number. */
int bf);                              /* in -- Blocking factor. */
```

CDFsetzVarBlockingFactor specifies the blocking factor (number of records allocated) for the specified zVariable in a CDF. Refer to the CDF User's Guide for a description of the blocking factor.

The arguments to CDFsetzVarBlockingFactor are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
bf	The blocking factor. A value of zero (0) indicates that the default blocking factor is being used.

4.3.95.1. Example(s)

The following example sets the blocking factor to 100 records for zVariable "MY_VAR" in a CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int bf;             /* The blocking factor. */
.
.
bf = 100;
try {
    ....
    status = CDFsetzVarBlockingFactor (id, CDFgetVarNum(id, "MY_VAR"), bf);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
.
```

4.3.96 CDFsetzVarCacheSize

```
int CDFsetzVarCacheSize(          /* out -- Completion status code. */
void* id,                         /* in -- CDF identifier. */
int varNum,                       /* in -- Variable number. */
int numBuffers);                 /* in -- Number of cache buffers. */
```

CDFsetzVarCacheSize specifies the number of cache buffers being for the zVariable in a CDF. This operation is not applicable to a single-file CDF. Refer to the CDF User's Guide for description about caching scheme used by the CDF library.

The arguments to CDFsetzVarCacheSize are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
numBuffers	The number of cache buffers.

4.3.96.1. Example(s)

The following example sets the number of cache buffers to 10 for zVariable "MY_VAR" in a CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  numBuffers;      /* The number of cache buffers. */
.
.
numBuffers = 10;
try {
    ...
    status = CDFsetzVarCacheSize (id, CDFgetVarNum(id, "MY_VAR"), numBuffers);
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.97 CDFsetzVarCompression

```

int CDFsetzVarCompression(          /* out -- Completion status code. */
void* id,                          /* in -- CDF identifier. */
int varNum,                        /* in -- Variable number. */
int cType,                         /* in -- Compression type. */
int[] cParms);                    /* in -- Compression parameters. */

```

CDFsetzVarCompression specifies the compression type/parameters for the specified zVariable in a CDF. Refer to Section 2.11 for a description of the CDF supported compression types/parameters.

The arguments to CDFsetzVarCompression are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
----	---

varNum	The zVariable number.
cType	The compression type.
cParms	The compression parameters.

4.3.97.1. Example(s)

The following example sets the compression to GZIP.6 for zVariable “MY_VAR” in a CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  cType;          /* The compression type. */
int[] cParms = new int[1]; /* The compression parameters. */
.
.
cType = GZIP_COMPRESSION;
cParms[0] = 6;
try {
    ....
    status = CDFsetzVarCompression (id, CDFgetVarNum (id, “MY_VAR”), cType, cParms);
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.98 CDFsetzVarDataSpec

```

int CDFsetzVarDataSpec(          /* out -- Completion status code. */
void* id,                      /* in -- CDF identifier. */
int varNum,                    /* in -- Variable number. */
int dataType)                  /* in -- Data type. */

```

CDFsetzVarDataSpec respecifies the data type of the specified zVariable in a CDF. The variable’s data type cannot be changed if the new data type is not equivalent (type having a different data size) to the old data type and any values (including the pad value) have been written. Data specifications are considered equivalent if the data types are equivalent. Refer to the CDF User’s Guide for equivalent data types.

The arguments to CDFsetzVarDataSpec are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
dataType	The new data type.

4.3.98.1. Example(s)

The following example respecifies the data type to CDF_INT2 (from its original CDF_UINT2) for zVariable “MY_VAR” in a CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  dataType;        /* The data type. */
.
.
dataType = CDF_INT2;
try {
    ....
    status = CDFsetzVarDataSpec (id, CDFgetVarNum (id, “MY_VAR”), dataType);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
.
```

4.3.99 CDFsetzVarDimVariances

```
int CDFsetzVarDimVariances(          /* out -- Completion status code. */
void* id,                          /* in -- CDF identifier. */
int varNum,                         /* in -- Variable number. */
int[] dimVarys);                   /* in -- Dimension variances. */
```

CDFsetzVarDimVariances respecifies the dimension variances of the specified zVariable in a CDF. For 0-dimensional zVariable, this operation is not applicable. The dimension variances are described in Section 2.10.

The arguments to CDFsetzVarDimVariances are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
dimVarys	The dimension variances.

4.3.99.1. Example(s)

The following example resets the dimension variances to true (VARY) and true (VARY) for zVariable “MY_VAR”, a 2-dimensional variable, in a CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  varNum;          /* zVariable number. */
int[] dimVarys = new int[] {VARY, VARY}; /* The dimension variances. */
.
.
try {
    ....
    varNum = CDFgetVarNum (id, "MY_VAR");
    status = CDFsetzVarDimVariances (id, varNum, dimVarys);
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.100 CDFsetzVarInitialRecs

```

int CDFsetzVarInitialRecs(          /* out -- Completion status code. */
void* id,                          /* in -- CDF identifier. */
int  varNum,                       /* in -- Variable number. */
int  numRecs);                    /* in -- Number of records. */

```

CDFsetzVarInitialRecs specifies a number of records to initially write to the specified zVariable in a CDF. The records are written beginning at record number 0 (zero). This may be specified only once per zVariable and before any other records have been written to that zVariable. If a pad value has not yet been specified, the default is used (see the Concepts chapter in the CDF User's Guide). If a pad value has been explicitly specified, that value is written to the records. The Concepts chapter in the CDF User's Guide describes initial records.

The arguments to CDFsetzVarInitialRecs are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
numRecs	The initially written records.

4.3.100.1 Example(s)

The following example writes the initial 100 records to zVariable "MY_VAR" in a CDF.

```

.
.
..
void*      id;          /* CDF identifier. */
int  varNum;          /* zVariable number. */
int  numRecs          /* The number of records. */

```

```

.
.
try {
    ...
    varNum = CDFgetVarNum (id, "MY_VAR");
    numRecs = 100;
    status = CDFsetzVarInitialRecs (id, varNum, numRecs);
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.101 CDFsetzVarRecVariance

```

int CDFsetzVarRecVariance(                                     /* out -- Completion status code. */
void* id,                                                     /* in -- CDF identifier. */
int varNum,                                                  /* in -- Variable number. */
int recVary);                                                /* in -- Record variance. */

```

CDFsetzVarRecVariance specifies the record variance of the specified zVariable in a CDF. The record variances are described in Section 2.10.

The arguments to CDFsetzVarRecVariance are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
recVary	The record variance.

4.3.101.1. Example(s)

The following example sets the record variance to VARY (from NOVARY) for zVariable "MY_VAR" in a CDF.

```

.
.
.
void* id;                                                     /* CDF identifier. */
int recVary;                                                /* The record variance. */
.
.
recVary = VARY;
try {
    ....
    status = CDFsetzVarRecVariance (id, CDFgetVarNum (id, "MY_VAR"), recVary);
    ...
    ...
} catch (CDFException ex) {

```



```
...
}.
```

4.3.102 CDFsetzVarReservePercent

```
int CDFsetzVarReservePercent(          /* out -- Completion status code. */
void* id,                             /* in -- CDF identifier. */
int varNum,                           /* in -- Variable number. */
int percent);                         /* in -- Reserve percentage. */
```

CDFsetzVarReservePercent specifies the compression reserve percentage being used for the specified zVariable in a CDF. This operation only applies to compressed zVariables. Refer to the CDF User's Guide for a description of the reserve scheme used by the CDF library.

The arguments to CDFsetzVarReservePercent are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
percent	The reserve percentage.

4.3.102.1. Example(s)

The following example sets the reserve percentage to 10 for zVariable "MY_VAR" in a CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  percent;         /* The reserve percentage. */
.
.
percent = 10;
try {
    ....
    status = CDFsetzVarReservePercent (id, CDFgetVarNum (id, "MY_VAR"), percent);
    ...
    ...
} catch (CDFException ex) {
    ...
}.
.
```

4.3.103 CDFsetzVarsCacheSize

```

int CDFsetzVarsCacheSize(                               /* out -- Completion status code. */
void* id,                                               /* in -- CDF identifier. */
int numBuffers);                                       /* in -- Number of cache buffers. */

```

CDFsetzVarsCacheSize specifies the number of cache buffers to be used for all of the zVariable files in a CDF. This operation is not applicable to a single-file CDF. The Concepts chapter in the CDF User's Guide describes the caching scheme used by the CDF library.

The arguments to CDFsetzVarsCacheSize are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
numBuffers	The number of buffers.

4.3.103.1. Example(s)

The following example sets the number of cache buffers to 10 for all zVariables in a CDF.

```

.
.
.
void* id;                                               /* CDF identifier. */
int numBuffers;                                       /* The number of cache buffers. */
.
.
numBuffers = 10;
try {
    ....
    status = CDFsetzVarsCacheSize (id, numBuffers);
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.104 CDFsetzVarSeqPos

```

int CDFsetzVarSeqPos(                               /* out -- Completion status code. */
void* id,                                               /* in -- CDF identifier. */
int varNum,                                           /* in -- Variable number. */
int recNum,                                           /* in -- Record number. */
int[] indices);                                       /* in -- Indices in a record. */

```

CDFsetzVarSeqPos specifies the current sequential value (position) for sequential access for the specified zVariable in a CDF. Note that a current sequential value is maintained for each zVariable individually. Use CDFgetzVarSeqPos method to get the current sequential value.

The arguments to CDFsetzVarSeqPos are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
varNum	The zVariable number.
recNum	The zVariable record number.
indices	The dimension indices. Each element of indices receives the corresponding dimension index. For 0-dimensional zVariable, this argument is ignored, but must be presented.

4.3.104.1. Example(s)

The following example sets the current sequential value to the first value element in record number 2 for a zVariable, a 2-dimensional variable, in a CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  varNum;          /* The variable number. */
int  recNum;          /* The record number. */
int[] indices = new int[2]; /* The indices. */
.
.
recNum = 2;
indices[0] = 0;
indices[1] = 0;
try {
    status = CDFsetzVarSeqPos (id, varNum, recNum, indices);
    ...
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.105 CDFsetzVarSparseRecords

```

int CDFsetzVarSparseRecords(          /* out -- Completion status code. */
void* id,                            /* in -- CDF identifier. */
int varNum,                          /* in -- The variable number. */
int sRecordsType);                  /* in -- The sparse records type. */

```

CDFsetzVarSparseRecords specifies the sparse records type of the specified zVariable in a CDF. Refer to Section 2.12.1 for the description of sparse records.

The arguments to CDFsetzVarSparseRecords are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
----	---

varNum The zVariable number.
sRecordsType The sparse records type.

4.3.105.1. Example(s)

The following example sets the sparse records type to PAD_SPARSERECORDS from its original type for zVariable “MY_VAR” in a CDF.

```
.
.
.
void*            id;                            /* CDF identifier. */
int   sRecordsType;                           /* The sparse records type. */
.
.
sRecordsType = PAD_SPARSERECORDS;
try {
  status = CDFsetzVarSparseRecords (id, CDFgetVarNum(id, “MY_VAR”), sRecordsType);
  ...
  ...
} catch (CDFException ex) {
  ...
}.
.
```

4.3.106 CDFvarClose¹¹

```
int CDFvarClose(                                /* out -- Completion status code. */
void* id,                                        /* in -- CDF identifier. */
int varNum);                                    /* in -- rVariable number. */
```

CDFvarClose closes the specified rVariable file from a multi-file format CDF. The variable's cache buffers are flushed before the variable's open file is closed. However, the CDF file is still open.

NOTE: You must close all open variable files to guarantee that all modifications you have made will actually be written to the CDF's file(s). If your program exits, normally or otherwise, without a successful call to CDFclose, the CDF's cache buffers are left unflushed.

The arguments to CDFclose are defined as follows:

id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.

varNum The variable number for the open rVariable's file. This identifier must have been initialized by a call to CDFgetVarNum.

¹¹ A legacy CDF function, handling rVariables only. While it is still available in V3.1, CDFcloserVar is the preferred function for it.

4.3.106.1. Example(s)

The following example will close an open rVariable in a multi-file CDF.

```
.  
. .  
. .  
void*      id;          /* CDF identifier. */  
int       status;      /* Returned status code. */  
. .  
try {  
  
    status = CDFvarClose (id, CDFvarNum (id, "Flux"));  
  
} catch (CDFException ex) {  
    ...  
}.  
}
```

4.3.107 CDFvarCreate¹²

```
int CDFvarCreate(          /* out -- Completion status code. */  
void* id,                /* in -- CDF identifier. */  
string varName,          /* in -- rVariable name. */  
int dataType,           /* in -- Data type. */  
int numElements,        /* in -- Number of elements (of the data type). */  
int recVariance,         /* in -- Record variance. */  
int[] dimVariances,     /* in -- Dimension variances. */  
TYPE varNum);          /* out -- rVariable number. */  
                        /* TYPE -- int* or "out int". */
```

CDFvarCreate is used to create a new rVariable in a CDF. A variable (rVariable or zVariable) with the same name must not already exist in the CDF.

The arguments to CDFvarCreate are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.
varName	The name of the rVariable to create. This may be at most CDF_VAR_NAME_LEN256 characters. Variable names are case-sensitive.
dataType	The data type of the new rVariable. Specify one of the data types defined in Section 2.6.
numElements	The number of elements of the data type at each value. For character data types (CDF_CHAR and CDF_UCHAR), this is the number of characters in the string (each value consists of the entire string). For all other data types this must always be one (1) - multiple elements at each value are not allowed for non-character data types.

¹² A legacy CDF function, handling rVariables only. While it is still available in V3.1, CDFcreateVar is the preferred function for it.

recVariance	The rVariable's record variance. Specify one of the variances defined in Section 2.10.
dimVariances	The rVariable's dimension variances. Each element of dimVariances specifies the corresponding dimension variance. For each dimension specify one of the variances defined in Section 2.10. For 0-dimensional rVariables this argument is ignored (but must be present).
varNum	The number assigned to the new rVariable. This number must be used in subsequent CDF function calls when referring to this rVariable. An existing rVariable's number may be determined with the CDFvarNum or CDFgetVarNum function.

4.3.107.1. Example(s)

The following example will create several rVariables in a 2-dimensional CDF.

```

.
.
.
void*      id;                /* CDF identifier. */
Int  status;                 /* Returned status code. */
int  EPOCHrecVary = {VARY};  /* EPOCH record variance. */
int  LATrecVary = {NOVARY};  /* LAT record variance. */
int  LONrecVary = {NOVARY};  /* LON record variance. */
int  TMPrecVary = {VARY};    /* TMP record variance. */
int[] EPOCHdimVarys = new int[] {NOVARY,NOVARY}; /* EPOCH dimension variances. */
int[] LATdimVarys = new int[] {VARY,VARY};      /* LAT dimension variances. */
int[] LONdimVarys = new int[] {VARY,VARY};      /* LON dimension variances. */
int[] TMPdimVarys = new int[] {VARY,VARY};      /* TMP dimension variances. */
int  EPOCHvarNum;           /* EPOCH zVariable number. */
int  LATvarNum;            /* LAT zVariable number. */
int  LONvarNum;           /* LON zVariable number. */
int  TMPvarNum;           /* TMP zVariable number. */
.
.
try {
    ....
    status = CDFvarCreate (id, "EPOCH", CDF_EPOCH, 1,
                          EPOCHrecVary, EPOCHdimVarys, &EPOCHvarNum);

    status = CDFvarCreate (id, "LATITUDE", CDF_INT2, 1,
                          LATrecVary, LATdimVarys, &LATvarNum);

    status = CDFvarCreate (id, "INTITUDE", CDF_INT2, 1,
                          LONrecVary, LONdimVarys, &LONvarNum);

    status = CDFvarCreate (id, "TEMPERATURE", CDF_REAL4, 1,
                          TMPrecVary, TMPdimVarys, &TMPvarNum);

Or
    status = CDFvarCreate (id, "EPOCH", CDF_EPOCH, 1,
                          EPOCHrecVary, EPOCHdimVarys, out EPOCHvarNum);

```

```

status = CDFvarCreate (id, "LATITUDE", CDF_INT2, 1,
                      LATrecVary, LATdimVarys, out LATvarNum);

status = CDFvarCreate (id, "INTITUDE", CDF_INT2, 1,
                      LONrecVary, LONdimVarys, out LONvarNum);

status = CDFvarCreate (id, "TEMPERATURE", CDF_REAL4, 1,
                      TMPrecVary, TMPdimVarys, out TMPvarNum);

.
} catch (CDFException ex) {
.
.
}.

```

4.3.108 CDFvarGet¹³

```

int CDFvarGet(                                     /* out -- Completion status code. */
void* id,                                         /* in -- CDF identifier. */
int varNum,                                       /* in -- rVariable number. */
int recNum,                                       /* in -- Record number. */
int[] indices,                                   /* in -- Dimension indices. */
TYPE value);                                     /* out -- Value. */
/* TYPE -- void*, "out string" or "out object". */

```

CDFvarGet is used to read a single value from an rVariable.

The arguments to CDFvarGet are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.
varNum	The rVariable number from which to read data.
recNum	The record number at which to read.
indices	The dimension indices within the record.
value	The data value read. This buffer must be large enough to hold the value.

4.3.108.1. Example(s)

The following example returns two data values, the first and the fifth element, in Record 0 from an rVariable named MY_VAR, a 2-dimensional (2 by 3) CDF_DOUBLE type variable, in a row-major CDF. The first get operation passes the value pointer, while the second operation uses “out” argument modifier.

```

.
.

```

¹³ A legacy CDF function, handling rVariables only. While it is still available in V3.1, CDFgetrVarData is the preferred function for it.

```

.
void*      id;          /* CDF identifier. */
int  varNum;          /* rVariable number. */
int  recNum;          /* The record number. */
int[] indices = new int[2]; /* The dimension indices. */
double  value1, value2; /* The data values. */
.
.
try {
    ....
    varNum = CDFvarNum (id, "MY_VAR");
    recNum = 0;
    indices[0] = 0;
    indices[1] = 0;
    status = CDFvarGet (id, varNum, recNum, indices, &value1);
    indices[0] = 1;
    indices[1] = 1;
    object value2o;
    status = CDFvarGet (id, varNum, recNum, indices, out value2o);
    value2 = (double) value2o;
} catch (CDFException ex) {
    ...
}.

```

4.3.109 CDFvarHyperGet¹⁴

```

int CDFvarHyperGet(          /* out -- Completion status code. */
void* id,                   /* in -- CDF identifier. */
int varNum,                 /* in -- rVariable number. */
int recStart,              /* in -- Starting record number. */
int recCount,             /* in -- Number of records. */
int recInterval,          /* in -- Subsampling interval between records. */
int[] indices,            /* in -- Dimension indices of starting value. */
int[] counts,             /* in -- Number of values along each dimension. */
int[] intervals,         /* in -- Subsampling intervals along each dimension. */
TYPE buffer);           /* out -- Values. */
/* TYPE -- void*, "out string", "out string[]" or "out object". */

```

CDFvarHyperGet is used to fill a buffer of one or more values from the specified rVariable. It is important to know the variable majority of the CDF before using CDFvarHyperGet because the values placed into the buffer will be in that majority. CDFinquire can be used to determine the default variable majority of a CDF distribution. The Concepts chapter in the CDF User's Guide describes the variable majorities. **Note:** you need to provide dummy arrays, with at least one (1) element, for indices, counts and intervals for scalar variables.

4.3.109.1. Example(s)

The following example will read an entire record of data from an rVariable. The CDF's rVariables are 3-dimensional with sizes [180,91,10] and CDF's variable majority is ROW_MAJOR. For the rVariable the record variance is VARY,

¹⁴ A legacy CDF function, handling rVariables only. While it is still available in V3.1, CDFhyperGetVarData is the preferred function for it.

the dimension variances are [VARY,VARY,VARY], and the data type is CDF_REAL4. This example is similar to the example provided for CDFvarGet except that it uses a single call to CDFvarHyperGet rather than numerous calls to CDFvarGet.

```

.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
float[,.]  tmp;        /* Temperature values. */
int  varN;           /* rVariable number. */
int  recStart = 13;   /* Record number. */
int  recCount = 1;    /* Record counts. */
int  recInterval = 1; /* Record interval. */
int[] indices = new int[] {0,0,0}; /* Dimension indices. */
int[] counts = new int[] {180,91,10}; /* Dimension counts. */
int[] intervals = new int[] {1,1,1}; /* Dimension intervals. */
.
.
try {
    varN = CDFgetVarNum (id, "Temperature");
    ...
    tmp = new float[180,91,10];
    fixed (void* ptmp = tmp) {
        status = CDFvarHyperGet (id, varN, recStart, recCount, recInterval, indices, counts, intervals, ptmp);
    }
    Or
    status = CDFvarHyperGet (id, varN, recStart, recCount, recInterval, indices, counts, intervals, out tmp);
.
} catch (CDFException ex) {
    ...
}.

```

Note that if the CDF's variable majority had been COLUMN_MAJOR, the tmp array would have been declared float tmp[10,91,180] for proper indexing.

4.3.110 CDFvarHyperPut¹⁵

```

int CDFvarHyperPut(          /* out -- Completion status code. */
void* id,                  /* in -- CDF identifier. */
int varNum,                /* in -- rVariable number. */
int recStart,              /* in -- Starting record number. */
int recCount,              /* in -- Number of records. */
int recInterval,           /* in -- Interval between records. */
int[] indices,             /* in -- Dimension indices of starting value. */
int[] counts,              /* in -- Number of values along each dimension. */
int[] intervals,           /* in -- Interval between values along each dimension. */
TYPE buffer);             /* in -- Buffer of values. */
/* TYPE -- void*, string, string[] or object. */

```

¹⁵ A legacy CDF function, handling rVariables only. While it is still available in V3.1, CDFhyperPutrVarData is the preferred function for it.

CDFvarHyperPut is used to write one or more values from the data holding buffer to the specified rVariable. It is important to know the variable majority of the CDF before using this routine because the values in the buffer to be written must be in the same majority. CDFinquire can be used to determine the default variable majority of a CDF distribution. The Concepts chapter in the CDF User's Guide describes the variable majorities. **Note:** you need to provide dummy arrays, with at least one (1) element, for indices, counts and intervals for scalar variables.

4.3.110.1. Example(s)

The following example writes values to the rVariable LATITUDE of a CDF that is a 2-dimensional array with dimension sizes [360,181]. For LATITUDE the record variance is NOVARY, the dimension variances are [NOVARY,VARY], and the data type is CDF_INT2. This example is similar to the CDFvarPut example except that it uses a single call to CDFvarHyperPut rather than numerous calls to CDFvarPut.

```
.
.
.
void*      id;                /* CDF identifier. */
Int  status;                 /* Returned status code. */
int     lat;                 /* Latitude value. */
short[] lats = new short[181]; /* Buffer of latitude values. */
int     varN;                /* rVariable number. */
int     recStart = 0;        /* Record number. */
int     recCount = 1;        /* Record counts. */
int     recInterval = 1;     /* Record interval. */
int[] indices = new int[] {0,0}; /* Dimension indices. */
int[] counts = new int[] {1,181}; /* Dimension counts. */
int[] intervals = new int[] {1,1}; /* Dimension intervals. */

.
.
try {
    ....
    varN = CDFvarNum (id, "LATITUDE");
    for (lat = -90; lat <= 90; lat++)
        lats[90+lat] = (short) lat;
    fixed (void* plats = lats) {
        status = CDFvarHyperPut (id, varN, recStart, recCount, recInterval, indices, counts, intervals, plats);
    }
    Or
    status = CDFvarHyperPut (id, varN, recStart, recCount, recInterval, indices, counts, intervals, lats);
    ....
} catch (CDFException ex) {
    ...
}.
.
```

4.3.111 CDFvarInquire

```
int CDFvarInquire(                /* out -- Completion status code. */
void* id,                        /* in -- CDF identifier. */
```

```

int varNum, /* in -- rVariable number. */
out string varName, /* out -- rVariable name. */
TYPE dataType, /* out -- Data type. */
TYPE numElements, /* out -- Number of elements (of the data type). */
TYPE recVariance, /* out -- Record variance. */
TYPE2 dimVariances); /* out -- Dimension variances. */
/* TYPE -- int* or "out int". */
/* TYPE2 -- int* or "out int[]". */

```

CDFvarInquire is used to inquire about the specified rVariable. This method would normally be used before reading rVariable values (with CDFvarGet or CDFvarHyperGet) to determine the data type and number of elements (of that data type).

The arguments to CDFvarInquire are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.
varNum	The number of the rVariable to inquire. This number may be determined with a call to CDFvarNum (see Section 4.3.112).
varName	The rVariable's name.
dataType	The data type of the rVariable. The data types are defined in Section 2.6.
numElements	The number of elements of the data type at each rVariable value. For character data types (CDF_CHAR and CDF_UCHAR), this is the number of characters in the string. (Each value consists of the entire string.) For all other data types, this will always be one (1) - multiple elements at each value are not allowed for non-character data types.
recVariance	The record variance. The record variances are defined in Section 2.10.
dimVariances	The dimension variances. Each element of dimVariances receives the corresponding dimension variance. The dimension variances are defined in Section 2.10. For 0-dimensional rVariables this argument is ignored (but a placeholder is necessary).

4.3.111.1. Example(s)

The following example returns about an rVariable named HEAT_FLUX in a CDF. Note that the rVariable name returned by CDFvarInquire will be the same as that passed in to CDFgetVarNum.

```

.
.
.
void*      id; /* CDF identifier. */
int status; /* Returned status code. */
string varName; /* rVariable name. */
int dataType; /* Data type of the rVariable. */
int numElems; /* Number of elements (of data type). */
int recVary; /* Record variance. */
int[] dimVarys; /* Dimension variances (allocate to allow the
                maximum number of dimensions). */
.

```

```

try {
    ....
    dimVarys = new int[CDF_MAX_DIMS];
    fixed (int* pdimVarys = dimVarys) {
        status = CDFvarInquire (id, CDFgetVarNum(id,"HEAT_FLUX"), out varName, &dataType,
                               &numElems, &recVary, pdimVarys);
    }
    Or
    status = CDFvarInquire (id, CDFgetVarNum(id,"HEAT_FLUX"), out varName, out dataType,
                            out numElems, out recVary, out dimVarys);
    ...
} catch (CDFException ex) {
    ...
}.

```

4.3.112 CDFvarNum¹⁶

```

int CDFvarNum(                /* out -- Variable number. */
void* id,                    /* in -- CDF identifier. */
string varName);             /* in -- Variable name. */

```

CDFvarNum is used to determine the number associated with a given variable name. If the variable is found, CDFvarNum returns its variable number - which will be equal to or greater than zero (0). If an error occurs (e.g., the variable does not exist in the CDF), an error code (of type Int) is returned. Error codes are less than zero (0). The returned variable number should be used in the functions of the same variable type, rVariable or zVariable. If it is an rVariable, functions dealing with rVariables should be used. Similarly, functions for zVariables should be used for zVariables.

The arguments to CDFvarNum are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.
varName	The name of the variable to search. This may be at most CDF_VAR_NAME_LEN256 characters. Variable names are case-sensitive.

4.3.112.1. Example(s)

In the following example CDFvarNum is used as an embedded function call when inquiring about an rVariable.

```

.
.
.
void*      id;                /* CDF identifier. */
int  status;                  /* Returned status code. */
string    varName;           /* Variable name. */
int  dataType;               /* Data type of the rVariable. */

```

¹⁶ A legacy CDF function. It used to handle only rVariables. It has been extended to include zVariables. While it is still available in V3.1, CDFgetVarNum is the preferred function for it.

```

int  numElements;          /* Number of elements (of the data type). */
int  recVariance;         /* Record variance. */
int[] dimVariances;       /* Dimension variances. */
.
.
try {
    ....
    dimVariances = new int[CDF_MAX_DIMS];
    fixed (int* pdimVariances = dimVariances) {
        status = CDFvarInquire (id, CDFvarNum(id,"LATITUDE"), out varName, &dataType,
                                &numElements, &recVariance, pdimVariances);
    }
    Or
    status = CDFvarInquire (id, CDFvarNum(id,"LATITUDE"), out varName, out dataType,
                            out numElements, out recVariance, out dimVariances);
    .
} catch (CDFException ex) {
    ...
}.

```

In this example the rVariable named LATITUDE was inquired. Note that if LATITUDE did not exist in the CDF, the call to CDFgetVarNum would have returned an error code. Passing that error code to CDFvarInquire as an rVariable number would have resulted in CDFvarInquire also returning an error code. Also note that the name written into varName is already known (LATITUDE). In some cases the rVariable names will be unknown - CDFvarInquire would be used to determine them. CDFvarInquire is described in Section 4.3.111.

4.3.113 CDFvarPut¹⁷

```

int CDFvarPut(              /* out -- Completion status code. */
void* id,                  /* in -- CDF identifier. */
int varNum,                /* in -- rVariable number. */
int recNum,               /* in -- Record number. */
int[] indices,            /* in -- Dimension indices. */
TYPE value);             /* in -- Value. */
                          /* TYPE -- void*, string or object. */

```

CDFvarPut writes a single data value to an rVariable. CDFvarPut may be used to write more than one value with a single call.

The arguments to CDFvarPut are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.
varNum	The rVariable number to which to write. This number may be determined with a call to CDFvarNum.
recNum	The record number at which to write.

¹⁷ A legacy CDF function, handling rVariables only. While it is still available in V3.1, CDFputrVarData is the preferred function for it.

indices	The dimension indices within the specified record at which to write. Each element of indices specifies the corresponding dimension index. For 0-dimensional variables, this argument is ignored (but must be present).
value	The data value to write.

4.3.113.1. Example(s)

The following example will write two data values (1st and 5th elements) of a 2-dimensional rVariable (2 by 3) named MY_VAR to record number 0.

```

.
.
.
void*      id;          /* CDF identifier. */
int  varNum;          /* rVariable number. */
int  recNum;         /* The record number. */
int[] indices = new int[2]; /* The dimension indices. */
double  value1, value2; /* The data values. */
.
.
try {
....
    varNum = CDFgetVarNum (id, "MY_VAR");
    recNum = 0;
    indices[0] = 0;
    indices[1] = 0;
    value1 = 10.1;
    status = CDFvarPut (id, varNum, recNum, indices, &value1);
    indices[0] = 1;
    indices[1] = 1;
    value2 = 20.2;
    status = CDFvarPut (id, varNum, recNum, indices, value2);
.
} catch (CDFException ex) {
...
}.

```

4.3.114 CDFvarRename¹⁸

```

int CDFvarRename(          /* out -- Completion status code. */
void* id,                 /* in -- CDF identifier. */
int varNum,               /* in -- rVariable number. */
string varName);          /* in -- New name. */

```

CDFvarRename is used to rename an existing rVariable. A variable (rVariable or zVariable) name must be unique.

¹⁸ A legacy CDF function, handling rVariables only. While it is still available in V3.1, CDFrenamerVar is the preferred function for it.

The arguments to CDFvarRename are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.
varNum	The rVariable number to rename. This number may be determined with a call to CDFvarNum.
varName	The new rVariable name. The maximum length of the new name is CDF_VAR_NAME_LEN256 characters. Variable names are case-sensitive.

4.3.114.1. Example(s)

In the following example the rVariable named TEMPERATURE is renamed to TMP (if it exists). Note that if CDFvarNum returns a value less than zero (0) then that value is not an rVariable number but rather a warning/error code.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  varNum;          /* rVariable number. */
.
.
try {
....
    varNum = CDFvarNum (id, "TEMPERATURE");
...
}
.
} catch (CDFException ex) {
...
}.
```

4.4 Attributes/Entries

This section provides functions that are related to CDF attributes or attribute entries. An attribute is identified by its name or an number in the CDF. Before you can perform any operation on an attribute or attribute entry, the CDF in which it resides must be opened.

4.4.1 CDFattrCreate¹⁹

```
int CDFattrCreate(          /* out -- Completion status code. */
void* id,                  /* in -- CDF identifier. */
string attrName,          /* in -- Attribute name. */
```

¹⁹ Same as CDFcreateAttr.

```

int attrScope,                               /* in -- Scope of attribute. */
TYPE attrNum);                             /* out -- Attribute number. */
                                           /* TYPE -- int* or "out int". */

```

CDFattrCreate creates an attribute in the specified CDF. An attribute with the same name must not already exist in the CDF.

The arguments to CDFattrCreate are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.
attrName	The name of the attribute to create. This may be at most CDF_ATTR_NAME_LEN256 characters. Attribute names are case-sensitive.
attrScope	The scope of the new attribute. Specify one of the scopes described in Section 2.13.
attrNum	The number assigned to the new attribute. This number must be used in subsequent CDF function calls when referring to this attribute. An existing attribute's number may be determined with the CDFgetAttrNum function.

4.4.1.1. Example(s)

The following example creates two attributes. The TITLE attribute is created with global scope - it applies to the entire CDF (most likely the title of the data set stored in the CDF). The Units attribute is created with variable scope - each entry describes some property of the corresponding variable (in this case the units for the data).

```

.
.
.
void*      id;                               /* CDF identifier. */
int  status;                               /* Returned status code. */
string    UNITSattrName = "Units";         /* Name of "Units" attribute. */
int  UNITSattrNum;                          /* "Units" attribute number. */
int  TITLEattrNum;                          /* "TITLE" attribute number. */
int  TITLEattrScope = GLOBAL_SCOPE;        /* "TITLE" attribute scope. */
.
.
try {
    ...
    status = CDFattrCreate (id, "TITLE", TITLEattrScope, &TITLEattrNum);
    status = CDFattrCreate (id, UNITSattrName, VARIABLE_SCOPE, out UNITSattrnum);
    ...
    ...
} catch (CDFException ex) {
    ...
}
.
.

```


4.4.2 CDFattrEntryInquire

```
int CDFattrEntryInquire(                                /* out -- Completion status code. */
void* id,                                              /* in -- CDF identifier. */
int attrNum,                                          /* in -- Attribute number. */
int entryNum,                                         /* in -- Entry number. */
TYPE dataType,                                       /* out -- Data type. */
TYPE numElements);                                  /* out -- Number of elements (of the data type). */
                                                    /* TYPE -- int* or "out int". */
```

CDFattrEntryInquire is used to inquire about a specific attribute entry. To inquire about the attribute in general, use CDFattrInquire. CDFattrEntryInquire would normally be called before calling CDFattrGet in order to determine the data type and number of elements (of that data type) for an entry. This would be necessary to correctly allocate enough memory to receive the value read by CDFattrGet.

The arguments to CDFattrEntryInquire are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.
attrNum	The attribute number for which to inquire an entry. This number may be determined with a call to CDFattrNum (see Section 4.4.5).
entryNum	The entry number to inquire. If the attribute is global in scope, this is simply the gEntry number and has meaning only to the application. If the attribute is variable in scope, this is the number of the associated rVariable (the rVariable being described in some way by the rEntry).
dataType	The data type of the specified entry. The data types are defined in Section 2.6.
NumElements	The number of elements of the data type. For character data types (CDF_CHAR and CDF_UCHAR), this is the number of characters in the string (An array of characters). For all other data types this is the number of elements in an array of that data type.

4.4.2.1. Example(s)

The following example returns each entry for an attribute. Note that entry numbers need not be consecutive - not every entry number between zero (0) and the maximum entry number must exist. For this reason NO_SUCH_ENTRY is an expected error code. Note also that if the attribute has variable scope, the entry numbers are actually rVariable numbers.

```
.
.
.
void*      id;                                         /* CDF identifier. */
int  status;                                         /* Returned status code. */
int  attrN;                                         /* attribute number. */
int  entryN;                                         /* Entry number. */
string attrName;                                     /* attribute name. */
int  attrScope;                                     /* attribute scope. */
int  maxEntry;                                       /* Maximum entry number used. */
int  dataType;                                       /* Data type. */
int  numElem;                                        /* Number of elements (of the data type). */
```

```

.
.
try {
...
attrN = CDFgetAttrNum (id, "TMP");
status = CDFattrInquire (id, attrN, out attrName, &attrScope, &maxEntry);

for (entryN = 0; entryN <= maxEntry; entryN++) {
    status = CDFattrEntryInquire (id, attrN, entryN, &dataType, &numElems);
Or
    status = CDFattrEntryInquire (id, attrN, entryN, out dataType, out numElems);
.
}
...
} catch (CDFException ex) {
...
}

```

4.4.3 CDFattrGet²⁰

```

int CDFattrGet(                                     /* out -- Completion status code. */
void* id,                                         /* in -- CDF identifier. */
int attrNum,                                     /* in -- Attribute number. */
int entryNum,                                    /* in -- Entry number. */
TYPE value);                                     /* out -- Attribute entry value. */
                                                /* TYPE -- void*, "out string" or "out object". */

```

CDFattrGet is used to read an attribute entry from a CDF. In most cases it will be necessary to call CDFattrEntryInquire before calling CDFattrGet in order to determine the data type and number of elements (of that data type) for the entry.

The arguments to CDFattrGet are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.
attrNum	The attribute number. This number may be determined with a call to CDFattrNum (Section 4.4.5).
entryNum	The entry number. If the attribute is global in scope, this is simply the gEntry number and has meaning only to the application. If the attribute is variable in scope, this is the number of the associated rVariable (the rVariable being described in some way by the rEntry).
value	The value read. This buffer must be large enough to hold the value. The method CDFattrEntryInquire would be used to determine the entry data type and number of elements (of that data type). The value is read from the CDF and placed into memory at address value.

²⁰ A legacy CDF function. While it is still available in V3.1, CDFgetAttrgEntry or CDFgetAttrEntry is the preferred function for it.

4.4.3.1. Example(s)

The following example displays the value of the UNITS attribute for the rEntry corresponding to the PRES_LVL rVariable (but only if the data type is CDF_CHAR).

```
.
.
.
void*      id;                /* CDF identifier. */
Int  status;                 /* Returned status code. */
int    attrN;                /* Attribute number. */
int    entryN;               /* Entry number. */
int    dataType;             /* Data type. */
int    numElems;             /* Number of elements (of data type). */
.
.
try {
    ...
    attrN = CDFattrNum (id, "UNITS");
    entryN = CDFvarNum (id, "PRES_LVL"); /* The rEntry number is the rVariable number. */

    status = CDFattrEntryInquire (id, attrN, entryN, out dataType, out numElems);

    if (dataType == CDF_CHAR) {
        string buffer;
        status = CDFattrGet (id, attrN, entryN, out buffer);
    }
} catch (CDFException ex) {
    ...
}.
.
```

4.4.4 CDFattrInquire²¹

```
int CDFattrInquire(                /* out -- Completion status code. */
void* id,                          /* in -- CDF identifier. */
int attrNum,                       /* in -- Attribute number. */
out string attrName,               /* out -- Attribute name. */
TYPE attrScope,                   /* out -- Attribute scope. */
TYPE maxEntry);                   /* out -- Maximum gEntry/rEntry number. */
/* TYPE -- int* or "out int". */
```

CDFattrInquire is used to inquire about the specified attribute. To inquire about a specific attribute entry, use CDFattrEntryInquire.

The arguments to CDFattrInquire are defined as follows:

²¹ A legacy function. While it is still available in V3.1, CDFinquireAttr is the preferred function for it.

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.
attrNum	The number of the attribute to inquire. This number may be determined with a call to CDFattrNum (see Section 4.4.5).
attrName	The attribute's name. This string length is limited to CDF_ATTR_NAME_LEN256.
attrScope	The scope of the attribute. Attribute scopes are defined in Section 2.13.
maxEntry	For gAttributes this is the maximum gEntry number used. For vAttributes this is the maximum rEntry number used. In either case this may not correspond with the number of entries (if some entry numbers were not used). If no entries exist for the attribute, then a value of -1 will be passed back.

4.4.4.1. Example(s)

The following example displays the name of each attribute in a CDF. The number of attributes in the CDF is first determined using the method CDFinquire. Note that attribute numbers start at zero (0) and are consecutive.

```

.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  numDims;        /* Number of dimensions. */
int[] dimSizes;      /* Dimension sizes (allocate to allow the maximum
                    /* number of dimensions). */
int  encoding;      /* Data encoding. */
int  majority;     /* Variable majority. */
int  maxRec;       /* Maximum record number in CDF. */
int  numVars;     /* Number of variables in CDF. */
int  numAttrs;   /* Number of attributes in CDF. */
int  attrN;      /* attribute number. */
string attrName; /* attribute name. */
int  attrScope; /* attribute scope. */
int  maxEntry;  /* Maximum entry number. */
.
.
try {
    ....
    status = CDFinquire (id, out numDims, out dimSizes, out encoding, out majority, out maxRec, out numVars,
                        out numAttrs);
    for (attrN = 0; attrN < numAttrs; attrN++) {
        status = CDFattrInquire (id, attrN, out attrName, out attrScope, out maxEntry);
        Or
        status = CDFattrInquire (id, attrN, out attrName, &attrScope, &maxEntry);
    }
} catch (CDFException ex) {
    ...
}
.

```

4.4.5 CDFAttrNum²²

```
int CDFAttrNum(                                     /* out -- attribute number. */
void* id,                                           /* in -- CDF id */
string attrName);                                  /* in -- Attribute name */
```

CDFAttrNum is used to determine the attribute number associated with a given attribute name. If the attribute is found, CDFAttrNum returns its number - which will be equal to or greater than zero (0). If an error occurs (e.g., the attribute name does not exist in the CDF), an error code (of type Int) is returned. Error codes are less than zero (0).

The arguments to CDFAttrNum are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.
attrName	The name of the attribute for which to search. This may be at most CDF_ATTR_NAME_LEN256 characters. Attribute names are case-sensitive.

CDFAttrNum may be used as an embedded function call when an attribute number is needed.

4.4.5.1. Example(s)

In the following example the attribute named pressure will be renamed to PRESSURE with CDFAttrNum being used as an embedded function call. Note that if the attribute pressure did not exist in the CDF, the call to CDFAttrNum would have returned an error code. Passing that error code to CDFAttrRename as an attribute number would have resulted in CDFAttrRename also returning an error code.

```
.
.
.
void*      id;                                     /* CDF identifier. */
int  status;                                       /* Returned status code. */
.
.
try {
    ....
    status = CDFAttrRename (id, CDFAttrNum(id,"pressure"), "PRESSURE");
    ....
} catch (CDFException ex) {
    ...
}
```

4.4.6 CDFAttrPut

```
int CDFAttrPut(                                     /* out -- Completion status code. */
```

²² A legacy CDF function. While it is still available in V3.1, CDFgetAttrNum is the preferred function for it.

```

void* id,          /* in -- CDF identifier. */
int attrNum,      /* in -- Attribute number. */
int entryNum,     /* in -- Entry number. */
int dataType,     /* in -- Data type of this entry. */
int numElements, /* in -- Number of elements (of the data type). */
TYPE value);     /* in -- Attribute entry value. */
/* TYPE -- void*, string, string[] or object. */

```

CDFattrPut is used to write an entry to a global or rVariable attribute in a CDF. The entry may or may not already exist. If it does exist, it is overwritten. The data type and number of elements (of that data type) may be changed when overwriting an existing entry.

The arguments to CDFattrPut are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.
attrNum	The attribute number. This number may be determined with a call to CDFgetAttrNum.
entryNum	The entry number. If the attribute is global in scope, this is simply the gEntry number and has meaning only to the application. If the attribute is variable in scope, this is the number of the associated rVariable (the rVariable being described in some way by the rEntry).
dataType	The data type of the specified entry. Specify one of the data types defined in Section 2.6.
numElements	The number of elements of the data type. For character data types (CDF_CHAR and CDF_UCHAR), this is the number of characters in the string (an array of characters). For all other data types this is the number of elements in an array of that data type.
value	The value(s) to write. The entry value is written to the CDF from memory address value.

4.4.6.1. Example(s)

The following example writes two attribute entries. The first is to gEntry number zero (0) of the gAttribute TITLE. The second is to the variable scope attribute VALIDs for the rEntry that corresponds to the rVariable TMP.

```

.
.
.
void* id;          /* CDF identifier. */
int status;       /* Returned status code. */
int TITLE_LEN = 10; /* Entry string length. */
int entryNum;     /* Entry number. */
int numElements; /* Number of elements (of data type). */
string title = "CDF title."; /* Value of TITLE attribute, entry number 0. */
short[] TMPvalids = new short[] {15,30}; /* Value(s) of VALIDs attribute,
                                           rEntry for rVariable TMP. */
.
.
entryNum = 0;

```

```

try {
    status = CDFattrPut (id, CDFgetAttrNum(id,"TITLE"), entryNum, CDF_CHAR, TITLE_LEN, title);
    .
    numElements = 2;
    status = CDFattrPut (id, CDFgetAttrNum(id,"VALIDs"), CDFgetVarNum(id,"TMP"),
                        CDF_INT2, numElements, TMPvalids);
Or
    fixed (void* pTMPvalids = TMPvalids) {
        status = CDFattrPut (id, CDFgetAttrNum(id,"VALIDs"), CDFgetVarNum(id,"TMP"),
                            CDF_INT2, numElements, pTMPvalids);
    }
} catch (CDFException ex) {
    ...
}.
.

```

4.4.7 CDFattrRename²³

```

int CDFattrRename(                                     /* out -- Completion status code. */
void* id,                                             /* in -- CDF identifier. */
int attrNum,                                         /* in -- Attribute number. */
string attrName);                                    /* in -- New attribute name. */

```

CDFattrRename is used to rename an existing attribute. An attribute with the new name must not already exist in the CDF.

The arguments to CDFattrRename are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.
attrNum	The number of the attribute to rename. This number may be determined with a call to CDFattrNum (see Section 4.4.5).
attrName	The new attribute name. This may be at most CDF_ATTR_NAME_LEN256 characters. Attribute names are case-sensitive.

4.4.7.1. Example(s)

In the following example the attribute named LAT is renamed to LATITUDE.

```

.
.
.
void* id;                                             /* CDF identifier. */
int status;                                          /* Returned status code. */

```

²³ A legacy CDF function. While it is still available in V3.1, CDFrenameAttr is the preferred function for it.

```

.
.
try {
    status = CDFattrRename (id, CDFgetAttrNum(id,"LAT"), "LATITUDE");
.
} catch (CDFException ex) {
    ...
}.

```

4.4.8 CDFconfirmAttrExistence

```

int CDFconfirmAttrExistence(           /* out -- Completion status code. */
void* id,                             /* in -- CDF identifier. */
string attrName)                      /* in -- Attribute name. */

```

CDFconfirmAttrExistence confirms whether an attribute exists for the given attribute name in a CDF. If the attribute doesn't exist, the informational status code, NO_SUCH_ATTR, is returned and no exception is thrown.

The arguments to CDFconfirmAttrExistence are defined as follows:

id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.

attrName The attribute name to check.

4.4.8.1. Example(s)

The following example checks whether an attribute by the name of "ATTR_NAME1" is in a CDF.

```

.
.
.
void*        id;                       /* CDF identifier. */
int        status;                     /* Returned status code. */
.
.
try {
    ....
    status = CDFconfirmAttrExistence (id, "ATTR_NAME1");
    if (status == NO_SUCH_ATTR) {
        ....
    }
.
} catch (CDFException ex) {
    ...
}.

```


4.4.9 CDFconfirmgEntryExistence

```
int CDFconfirmgEntryExistence(          /* out -- Completion status code. */
void* id,                               /* in -- CDF identifier. */
int attrNum,                            /* in -- Attribute number. */
int entryNum);                          /* in -- gEntry number. */
```

CDFconfirmgEntryExistence confirms the existence of the specified entry (gEntry), in a global attribute from a CDF. If the gEntry does not exist, the informational status code NO_SUCH_ENTRY will be returned and no exception is thrown.

The arguments to CDFconfirmgEntryExistence are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
attrNum	The (global) attribute number.
entryNum	The gEntry number.

4.4.9.1. Example(s)

The following example checks the existence of a gEntry numbered 1 for attribute “MY_ATTR” in a CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  attrNum;        /* Attribute number. */
int  entryNum;       /* gEntry number. */
.
.
try {
    ....
    attrNum = CDFgetAttrNum(id, “MY_ATTR”);
    entryNum = 1;
    status = CDFconfirmgEntryExistence (id, attrNum, entryNum);
    if (status == NO_SUCH_ENTRY) UserStatusHandler (status);
.
.
.
```

4.4.10 CDFconfirmrEntryExistence

```
int CDFconfirmrEntryExistence(          /* out -- Completion status code. */
void* id,                               /* in -- CDF identifier. */
int attrNum,                            /* in -- Attribute number. */
int entryNum);                          /* in -- rEntry number. */
```

CDFconfirmrEntryExistence confirms the existence of the specified entry (rEntry), corresponding to an rVariable, in a variable attribute from a CDF. If the rEntry does not exist, the informational status code NO_SUCH_ENTRY will be returned and no exception is thrown.

The arguments to CDFconfirmrEntryExistence are defined as follows:

id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.

attrNum The variable attribute number.

entryNum The rEntry number.

4.4.10.1. Example(s)

The following example checks the existence of an rEntry, corresponding to rVariable “MY_VAR”, for attribute “MY_ATTR” in a CDF.

```

.
.
.
void* id;                            /* CDF identifier. */
int status;                         /* Returned status code. */
int attrNum;                        /* Attribute number. */
int entryNum;                       /* rEntry number. */
.
.
try {
    ....
    attrNum = CDFgetAttrNum(id, "MY_ATTR");
    entryNum = CDFgetVarNum(id, "MY_VAR");
    status = CDFconfirmrEntryExistence (id, attrNum, entryNum);
    if (status == NO_SUCH_ENTRY) UserStatusHandler (status);
.
} catch (CDFException ex) {
    ...
}.

```

4.4.11 CDFconfirmzEntryExistence

```

int CDFconfirmzEntryExistence(                            /* out -- Completion status code. */
void* id,                                                 /* in -- CDF identifier. */
int attrNum,                                             /* in -- Attribute number. */
int entryNum);                                           /* in -- zEntry number. */

```

CDFconfirmzEntryExistence confirms the existence of the specified entry (zEntry), corresponding to a zVariable, in a variable attribute from a CDF. If the zEntry does not exist, the informational status code NO_SUCH_ENTRY will be returned and no exception is thrown.

The arguments to `CDFconfirmzEntryExistence` are defined as follows:

`id` The identifier of the CDF. This identifier must have been initialized by a call to `CDFcreate` (or `CDFcreateCDF`) or `CDFopenCDF`.

`attrNum` The (variable) attribute number.

`entryNum` The `zEntry` number.

4.4.11.1. Example(s)

The following example checks the existence of the `zEntry` corresponding to `zVariable` “MY_VAR” for the variable attribute “MY_ATTR” in a CDF.

```
.
.
.
void*      id;           /* CDF identifier. */
int  status;           /* Returned status code. */
int  attrNum;         /* Attribute number. */
int  entryNum;        /* zEntry number. */
.
.
try {
    ....
    attrNum = CDFgetAttrNum(id, "MY_ATTR");
    entryNum = CDFgetVarNum(id, "MY_VAR");
    status = CDFconfirmzEntryExistence (id, attrNum, entryNum);
    if (status == NO_SUCH_ENTRY) UserStatusHandler (status);
.
} catch (CDFException ex) {
    ...
}.
.
```

4.4.12 CDFcreateAttr

```
int CDFcreateAttr(           /* out -- Completion status code. */
void* id,                   /* in -- CDF identifier. */
string attrName,           /* in -- Attribute name. */
int attrScope,            /* in -- Scope of attribute. */
TYPE attrNum);           /* out -- Attribute number. */
                          /* TYPE -- int* or "out int". */
```

`CDFcreateAttr` creates an attribute with the specified scope in a CDF. It is identical to the method `CDFattrCreate`. An attribute with the same name must not already exist in the CDF.

The arguments to `CDFcreateAttr` are defined as follows:

`id` The identifier of the CDF. This identifier must have been initialized by a call to `CDFcreate` (or `CDFcreateCDF`) or `CDFopenCDF`.

attrName	The name of the attribute to create. This may be at most CDF_ATTR_NAME_LEN256 characters. Attribute names are case-sensitive.
attrScope	The scope of the new attribute. Specify one of the scopes described in Section 2.13.
attrNum	The number assigned to the new attribute. This number must be used in subsequent CDF function calls when referring to this attribute. An existing attribute's number may be determined with the CDFgetAttrNum function.

4.4.12.1. Example(s)

The following example creates two attributes. The TITLE attribute is created with global scope - it applies to the entire CDF (most likely the title of the data set stored in the CDF). The Units attribute is created with variable scope - each entry describes some property of the corresponding variable (in this case the units for the data).

```
.
.
.
void*      id;                /* CDF identifier. */
int  status;                /* Returned status code. */
string    UNITSattrName = "Units"; /* Name of "Units" attribute. */
int      UNITSattrNum;      /* "Units" attribute number. */
int      TITLEattrNum;     /* "TITLE" attribute number. */
int  TITLEattrScope = GLOBAL_SCOPE; /* "TITLE" attribute scope. */
.
.
try {
    ....
    status = CDFcreateAttr (id, "TITLE", TITLEattrScope, &TITLEattrNum);
    status = CDFcreateAttr (id, UNITSattrName, VARIABLE_SCOPE, out UNITSattrnum);
.
} catch (CDFException ex) {
    ...
}.
.
```

4.4.13 CDFdeleteAttr

```
int CDFdeleteAttr(                /* out -- Completion status code. */
void* id,                        /* in -- CDF identifier. */
int attrNum);                   /* in -- Attribute identifier. */
```

CDFdeleteAttr deletes the specified attribute from a CDF.

The arguments to CDFdeleteAttr are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
attrNum	The attribute number to be deleted.

4.4.13.1. Example(s)

The following example deletes an existing attribute named MY_ATTR from a CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  attrNum;        /* Attribute number. */
.
.
try {
    ....
    attrNum = CDFgetAttrNum (id, "MY_ATTR");
    status = CDFdeleteAttr (id, attrNum);
.
} catch (CDFException ex) {
    ...
}.
.
```

4.4.14 CDFdeleteAttrEntry

```
int CDFdeleteAttrEntry( /* out -- Completion status code. */
void* id,              /* in -- CDF identifier. */
int attrNum,          /* in -- Attribute identifier. */
int entryNum);        /* in -- gEntry identifier. */
```

CDFdeleteAttrEntry deletes the specified entry (gEntry) in a global attribute from a CDF.

The arguments to CDFdeleteAttrEntry are defined as follows:

- id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
- attrNum The global attribute number from which to delete an attribute entry.
- entryNum The gEntry number to delete.

4.4.14.1. Example(s)

The following example deletes the entry number 5 from an existing global attribute MY_ATTR in a CDF.

```
.
.
```

```

.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  attrNum;        /* Attribute number. */
int  entryNum;       /* gEntry number. */
.
.
try {
    ....
    attrNum = CDFgetAttrNum (id, "MY_ATTR");
    entryNum = 5;
    status = CDFdeleteAttrEntry (id, attrNum, entryNum);

.
} catch (CDFException ex) {
    ...
}.
.

```

4.4.15 CDFdeleteAttrEntry

```

int CDFdeleteAttrEntry(          /* out -- Completion status code. */
void* id,                       /* in -- CDF identifier. */
int attrNum,                   /* in -- Attribute identifier. */
int entryNum);                 /* in -- rEntry identifier. */

```

CDFdeleteAttrEntry deletes the specified entry (rEntry), corresponding to an rVariable, in an (variable) attribute from a CDF.

The arguments to CDFdeleteAttrEntry are defined as follows:

- id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
- attrNum The (variable) attribute number.
- entryNum The rEntry number.

4.4.15.1. Example(s)

The following example deletes the entry corresponding to rVariable "MY_VAR1" from the variable attribute "MY_ATTR" in a CDF.

```

.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  attrNum;        /* Attribute number. */
int  entryNum;       /* rEntry number. */

```

```

.
.
try {
    ....
    attrNum = CDFgetAttrNum (id, "MY_ATTR");
    entryNum = CDFgetVarNum(id, "MY_VARI");
    status = CDFdeleteAttrEntry (id, attrNum, entryNum);
.
} catch (CDFException ex) {
    ...
}.
.

```

4.4.16 CDFdeleteAttrzEntry

```

int CDFdeleteAttrzEntry(                                     /* out -- Completion status code. */
void* id,                                                  /* in -- CDF identifier. */
int attrNum,                                              /* in -- Attribute identifier. */
int entryNum);                                           /* in -- zEntry identifier. */

```

CDFdeleteAttrzEntry deletes the specified entry (zEntry), corresponding to a zVariable, in an (variable) attribute from a CDF.

The arguments to CDFdeleteAttrzEntry are defined as follows:

- id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
- attrNum The identifier of the variable attribute.
- entryNum The zEntry number to be deleted that is the zVariable number.

4.4.16.1. Example(s)

The following example deletes the variable attribute entry named MY_ATTR that is attached to the zVariable MY_VARI.

```

.
.
.
void*            id;                                       /* CDF identifier. */
int status;                                             /* Returned status code. */
int attrNum;                                           /* Attribute number. */
int entryNum;                                         /* zEntry number. */
.
.
try {
    ....
    attrNum = CDFgetAttrNum (id, "MY_ATTR");
    entryNum = CDFgetVarNum(id, "MY_VARI");

```

```

        status = CDFdeleteAttrEntry (id, attrNum, entryNum);
    } catch (CDFException ex) {
        ...
    }.
    .

```

4.4.17 CDFgetAttrEntry

```

int CDFgetAttrEntry (                                /* out -- Completion status code. */
void* id,                                           /* in -- CDF identifier. */
int attrNum,                                       /* in -- Attribute identifier. */
int entryNum,                                       /* in -- gEntry number. */
TYPE value);                                       /* out -- gEntry data. */
                                                    /* TYPE -- void*, "out string" or "out object". */

```

This method is identical to the method CDFattrGet. CDFgetAttrEntry is used to read a global attribute entry from a CDF. In most cases it will be necessary to call CDFinquireAttrEntry before calling CDFgetAttrEntry in order to determine the data type and number of elements (of that data type) for the entry.

The arguments to CDFgetAttrEntry are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
attrNum	The attribute number. This number may be determined with a call to CDFgetAttrNum.
entryNum	The global attribute entry number.
value	The value read.

4.4.17.1. Example(s)

The following example displays the value of the global attribute called HISTORY.

```

.
.
.
void*      id;                                       /* CDF identifier. */
int status;                                       /* Returned status code. */
int attrN;                                       /* Attribute number. */
int entryN;                                       /* Entry number. */
int dataType;                                       /* Data type. */
int numElems;                                       /* Number of elements (of data type). */
string     buffer;                                   /* Buffer to receive value. */
.
.
try {
    ....
    attrN = CDFattrNum (id, "HISTORY");

```



```

try {
    ....
    attrNum = CDFgetAttrNum (id, "MY_ATTR");
    entryNum = 2;
    status = CDFgetAttrgEntryDataType (id, attrNum, entryNum, &dataType);
    Or
    status = CDFgetAttrgEntryDataType (id, attrNum, entryNum, out dataType);
    .
} catch (CDFException ex) {
    ...
}.
.

```

4.4.19 CDFgetAttrgEntryNumElements

```

int CDFgetAttrgEntryNumElements (
void* id,
int attrNum,
int entryNum,
TYPE numElems);
/* out -- Completion status code. */
/* in -- CDF identifier. */
/* in -- Attribute identifier. */
/* in -- gEntry number. */
/* out -- gEntry's number of elements. */
/* TYPE -- int* or "out int". */

```

CDFgetAttrgEntryNumElements returns the number of elements of the specified global attribute and gentry number in a CDF.

The arguments to CDFgetAttrgEntryNumElements are defined as follows:

id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.

attrNum The identifier of the global attribute.

entryNum The gEntry number.

numElems The number of elements of the gEntry.

4.4.19.1. Example(s)

The following example gets the number of elements from the gEntry numbered 2 from the global attribute "MY_ATTR" in a CDF.

```

.
.
.
void*        id;
int    status;
int    attrNum;
int    entryNum;
int    numElements;
/* CDF identifier. */
/* Returned status code. */
/* Attribute number. */
/* gEntry number. */
/* gEntry's number of elements. */
.

```

```

.
try {
    ....
    attrNum = CDFgetAttrNum (id, "MY_ATTR");
    entryNum = 2;
    status = CDFgetAttrgEntryNumElements (id, attrNum, entryNum, out numElements);
Or
    status = CDFgetAttrgEntryNumElements (id, attrNum, entryNum, &numElements);

.
} catch (CDFException ex) {
    ...
}.
.

```

4.4.20 CDFgetAttrMaxgEntry

```

int CDFgetAttrMaxgEntry (                               /* out -- Completion status code. */
void* id,                                               /* in -- CDF identifier. */
int attrNum,                                           /* in -- Attribute identifier. */
TYPE maxEntry);                                       /* out -- The last gEntry number. */
                                                         /* TYPE -- int* or "out int". */

```

CDFgetAttrMaxgEntry returns the last entry number of the specified global attribute in a CDF.

The arguments to CDFgetAttrMaxgEntry are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
attrNum	The identifier of the global attribute.
maxEntry	The last gEntry number.

4.4.20.1. Example(s)

The following example gets the last entry number from the global attribute "MY_ATTR" in a CDF.

```

.
.
.
void*      id;                                         /* CDF identifier. */
int  status;                                         /* Returned status code. */
int  attrNum;                                       /* Attribute number. */
int  maxEntry;                                       /* The last gEntry number. */
.
.
try {
    ....
    attrNum = CDFgetAttrNum (id, "MY_ATTR");

```

```

    status = CDFgetAttrMaxgEntry (id, attrNum, out maxEntry);
Or
    status = CDFgetAttrMaxgEntry (id, attrNum, &maxEntry);
.
} catch (CDFException ex) {
    ...
}.
.

```

4.4.21 CDFgetAttrMaxrEntry

```

int CDFgetAttrMaxrEntry (
void* id,
int attrNum,
TYPE maxEntry);

```

/ out -- Completion status code. */*
/ in -- CDF identifier. */*
/ in -- Attribute identifier. */*
/ out -- The maximum rEntry number. */*
/ TYPE -- int* or "out int". */*

CDFgetAttrMaxrEntry returns the last rEntry number (rVariable number) to which the given variable attribute is attached.

The arguments to CDFgetAttrMaxrEntry are defined as follows:

id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.

attrNum The identifier of the variable attribute.

maxEntry The last rEntry number (rVariable number) to which attrNum is attached..

4.4.21.1. Example(s)

The following example gets the last entry, corresponding to the last rVariable number, from the variable attribute "MY_ATTR" in a CDF.

```

.
.
.
void*      id;
int  status;
int  attrNum;
int  maxEntry;
.
.
try {
    ....
    attrNum = CDFgetAttrNum (id, "MY_ATTR");
    status = CDFgetAttrMaxrEntry (id, attrNum, out maxEntry);
Or
    status = CDFgetAttrMaxrEntry (id, attrNum, &maxEntry);

```

/ CDF identifier. */*
/ Returned status code. */*
/ Attribute number. */*
/ The last rEntry number. */*

```

} catch (CDFException ex) {
    ...
}.
.

```

4.4.22 CDFgetAttrMaxzEntry

```

int CDFgetAttrMaxzEntry (
void* id,
int attrNum,
TYPE maxEntry);

```

/ out -- Completion status code. */*
/ in -- CDF identifier. */*
/ in -- Attribute identifier. */*
/ out -- The maximum zEntry number. */*
/ **TYPE** -- int* or "out int". */*

CDFgetAttrMaxzEntry returns the last entry number, corresponding to the last zVariable number, to which the given variable attribute is attached.

The arguments to CDFgetAttrMaxzEntry are defined as follows:

- id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
- attrNum The identifier of the variable attribute.
- maxEntry The last zEntry number (zVariable number) to which attrNum is attached..

4.4.22.1. Example(s)

The following example gets the last entry, corresponding to the last zVariable number, attached to the variable attribute MY_ATTR in a CDF.

```

.
.
.
void*        id;
int    status;
int    attrNum;
int    maxEntry;
.
.
try {
    ....
    attrNum = CDFgetAttrNum (id, "MY_ATTR");
    status = CDFgetAttrMaxzEntry (id, attrNum, out maxEntry);
    Or
    status = CDFgetAttrMaxzEntry (id, attrNum, &maxEntry);
} catch (CDFException ex) {
    ...
}.
.

```


CDFgetAttrNum is used to determine the attribute number associated with a given attribute name. If the attribute is found, CDFgetAttrNum returns its number - which will be equal to or greater than zero (0). If an error occurs (e.g., the attribute name does not exist in the CDF), an error code (of type Int) is returned. Error codes are less than zero (0).

The arguments to CDFgetAttrNum are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
attrName	The name of the attribute for which to search. This may be at most CDF_ATTR_NAME_LEN256 characters. Attribute names are case-sensitive.

CDFgetAttrNum may be used as an embedded function call when an attribute number is needed.

4.4.24.1. Example(s)

In the following example the attribute named pressure will be renamed to PRESSURE with CDFgetAttrNum being used as an embedded function call. Note that if the attribute pressure did not exist in the CDF, the call to CDFgetAttrNum would have returned an error code. Passing that error code to CDFattrRename as an attribute number would have resulted in CDFattrRename also returning an error code.

```

.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
.
.
try {
    ....
    status = CDFrenameAttr (id, CDFgetAttrNum(id,"pressure"), "PRESSURE");

} catch (CDFException ex) {
    ...
}.

```

4.4.25 CDFgetAttrEntry²⁴

```

int CDFgetAttrEntry (
void* id,
int attrNum,
int entryNum,
TYPE value);
/* out -- Completion status code. */
/* in -- CDF identifier. */
/* in -- Attribute identifier. */
/* in -- Entry number. */
/* out -- Entry data. */
/* TYPE -- void*, "out string", "out string[]",
or "out object". */

```

²⁴ An array of strings may be returned, after CDF V3.7.0.


```

void* id,                /* in -- CDF identifier. */
int attrNum,            /* in -- Attribute identifier. */
int entryNum,          /* in -- rEntry number. */
TYPE dataType);       /* out -- rEntry data type. */
                        /* TYPE -- int* or "out int". */

```

CDFgetAttrEntryDataType returns the data type of the rEntry from an (variable) attribute in a CDF. The data types are described in Section 2.6.

The arguments to CDFgetAttrEntryDataType are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
attrNum	The identifier of the variable attribute.
entryNum	The rEntry number.
dataType	The data type of the rEntry.

4.4.26.1. Example(s)

The following example gets the data type for the entry of rVariable “MY_VAR1” in the (variable) attribute “MY_ATTR” in a CDF.

```

.
.
.
void* id;                /* CDF identifier. */
int status;             /* Returned status code. */
int attrNum;           /* Attribute number. */
int entryNum;          /* rEntry number. */
int dataType;          /* rEntry data type. */
.
.
try {
    ....
    attrNum = CDFgetAttrNum (id, "MY_ATTR");
    entryNum = CDFgetVarNum(id, "MY_VAR1");
    status = CDFgetAttrEntryDataType (id, attrNum, entryNum, out dataType);
    Or
    status = CDFgetAttrEntryDataType (id, attrNum, entryNum, &dataType);
.
} catch (CDFException ex) {
    ...
}.
.

```

4.4.27 CDFgetAttrEntryNumElements

```
int CDFgetAttrEntryNumElements (                                /* out -- Completion status code. */
void* id,                                                       /* in -- CDF identifier. */
int attrNum,                                                    /* in -- Attribute identifier. */
int varNum,                                                     /* in -- rVariable number. */
TYPE numElems);                                               /* out -- rEntry's number of elements. */
                                                                /* TYPE -- int* or "out int". */
```

CDFgetAttrEntryNumElements returns the number of elements of the rEntry from an (variable) attribute in a CDF.

The arguments to CDFgetAttrEntryNumElements are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
attrNum	The identifier of the variable attribute.
varNum	The rVariable number.
numElems	The number of elements of the rEntry.

4.4.27.1. Example(s)

The following example gets the number of elements for the entry of rVariable “MY_VAR1” in the (variable) attribute “MY_ATTR” in a CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  attrNum;        /* Attribute number. */
int  varNum;         /* rVariable number. */
int  numElements;    /* rEntry's number of elements. */
.
.
try {
    ....
    attrNum = CDFgetAttrNum (id, "MY_ATTR");
    varNum = CDFgetVarNum(id, "MY_VAR1");
    status = CDFgetAttrEntryNumElements (id, attrNum, varNum, out numElements);
    Or
    status = CDFgetAttrEntryNumElements (id, attrNum, varNum, &numElements);
.
} catch (CDFException ex) {
    ...
}.
.
```

4.4.28 CDFgetAttrEntryNumStrings

```
int CDFgetAttrEntryNumStrings (                                /* out -- Completion status code. */
void* id,                                                       /* in -- CDF identifier. */
int attrNum,                                                    /* in -- Attribute identifier. */
int varNum,                                                     /* in -- rVariable number. */
TYPE numStrings);                                             /* out -- rEntry's number of strings. */
                                                                /* TYPE -- int* or "out int". */
```

CDFgetAttrEntryNumStrings returns the number of strings of the rEntry from an (variable) attribute in a CDF. This method is relevant to string typed entry.

The arguments to CDFgetAttrEntryNumStrings are defined as follows:

id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.

attrNum The identifier of the variable attribute.

varNum The rVariable number.

numStrings The number of strings of the rEntry.

4.4.28.1. Example(s)

The following example gets the number of strings for the entry of rVariable "MY_VAR1" in the (variable) attribute "MY_ATTR" in a CDF.

```
.
.
.
void*        id;                                                /* CDF identifier. */
int    status;                                                /* Returned status code. */
int    attrNum;                                               /* Attribute number. */
int    varNum;                                               /* rVariable number. */
int    numStrings;                                            /* rEntry's number of strings. */
.
.
try {
    ....
    attrNum = CDFgetAttrNum (id, "MY_ATTR");
    varNum = CDFgetVarNum(id, "MY_VAR1");
    status = CDFgetAttrEntryNumStrings (id, attrNum, varNum, out numStrings);
Or
    status = CDFgetAttrEntryNumStrings (id, attrNum, varNum, &numStrings);
.
} catch (CDFException ex) {
    ...
}.
.
```

4.4.29 CDFgetAttrEntryStrings

```
int CDFgetAttrEntryStrings (                                     /* out -- Completion status code. */
void* id,                                                       /* in -- CDF identifier. */
int attrNum,                                                    /* in -- Attribute identifier. */
int varNum,                                                     /* in -- rVariable number. */
TYPE strings);                                                /* out -- rEntry's data in strings. */
                                                                /* TYPE -- "out string[]" or "out object". */
```

CDFgetAttrEntryStrings returns the strings of the rEntry from an (variable) attribute in a CDF. This method is relevant to string typed entry.

The arguments to CDFgetAttrEntryStrings are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
attrNum	The identifier of the variable attribute.
varNum	The rVariable number.
strings	The strings of the rEntry data.

4.4.29.1. Example(s)

The following example gets the strings for the entry of rVariable "MY_VAR1" in the (variable) attribute "MY_ATTR" in a CDF.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  attrNum;        /* Attribute number. */
int  varNum;         /* rVariable number. */
string[] strings;    /* rEntry's returned strings. */
.
.
try {
    ....
    attrNum = CDFgetAttrNum (id, "MY_ATTR");
    varNum = CDFgetVarNum(id, "MY_VAR1");
    status = CDFgetAttrEntryStrings (id, attrNum, varNum, out strings);
.
} catch (CDFException ex) {
    ...
}.
.
```

4.4.30 CDFgetAttrScope

```
int CDFgetAttrScope (                                     /* out -- Completion status code. */
void* id,                                                /* in -- CDF identifier. */
int attrNum,                                           /* in -- Attribute number. */
TYPE attrScope);                                       /* out -- Attribute scope. */
                                                         /* TYPE -- int* or "out int". */
```

CDFgetAttrScope returns the attribute scope (GLOBAL_SCOPE or VARIABLE_SCOPE) of the specified attribute in a CDF. Refer to Section 2.13 for the description of the attribute scopes.

The arguments to CDFgetAttrScope are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
attrNum	The attribute number.
attrScope	The scope of the attribute.

4.4.30.1. Example(s)

The following example gets the scope of the attribute "MY_ATTR" in a CDF.

```
.
.
.
void* id;                                               /* CDF identifier. */
int status;                                           /* Returned status code. */
int attrNum;                                          /* Attribute number. */
int attrScope;                                       /* Attribute scope. */
.
.
try {
    ....
    attrNum = CDFgetAttrNum (id, "MY_ATTR");
    status = CDFgetAttrScope (id, attrNum, out attrScope);
    Or
    status = CDFgetAttrScope (id, attrNum, &attrScope);
.
} catch (CDFException ex) {
    ...
}.
.
```

4.4.31 CDFgetAttrzEntry²⁵

```
int CDFgetAttrzEntry(                                /* out -- Completion status code. */
void* id,                                           /* in -- CDF identifier. */
int attrNum,                                       /* in -- Variable attribute number. */
int entryNum,                                      /* in -- Entry number. */
TYPE value);                                       /* out -- Entry value. */
/* TYPE -- void*, "out string", "out string[]",
or "out object". */
```

CDFgetAttrzEntry is used to read zVariable's attribute entry.. In most cases it will be necessary to call CDFinquireAttrzEntry before calling this method in order to determine the data type and number of elements (of that data type) for the entry.

The arguments to CDFgetAttrzEntry are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
attrNum	The variable attribute number. This number may be determined with a call to CDFgetAttrNum.
entryNum	The variable attribute entry number that is the zVariable number from which the attribute entry is read.
value	The entry value.

4.4.31.1. Example(s)

The following example displays the value of the UNITS attribute for the PRES_LVL zVariable (but only if the data type is CDF_CHAR).

```
.
.
.
void*      id;                                     /* CDF identifier. */
int  status;                                     /* Returned status code. */
int  attrN;                                     /* Attribute number. */
int  entryN;                                    /* Entry number. */
int  dataType;                                  /* Data type. */
int  numElems;                                  /* Number of elements (of data type). */
.
try {
    ....
    attrN = CDFgetAttrNum (id, "UNITS");
    entryN = CDFgetVarNum (id, "PRES_LVL");      /* The zEntry number is the zVariable number. */
    status = CDFinquireAttrzEntry (id, attrN, entryN, out dataType, out numElems);
    if (dataType == CDF_CHAR) {
        string buffer;
        status = CDFgetAttrzEntry (id, attrN, entryN, out buffer);
    }
}
```

²⁵ An array of strings may be returned, after CDF V3.7.0.

```

    } catch (CDFException ex) {
    ...
    }.

```

4.4.32 CDFgetAttrzEntryDataType

```

int CDFgetAttrzEntryDataType (                               /* out -- Completion status code. */
void* id,                                                    /* in -- CDF identifier. */
int attrNum,                                                /* in -- Attribute identifier. */
int entryNum,                                              /* in -- zEntry number. */
TYPE dataType);                                           /* out -- zEntry data type. */
                                                         /* TYPE -- int* or "out int". */

```

CDFgetAttrzEntryDataType returns the data type of the zEntry for the specified variable attribute in a CDF. The data types are described in Section 2.6.

The arguments to CDFgetAttrzEntryDataType are defined as follows:

- id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
- attrNum The identifier of the variable attribute.
- entryNum The zEntry number that is the zVariable number.
- dataType The data type of the zEntry.

4.4.32.1. Example(s)

The following example gets the data type of the attribute named MY_ATTR for the zVariable MY_VAR1 in a CDF.

```

.
.
.
void*        id;                                            /* CDF identifier. */
int    status;                                           /* Returned status code. */
int    attrNum;                                          /* Attribute number. */
int    entryNum;                                        /* zEntry number. */
int    dataType;                                        /* zEntry data type. */
.
.
try {
    ....
    attrNum = CDFgetAttrNum (id, "MY_ATTR");
    entryNum = CDFgetVarNum(id, "MY_VAR1");
    status = CDFgetAttrzEntryDataType (id, attrNum, entryNum, out dataType);
Or
    status = CDFgetAttrzEntryDataType (id, attrNum, entryNum, &dataType);

```

```

.
} catch (CDFException ex) {
.
.
}
.

```

4.4.33 CDFgetAttrzEntryNumElements

```

int CDFgetAttrzEntryNumElements (                               /* out -- Completion status code. */
void* id,                                                       /* in -- CDF identifier. */
int attrNum,                                                    /* in -- Attribute identifier. */
int varNum,                                                     /* in -- zVariable number. */
TYPE numElems);                                               /* out -- zEntry's number of elements. */
                                                                /* TYPE -- int* or "out int". */

```

CDFgetAttrzEntryNumElements returns the number of elements of the zEntry for the specified variable attribute in a CDF.

The arguments to CDFgetAttrzEntryNumElements are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
attrNum	The identifier of the variable attribute.
varNum	The zVariable number.
numElems	The number of elements of the zEntry.

4.4.33.1. Example(s)

The following example returns the number of elements for attribute named MY_ATTR for the zVariable MY_VAR1 in a CDF

```

.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  attrNum;         /* Attribute number. */
int  varNum;          /* zVariable number. */
int  numElements;     /* zEntry's number of elements. */
.
.
try {
.
.
.
attrNum = CDFgetAttrNum (id, "MY_ATTR");
varNum = CDFgetVarNum(id, "MY_VAR1");
status = CDFgetAttrzEntryNumElements (id, attrNum, varNum, out numElements);
.
.
}

```



```

Or
    status = CDFgetAttrzEntryNumElements (id, attrNum, varNum, &numElements);

} catch (CDFException ex) {
    ...
}.
.

```

4.4.34 CDFgetAttrzEntryNumStrings

```

int CDFgetAttrzEntryNumStrings (                               /* out -- Completion status code. */
void* id,                                                       /* in -- CDF identifier. */
int attrNum,                                                    /* in -- Attribute identifier. */
int varNum,                                                     /* in -- zVariable number. */
TYPE numStrings);                                             /* out -- zEntry's number of strings. */
                                                                /* TYPE -- int* or "out int". */

```

CDFgetAttrzEntryNumStrings returns the number of strings of the zEntry from an (variable) attribute in a CDF. This method is relevant to string typed entry.

The arguments to CDFgetAttrzEntryNumStrings are defined as follows:

- id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
- attrNum The identifier of the variable attribute.
- varNum The zVariable number.
- numStrings The number of strings of the zEntry.

4.4.34.1. Example(s)

The following example gets the number of strings for the entry of zVariable "MY_VAR1" in the (variable) attribute "MY_ATTR" in a CDF.

```

.
.
.
void*        id;                                                /* CDF identifier. */
int    status;                                                /* Returned status code. */
int    attrNum;                                               /* Attribute number. */
int    varNum;                                               /* zVariable number. */
int    numStrings;                                            /* zEntry's number of strings. */
.
.
try {
    ....
    attrNum = CDFgetAttrNum (id, "MY_ATTR");
    varNum = CDFgetVarNum(id, "MY_VAR1");

```

```

    status = CDFgetAttrzEntryNumStrings (id, attrNum, varNum, out numStrings);
Or
    status = CDFgetAttrzEntryNumStrings (id, attrNum, varNum, &numStrings);
.
} catch (CDFException ex) {
    ...
}.
.

```

4.4.35 CDFgetAttrzEntryStrings

```

int CDFgetAttrzEntryStrings (                               /* out -- Completion status code. */
void* id,                                                  /* in -- CDF identifier. */
int attrNum,                                              /* in -- Attribute identifier. */
int varNum,                                              /* in -- zVariable number. */
TYPE strings);                                           /* out -- zEntry's data in strings. */
                                                         /* TYPE -- "out string[]" or "out object". */

```

CDFgetAttrzEntryStrings returns the strings of the zEntry from an (variable) attribute in a CDF. This method is relevant to string typed entry.

The arguments to CDFgetAttrzEntryStrings are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
attrNum	The identifier of the variable attribute.
varNum	The zVariable number.
strings	The strings of the zEntry data.

4.4.35.1. Example(s)

The following example gets the strings for the entry of zVariable "MY_VAR1" in the (variable) attribute "MY_ATTR" in a CDF.

```

.
.
.
void*      id;                                           /* CDF identifier. */
int status;                                           /* Returned status code. */
int attrNum;                                         /* Attribute number. */
int varNum;                                         /* zVariable number. */
string[] strings;                                     /* zEntry's returned strings. */
.
.
try {
    ....
    attrNum = CDFgetAttrNum (id, "MY_ATTR");

```

```

varNum = CDFgetVarNum(id, "MY_VAR1");
status = CDFgetAttrzEntryStrings (id, attrNum, varNum, out strings);

.
} catch (CDFException ex) {
.
...
}.
.

```

4.4.36 CDFgetNumAttrgEntries

```

int CDFgetNumAttrgEntries (                                     /* out -- Completion status code. */
void* id,                                                     /* in -- CDF identifier. */
int attrNum,                                                 /* in -- Attribute number. */
TYPE entries);                                              /* out -- Total gEntries. */
                                                            /* TYPE -- int* or "out int". */

```

CDFgetNumAttrgEntries returns the total number of entries (gEntries) written for the specified global attribute in a CDF.

The arguments to CDFgetNumAttrgEntries are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
attrNum	The attribute number.
entries	Number of gEntries for attrNum.

4.4.36.1. Example(s)

The following example retrieves the total number of gEntries for the global attribute MY_ATTR in a CDF.

```

.
.
.
int status;                                                 /* Returned status code. */
void* id;                                                  /* CDF identifier. */
int attrNum;                                              /* Attribute number. */
int numEntries;                                          /* Number of entries. */
int i;
.
.
try {
.
.
.
.
.
attrNum = CDFgetAttrNum(id, "MUY_ATTR");
status = CDFgetNumAttrgEntries (id, attrNum, out numEntries);
Or
status = CDFgetNumAttrgEntries (id, attrNum, &numEntries);

```

```

for (i=0; i < numEntries; i++) {
    .
    /* process an entry */
    .
}
.
} catch (CDFException ex) {
    ...
}.
.

```

4.4.37 CDFgetNumAttributes

```

int CDFgetNumAttributes (                               /* out -- Completion status code. */
void* id,                                             /* in -- CDF identifier. */
TYPE numAttrs);                                     /* out -- Total number of attributes. */
                                                    /* TYPE -- int* or "out int". */

```

CDFgetNumAttributes returns the total number of global and variable attributes in a CDF.

The arguments to CDFgetNumAttributes are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
numAttrs	The total number of global and variable attributes.

4.4.37.1. Example(s)

The following example returns the total number of global and variable attributes in a CDF.

```

.
.
int status;                                           /* Returned status code. */
void* id;                                           /* CDF identifier. */
int numAttrs;                                       /* Number of attributes. */
.
.
try {
    ....
    status = CDFgetNumAttributes (id, out numAttrs);
    Or
    status = CDFgetNumAttributes (id, &numAttrs);
    .
} catch (CDFException ex) {
    ...
}.

```

4.4.38 CDFgetNumAttrEntries

```
int CDFgetNumAttrEntries (                               /* out -- Completion status code. */
void* id,                                               /* in -- CDF identifier. */
int attrNum,                                           /* in -- Attribute number. */
TYPE entries);                                         /* out -- Total rEntries. */
                                                         /* TYPE -- int* or "out int". */
```

CDFgetNumAttrEntries returns the total number of entries (rEntries) written for the rVariables in the specified (variable) attribute of a CDF.

The arguments to CDFgetNumAttrEntries are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
attrNum	The attribute number.
entries	Total rEntries.

4.4.38.1. Example(s)

The following example returns the total number of rEntries from the variable attribute "MY_ATTR" in a CDF.

```
.
.
.
int status;                                           /* Returned status code. */
void* id;                                           /* CDF identifier. */
int attrNum;                                         /* Attribute number. */
int entries;                                         /* Number of entries. */
.
.
try {
    ....
    attrNum = CDFgetAttrNum(id, "MY_ATTR");
    status = CDFgetNumAttrEntries (id, attrNum, out entries);
    Or
    status = CDFgetNumAttrEntries (id, attrNum, &entries);
.
} catch (CDFException ex) {
    ...
}.
.
```



```

void* id,                                     /* in -- CDF identifier. */
TYPE numAttrs);                             /* out -- Total number of global attributes. */
                                              /* TYPE -- int* or "out int". */

```

CDFgetNumAttributes returns the total number of global attributes in a CDF.

The arguments to CDFgetNumAttributes are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
numAttrs	The number of global attributes.

4.4.40.1. Example(s)

The following example returns the total number of global attributes in a CDF.

```

.
.
.
int status;                                  /* Returned status code. */
void* id;                                    /* CDF identifier. */
int numAttrs;                                /* Number of global attributes. */

.
.
try {
    ....
    status = CDFgetNumAttributes (id, out numAttrs);
Or
    status = CDFgetNumAttributes (id, &numAttrs);
} catch (CDFException ex) {
    ...
}.
.

```

4.4.41 CDFgetNumvAttributes

```

int CDFgetNumvAttributes (                    /* out -- Completion status code. */
void* id,                                    /* in -- CDF identifier. */
TYPE numAttrs);                             /* out -- Total number of variable attributes. */
                                              /* TYPE -- int* or "out int". */

```

CDFgetNumvAttributes returns the total number of variable attributes in a CDF.

The arguments to CDFgetNumvAttributes are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
numAttrs	The number of variable attributes.

4.4.41.1. Example(s)

The following example returns the total number of variable attributes of a CDF.

```

.
.
.
int status; /* Returned status code. */
void* id; /* CDF identifier. */
int numAttrs; /* Number of variable attributes. */

.
.
try {
    ....
    status = CDFgetNumvAttributes (id, out numAttrs);
    Or
    status = CDFgetNumvAttributes (id, &numAttrs);
} catch (CDFException ex) {
    ...
}.
.

```

4.4.42 CDFinquireAttr

```

int CDFinquireAttr( /* out -- Completion status code. */
void* id, /* in -- CDF identifier. */
int attrNum, /* in -- Attribute number. */
out string attrName, /* out -- Attribute name. */
TYPE attrScope, /* out -- Attribute scope. */
TYPE maxgEntry, /* out -- Maximum gEntry number. */
TYPE maxrEntry, /* out -- Maximum rEntry number. */
TYPE maxzEntry); /* out -- Maximum zEntry number. */
/* TYPE -- int* or "out int". */

```

CDFinquireAttr is used to inquire information about the specified attribute. This method expands the method CDFattrInquire to provide an extra information about zEntry if the attribute has a variable scope.

The arguments to CDFinquireAttr are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
----	---

attrNum	The attribute number to inquire. This number may be determined with a call to CDFgetAttrNum.
attrName	The attribute's name that corresponds to attrNum. This string length is limited to CDF_ATTR_NAME_LEN256.
attrScope	The scope of the attribute (GLOBAL_SCOPE or VARIABLE_SCOPE). Attribute scopes are defined in Section 2.13.
maxgEntry	For vAttributes, this value of this field is -1 as it doesn't apply to global attribute entry (gEntry). For gAttributes, this is the maximum entry (gentry) number used. This number may not correspond with the number of entries (if some entry numbers were not used). If no entries exist for the attribute, then the value of -1 is returned.
maxrEntry	For gAttributes, this value of this field is -1 as it doesn't apply to rVariable attribute entry (rEntry). For vAttributes, this is the maximum rVariable attribute entry (rEntry) number used. This number may not correspond with the number of entries (if some entry numbers were not used). If no entries exist for the attribute, then the value of -1 is returned.
maxzEntry	For gAttributes, this value of this field is -1 as it doesn't apply to zVariable attribute entry (zEntry). For vAttributes, this is the maximum zVariable attribute entry (zEntry) number used. This may not correspond with the number of entries (if some entry numbers were not used). If no entries exist for the attribute, then the value of -1 is returned.

4.4.42.1. Example(s)

The following example displays the name of each attribute in a CDF. The number of attributes in the CDF is first determined by calling the method CDFinquireCDF. Note that attribute numbers start at zero (0) and are consecutive.

```

.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  numDims;        /* Number of dimensions. */
int[] dimSizes;      /* Dimension sizes (allocate to allow the
                    /* maximum number of dimensions). */

int  encoding;       /* Data encoding. */
int  majority;      /* Variable majority. */
int  maxRec;        /* Maximum record number in CDF. */
int  numVars;       /* Number of variables in CDF. */
int  numAttrs;     /* Number of attributes in CDF. */
int  attrN;        /* attribute number. */
string attrName;   /* attribute name. */
int  attrScope;   /* attribute scope. */
int  maxgEntry, maxrEntry, maxzEntry; /* Maximum entry numbers. */
.
.
try {
    ....
    status = CDFinquireCDF (id, out numDims, out dimSizes, out encoding, out majority, out maxRec,
                          out numVars, out numAttrs);
    for (attrN = 0; attrN < (int)numAttrs; attrN++) {

```



```

Int status; /* Returned status code. */
int attrN; /* attribute number. */
int entryN; /* Entry number. */
string attrName; /* attribute name. */
int attrScope; /* attribute scope. */
int maxEntry; /* Maximum entry number used. */
int dataType; /* Data type. */
int numElems; /* Number of elements (of the data type). */
.
.
try {
....
attrN = CDFgetAttrNum (id, "TITLE");
status = CDFattrInquire (id, attrN, attrName, out attrScope, out maxEntry);
for (entryN = 0; entryN <= maxEntry; entryN++) {
status = CDFinquireAttrEntry (id, attrN, entryN, out dataType, out numElems);
Or
status = CDFinquireAttrEntry (id, attrN, entryN, &dataType, &numElems);
/* process entries */
.
.
}
} catch (CDFException ex) {
...
}.

```

4.4.44 CDFinquireAttrEntry

```

int CDFinquireAttrEntry ( /* out -- Completion status code. */
void* id, /* in -- CDF identifier. */
int attrNum, /* in -- Attribute number. */
int entryNum, /* in -- Entry number. */
TYPE dataType, /* out -- Data type. */
TYPE numElements); /* out -- Number of elements (of the data type). */
/* TYPE -- int* or "out int". */

```

This method is identical to the method CDFattrEntryInquire. CDFinquireAttrEntry is used to inquire about an rVariable's attribute entry.

The arguments to CDFinquireAttrEntry are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
attrNum	The attribute number to inquire. This number may be determined with a call to CDFgetAttrNum.
entryNum	The entry number to inquire. This is the rVariable number (the rVariable being described in some way by the rEntry).
dataType	The data type of the specified entry. The data types are defined in Section 2.6.

numElements The number of elements of the data type. For character data types (CDF_CHAR and CDF_UCHAR), this is the number of characters in the string. For all other data types this is the number of elements in an array of that data type.

4.4.44.1. Example(s)

The following example determines the data type of the “UNITS” attribute for the rVariable “Temperature”, then retrieves and displays the value of the UNITS attribute.

```

.
.
.
void*      id;           /* CDF identifier. */
Int  status;           /* Returned status code. */
int  attrN;           /* Attribute number. */
int  entryN;          /* Entry number. */
int  dataType;        /* Data type. */
int  numElements;     /* Number of elements (of the data type). */
.
.
try {
    ....
    attrN = CDFgetAttrNum (id, "UNITS");
    entryN = CDFgetVarNum(id, "Temperature")
    status = CDFinquireAttrEntry (id, attrN, entryN, out dataType, out numElements);
    Or
    status = CDFinquireAttrEntry (id, attrN, entryN, &dataType, &numElements);
    if (dataType == CDF_CHAR) {
        string buffer;
        status = CDFgetAttrEntry (id, attrN, entryN, out buffer);
    }
.
} catch (CDFException ex) {
    ...
}.
.

```

4.4.45 CDFinquireAttrzEntry

```

int CDFinquireAttrzEntry (           /* out -- Completion status code. */
void* id,                           /* in -- CDF identifier. */
int attrNum,                        /* in -- (Variable) Attribute number. */
int entryNum,                       /* in -- zEntry number. */
TYPE dataType,                     /* out -- Data type. */
TYPE numElements);                /* out -- Number of elements (of the data type). */
/* TYPE -- int* or “out int”. */

```

CDFinquireAttrzEntry is used to inquire about a zVariable’s attribute entry.

The arguments to `CDFinquireAttrzEntry` are defined as follows:

<code>id</code>	The identifier of the CDF. This identifier must have been initialized by a call to <code>CDFcreate</code> (or <code>CDFcreateCDF</code>) or <code>CDFopenCDF</code> .
<code>attrNum</code>	The (variable) attribute number for which to inquire an entry. This number may be determined with a call to <code>CDFgetAttrNum</code> (see Section 4.4.24).
<code>entryNum</code>	The entry number to inquire. This is the <code>zVariable</code> number (the <code>zVariable</code> being described in some way by the <code>zEntry</code>).
<code>dataType</code>	The data type of the specified entry. The data types are defined in Section 2.6.
<code>numElements</code>	The number of elements of the data type. For character data types (<code>CDF_CHAR</code> and <code>CDF_UCHAR</code>), this is the number of characters in the string. For all other data types this is the number of elements in an array of that data type.

4.4.45.1. Example(s)

The following example determines the data type of the `UNITS` attribute for the `zVariable` `Temperature`, then retrieves and displays the value of the `UNITS` attribute.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  attrN;          /* attribute number. */
int  entryN;         /* Entry number. */
int  dataType;       /* Data type. */
int  numElements;   /* Number of elements (of the data type). */
.
.
try {
    ....
    attrN = CDFgetAttrNum (id, "UNITS");
    entryN = CDFgetVarNum (id, "Temperature")

    status = CDFinquireAttrzEntry (id, attrN, entryN, out dataType, out numElements);
Or
    status = CDFinquireAttrzEntry (id, attrN, entryN, &dataType, &numElements);
    if (dataType == CDF_CHAR) {
        string buffer ;
        status = CDFgetAttrzEntry (id, attrN, entryN, out buffer);
    }
} catch (CDFException ex) {
    ...
}.
.
```

4.4.46 CDFputAttrgEntry

```
int CDFputAttrgEntry(                                /* out -- Completion status code. */
void* id,                                           /* in -- CDF identifier. */
int attrNum,                                       /* in -- Attribute number. */
int entryNum,                                      /* in -- Attribute entry number. */
string value);                                     /* in -- Attribute entry value in string. */

int CDFputAttrgEntry(                                /* out -- Completion status code. */
void* id,                                           /* in -- CDF identifier. */
int attrNum,                                       /* in -- Attribute number. */
int entryNum,                                      /* in -- Attribute entry number. */
int dataType,                                     /* in -- Data type of this entry. */
int numElements,                                  /* in -- Number of elements in the entry (of the data type). */
TYPE value);                                       /* in -- Attribute entry value. */
/* TYPE -- void*, string or object. */
```

CDFputAttrgEntry is used to write a global attribute entry. The entry may or may not already exist. If it does exist, it is overwritten. The data type and number of elements (of that data type) may be changed when overwriting an existing entry. A global attribute can have one or more attribute entries.

The arguments to CDFputAttrgEntry are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
attrNum	The attribute number. This number may be determined with a call to CDFgetAttrNum.
entryNum	The attribute entry number.
dataType	The data type of the specified entry. Specify one of the data types defined in Section 2.6.
numElements	The number of elements of the data type. For character data types (CDF_CHAR and CDF_UCHAR), this is the number of characters in the string (An array of characters). For all other data types this is the number of elements in an array of that data type.
value	The value(s) to write. The entry value is written to the CDF from memory address value.

4.4.46.1. Example(s)

The following example writes a global attribute entry to the global attribute called TITLE.

```
.
.
.
void*      id;                                     /* CDF identifier. */
int  status;                                     /* Returned status code. */
int  entryNum;                                   /* Attribute entry number. */
string  title = "CDF title.";                   /* Value of TITLE attribute. */
.
```

```

entryNum = 0;
try {
    ....
    status = CDFputAttrEntry (id, CDFgetAttrNum(id,"TITLE"), entryNum, CDF_CHAR, title.Length, title);
} catch (CDFException ex) {
    ...
}.

```

4.4.47 CDFputAttrEntry

```

int CDFputAttrEntry(                                     /* out -- Completion status code. */
void* id,                                              /* in -- CDF identifier. */
int attrNum,                                          /* in -- Attribute number. */
int entryNum,                                        /* in -- Attribute entry number. */
string value);                                       /* in -- Attribute entry value in string. */

int CDFputAttrEntry(                                     /* out -- Completion status code. */
void* id,                                              /* in -- CDF identifier. */
int attrNum,                                          /* in -- Attribute number. */
int entryNum,                                        /* in -- Attribute entry number. */
int dataType,                                       /* in -- Data type. */
int numElems,                                       /* in -- Number of elements in the entry. */
TYPE value);                                       /* in -- Attribute entry value. */
/* TYPE -- void*, string or object. */

```

This method is identical to the method CDFattrPut. CDFputAttrEntry is used to write rVariable's attribute entry. The entry may or may not already exist. If it does exist, it is overwritten. The data type and number of elements (of that data type) may be changed when overwriting an existing entry.

The arguments to CDFputAttrEntry are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
attrNum	The attribute number. This number may be determined with a call to CDFgetAttrNum.
entryNum	The attribute entry number that is the rVariable number to which this attribute entry belongs.
dataType	The data type of the specified entry. Specify one of the data types defined in Section 2.6.
numElements	The number of elements of the data type. For character data types (CDF_CHAR and CDF_UCHAR), this is the number of characters in the string (An array of characters). For all other data types this is the number of elements in an array of that data type.
value	The value(s) to write. The entry value is written to the CDF from memory address value.

4.4.47.1. Example(s)

The following example writes to the variable scope attribute VALIDs for the entry, of two elements, that corresponds to the rVariable TMP.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  entryNum;       /* Entry number. */
int  numElements;   /* Number of elements (of data type). */
short[]  TMPvalids = new short[] {15,30}; /* Value(s) of VALIDs attribute,
                                           rEntry for rVariable TMP. */

.
numElements = 2;
try {
    ....
    status = CDFputAttrEntry (id, CDFgetAttrNum(id,"VALIDs"), CDFgetVarNum(id,"TMP"),
                             CDF_INT2, numElements, TMPvalids);
Or
    fixed (void* pTMPvalids = TMPvalids) {
        status = CDFputAttrEntry (id, CDFgetAttrNum(id,"VALIDs"), CDFgetVarNum(id,"TMP"),
                                   CDF_INT2, numElements, pTMPvalids);
    }
} catch (CDFException ex) {
    ...
}.
.
```

4.4.48 CDFputAttrEntryStrings

```
int CDFputAttrEntryStrings( /* out -- Completion status code. */
void* id,                  /* in -- CDF identifier. */
int attrNum,               /* in -- Attribute number. */
int varNum,                /* in -- rVariable number. */
TYPE values);             /* in -- Attribute entry values. */
                           /* TYPE -- string[] or object. */
```

CDFputAttrEntryStrings is used to write rVariable's attribute entry, which is an array of strings. The entry may or may not already exist. If it does exist, it is overwritten.

The arguments to CDFputAttrEntryStrings are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
attrNum	The attribute number. This number may be determined with a call to CDFgetAttrNum.

varNum	The attribute entry number that is the rVariable number to which this attribute entry belongs.
values	The value(s) to write. The entry value is written to the CDF from memory address value.

4.4.48.1. Example(s)

The following example writes to the variable scope attribute VALIDs for the entry, of two strings, that corresponds to the rVariable TMP.

```

.
.
.
void*      id;                /* CDF identifier. */
int  status;                 /* Returned status code. */
int  varNum;                 /* Entry number. */
string[]  TMPvalids = new string[] {"abc", "1234"}; /* Value(s) of VALIDs attribute,
                                                    rEntry for rVariable TMP. */
.
try {
    ....
    status = CDFputAttrEntryStrings (id, CDFgetAttrNum(id,"VALIDs"), CDFgetVarNum(id,"TMP"),
                                     TMPvalids);
.
} catch (CDFException ex) {
    ...
}.
.

```

4.4.49 CDFputAttrzEntry

```

int CDFputAttrzEntry(                /* out -- Completion status code. */
void* id,                          /* in -- CDF identifier. */
int attrNum,                       /* in -- Attribute number. */
int entryNum,                      /* in -- Attribute entry number. */
string value);                     /* in -- Attribute entry value in string. */

int CDFputAttrzEntry(                /* out -- Completion status code. */
void* id,                          /* in -- CDF identifier. */
int attrNum,                       /* in -- Attribute number. */
int entryNum,                      /* in -- Attribute entry number. */
int dataType,                     /* in -- Data type of this entry. */
int numElements,                  /* in -- Number of elements in the entry (of the data type). */
TYPE value);                       /* in -- Attribute entry value. */
/* TYPE -- void*, string or object. */

```

CDFputAttrzEntry is used to write zVariable's attribute entry. The entry may or may not already exist. If it does exist, it is overwritten. The data type and number of elements (of that data type) may be changed when overwriting an existing entry.

The arguments to CDFputAttrzEntry are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
attrNum	The (variable) attribute number. This number may be determined with a call to CDFgetAttrNum (see Section 4.4.24).
entryNum	The entry number that is the zVariable number to which this attribute entry belongs.
dataType	The data type of the specified entry. Specify one of the data types defined in Section 2.6.
numElements	The number of elements of the data type. For character data types (CDF_CHAR and CDF_UCHAR), this is the number of characters in the string (An array of characters). For all other data types this is the number of elements in an array of that data type.
value	The value(s) to write. The entry value is written to the CDF from memory address value.

4.4.49.1. Example(s)

The following example writes a zVariable's attribute entry. The entry has two elements (that is two values for non-CDF_CHAR type). The zEntry in the variable scope attribute VALIDs corresponds to the zVariable TMP.

```

.
.
.
void*      id;           /* CDF identifier. */
int  status;           /* Returned status code. */
int  numElements;     /* Number of elements (of data type). */
short[]    TMPvalids = new short[] {15,30}; /* Value(s) of VALIDs attribute,
                                           zEntry for zVariable TMP. */
.
.
numElements = 2;
try {
    ....
    status = CDFputAttrzEntry (id, CDFgetAttrNum(id,"VALIDs"), CDFgetVarNum(id,"TMP"),
                              CDF_INT2, numElements, TMPvalids);
Or
    fixed (void* pTMPvalids = TMPvalids) {
        status = CDFputAttrzEntry (id, CDFgetAttrNum(id,"VALIDs"), CDFgetVarNum(id,"TMP"),
                                   CDF_INT2, numElements, pTMPvalids);
    }
} catch (CDFException ex) {
    ...
}.

```

4.4.50 CDFputAttrzEntryStrings

```
int CDFputAttrzEntryStrings(                                     /* out -- Completion status code. */
void* id,                                                       /* in -- CDF identifier. */
int attrNum,                                                   /* in -- Attribute number. */
int varNum,                                                    /* in -- zVariable number. */
TYPE value);                                                  /* in -- Attribute entry value. */
                                                             /* TYPE -- string[] or object. */
```

CDFputAttrzEntryStrings is used to write zVariable's attribute entry, which is an array of strings. The entry may or may not already exist. If it does exist, it is overwritten.

The arguments to CDFputAttrzEntryStrings are defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
attrNum	The attribute number. This number may be determined with a call to CDFgetAttrNum.
varNum	The attribute entry number that is the zVariable number to which this attribute entry belongs.
value	The value(s) to write. The entry value is written to the CDF from memory address value.

4.4.50.1. Example(s)

The following example writes to the variable scope attribute VALIDs for the entry, of two strings, that corresponds to the zVariable TMP.

```
.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  varNum;         /* Entry number. */
string[]  TMPvalids = new string[] {"abc", "1234"}; /* Value(s) of VALIDs attribute,
                                                         zEntry for rVariable TMP. */
.
try {
    ....
    status = CDFputAttrzEntryStrings (id, CDFgetAttrNum(id,"VALIDs"), CDFgetVarNum(id,"TMP"),
                                     TMPvalids);
.
} catch (CDFException ex) {
    ...
}.
}
```

4.4.51 CDFrenameAttr

```
int CDFrenameAttr(                                     /* out -- Completion status code. */
void* id,                                             /* in -- CDF identifier. */
int attrNum,                                         /* in -- Attribute number. */
string attrName);                                    /* in -- New attribute name. */
```

This method is identical to method CDFattrRename. CDFrenameAttr renames an existing attribute.

4.4.51.1. Example(s)

In the following example the attribute named LAT is renamed to LATITUDE.

```
.
.
.
void*      id;                                       /* CDF identifier. */
int  status;                                       /* Returned status code. */
.
.
try {
    ....
    status = CDFrenameAttr (id, CDFgetAttrNum(id,"LAT"), "LATITUDE");
.
} catch (CDFException ex) {
    ...
}.
.
```

4.4.52 CDFsetAttrgEntryDataSpec

```
int CDFsetAttrgEntryDataSpec (                       /* out -- Completion status code. */
void* id,                                             /* in -- CDF identifier. */
int attrNum,                                         /* in -- Attribute number. */
int entryNum,                                        /* in -- gEntry number. */
int dataType);                                       /* in -- Data type. */
```

CDFsetAttrgEntryDataSpec respecifies the data type of a gEntry of a global attribute in a CDF. The new and old data type must be equivalent. Refer to the CDF User's Guide for descriptions of equivalent data types.

The arguments to CDFsetAttrgEntryDataSpec are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
----	---

attrNum	The global attribute number.
entryNum	The gEntry number.
dataType	The new data type.

4.4.52.1. Example(s)

The following example modifies the third entry's (entry number 2) data type of the global attribute MY_ATTR in a CDF. It will change its original data type from CDF_INT2 to CDF_UINT2.

```

.
.
.
void* id;           /* CDF identifier. */
int  status;       /* Returned status code. */
int  entryNum;     /* gEntry number. */
int  dataType;     /* The new data type */
.
.
entryNum = 2;
dataType = CDF_UINT2;
numElems = 1;
try {
    ....
    status = CDFsetAttrEntryDataSpec (id, CDFgetAttrNum(id, "MY_ATTR"), entryNum, dataType);
.
} catch (CDFException ex) {
    ...
}.
.

```

4.4.53 CDFsetAttrEntryDataSpec

```

int CDFsetAttrEntryDataSpec (           /* out -- Completion status code. */
void* id,                               /* in -- CDF identifier. */
int attrNum,                            /* in -- Attribute number. */
int entryNum,                           /* in -- rEntry number. */
int dataType,                           /* in -- Data type. */
int numElements);                      /* in -- Number of elements. */

```

CDFsetAttrEntryDataSpec respecifies the data specification (data type and number of elements) of an rEntry of a variable attribute in a CDF. The new and old data type must be equivalent, and the number of elements must not be changed. Refer to the CDF User's Guide for descriptions of equivalent data types.

The arguments to CDFsetAttrEntryDataSpec are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
----	---

attrNum	The variable attribute number.
entryNum	The rEntry number.
dataType	The new data type.
numElements	The new number of elements.

4.4.53.1. Example(s)

The following example modifies the data specification for an rEntry, corresponding to rVariable “MY_VAR”, in the variable attribute “MY_ATTR” in a CDF. It will change its original data type from CDF_INT2 to CDF_UINT2.

```

.
.
.
void*      id;          /* CDF identifier. */
int  status;          /* Returned status code. */
int  dataType, numElements; /* Data type and number of elements. */
.
.
dataType = CDF_UINT2;
numElems = 1;
try {
    ....
    status = CDFsetAttrEntryDataSpec (id, CDFgetAttrNum(id, “MY_ATTR”), CDFgetVarNum(id, “MY_VAR”),
                                     dataType, numElems);
.
} catch (CDFException ex) {
    ...
}.
.

```

4.4.54 CDFsetAttrScope

```

int CDFsetAttrScope (          /* out -- Completion status code. */
void* id,                    /* in -- CDF identifier. */
int attrNum,                 /* in -- Attribute number. */
int scope);                  /* in -- Attribute scope. */

```

CDFsetAttrScope respecifies the scope of an attribute in a CDF. Specify one of the scopes described in Section 2.13. Global-scoped attributes will contain only gEntries, while variable-scoped attributes can hold rEntries and zEntries.

The arguments to CDFsetAttrScope are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
attrNum	The attribute number.

scope The new attribute scope. The value should be either VARIABLE_SCOPE or GLOBAL_SCOPE.

4.4.54.1. Example(s)

The following example changes the scope of the global attribute named MY_ATTR to a variable attribute (VARIABLE_SCOPE).

```
.
.
.
void*            id;                    /* CDF identifier. */
int  status;                    /* Returned status code. */
int  scope;                    /* New attribute scope. */
.
.
scope = VARIABLE_SCOPE;
try {
    ....
    status = CDFsetAttrScope (id, CDFgetAttrNum(id, "MY_ATTR"), scope);
} catch (CDFException ex) {
    ...
}.
.
```

4.4.55 CDFsetAttrzEntryDataSpec

```
int CDFsetAttrzEntryDataSpec (                    /* out -- Completion status code. */
void* id,                    /* in -- CDF identifier. */
int attrNum,                    /* in -- Attribute number. */
int entryNum,                    /* in -- zEntry number. */
int dataType)                    /* in -- Data type. */
```

CDFsetAttrzEntryDataSpec modifies the data type of a zEntry of a variable attribute in a CDF. The new and old data type must be equivalent. Refer to the CDF User's Guide for the description of equivalent data types.

The arguments to CDFsetAttrzEntryDataSpec are defined as follows:

id	The identifier of the current CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopenCDF.
attrNum	The variable attribute number.
entryNum	The zEntry number that is the zVariable number.
dataType	The new data type.


```

bool encoding, /* in -- Whether to encode CDF epoch type */
bool basic, /* in -- Whether to get CDF basic information */
bool global, /* in -- Whether to get global metadata */
bool varspec, /* in -- Whether to get each variable's specification */
bool varmeta, /* in -- Whether to get each variable's metadata */
bool vardata); /* in -- Whether to get each variable's data */

Dictionary<string,object> ReadCDF ( /* out -- A dictionary . */
void* id, /* in -- CDF identifier. */
bool encoding, /* in -- Whether to encode CDF epoch type */
bool basic, /* in -- Whether to get CDF basic information */
bool global, /* in -- Whether to get global metadata */
bool varspec, /* in -- Whether to get each variable's specification */
bool varmeta, /* in -- Whether to get each variable's metadata */
bool vardata, /* in -- Whether to get each variable's data */
bool noentry); /* in -- Whether to show attributes without entry */

```

ReadCDF reads the specific element or all CDF information. There are three main key/value elements in the top of retrieved dictionary. The keys are “CDFInfo”, “GlobalAttributes” and “Variables”. Each of the values is also a dictionary itself. There may be another key/value element: “NoEntryAttributes” in the top dictionary.

The argument to ReadCDF is defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.
----	--

Optionally,

encoding	Whether to encode any CDF epoch data type in global or variable metadata into date/time string.
basic	Whether to read the CDF basic information.
global	Whether to read the global attributes.
var	Whether to read information from all variables.
varspec	Whether to read each variable's specification.
varmeta	Whether to read each variable's metadata.
vardata	Whether to read variable's data
noentry	Whether to collect the attribute names that don't have any entry data

4.5.1.1. Example(s)

The following example reads the whole information from the CDF, test.cdf and displays it.

```

.
.
.
void*      id; /* CDF identifier. */
int        status; /* Returned status code. */
Dictionary<string, object> cdf; /* Retrieved information. */
.
.
try {
...
status = CDFopen ("test", &id);
cdf = ReadCDFInfo (id);
CDFUtils.PrintDictionary (cdf);

```

```

...
...
} catch (CDFException ex) {
...
}
.
.

```

The output of the dictionary dump from the CDF looks as follows. The four keys are CDFInfo, GlobalAttributes, Variables and NoEntryAttributes. The value for CDFInfo is a dictionary, which contains the basic information about the CDF. The value for GlobalAttributes is a dictionary of dictionaries. Each element in the dictionary has the attribute name as the key with its value being another dictionary (with entry number being the key and value being the entry). The value for Variables is a dictionary of dictionaries. Each element in the dictionary is for information from a variable. The variable name is then the key for its specification, metadata and data, each of which is also a dictionary. If there is any attribute(s), global or variable, that has no entry data, its name will be collected in a list as a "GlobalAttributes" or "VariableAttributes" key element in the "NoEntryAttributes" dictionary.

```

CDFInfo =>
  Version => "3.7.0"
  Majority => "ROW"
  Format => "SINGLE"
  Encoding => "IBMPC"
...
...
GlobalAttributes =>
  Project
    0 => "..."
  PI =>
    0 => "Mr.Smith"
  Text =>
    0 => "Line 1"
    1 => "Line 2"
...
...
Key:Variables =>
  Var1 =>
    VarInfo
      DataType => "CDF_INT2"
      NumElements => 1
      NumDims => 1
      ...
      ...
      ...
    Key:VarMetaData =>
      VALIDMIN => 20
      VALIDMAX => 90
      ...
      ...
    VarData => 1 2 3
  Var2 =>
    VarInfo =>
      DataType => "CDF_INT4"
      NumElements => 1
      NumDims => 0
      ...

```

```

...
...
VarMetaData =>
  VALIDMIN => 2000
  VALIDMAX => 9000
...
...
VarData => 1
          2
          3
Var3 =>
VarInfo =>
  DataType => "CDF_DOUBLE"
  NumElements => 1
  NumDims => 1
...
...
...
VarMetaData =>
  VALIDMIN => 20.0
  VALIDMAX => 90.0
...
...
VarData => 1.1 2.2 3.3
...
...
NoEntryAttributes =>
  GlobalAttributes => "g1"
  VariableAttributes => "a1"

```

4.5.2 ReadCDFGlobalAttributes

```
Dictionary<string,object> ReadCDFGlobalAttributes (
void* id);
```

```
/* out – A dictionary . */
/* in -- CDF identifier. */
```

```
Dictionary(string,object> ReadCDFGlobalAttributes (
void* id,
bool encoding);
```

```
/* out – A dictionary . */
/* in -- CDF identifier. */
/* in -- Whether to encode CDF epoch type */
```

ReadCDFGlobalAttributes reads the global attributes for a given CDF. The value(s) in the key/value pair(s) from the returned dictionary can be a dictionary itself.

The argument to ReadCDFGlobalAttributes is defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.
Optionally,	
encoding	Whether to encode any CDF epoch data type in global or variable metadata.

4.5.2.1. Example(s)

The following example reads the global attributes from the CDF, test.cdf and displays it.

```
.
.
.
void*      id;          /* CDF identifier. */
int        status;     /* Returned status code. */
Dictionary<string, object> meta; /* Retrieved information. */
.
.
try {
    ...
    status = CDFopen ("test", &id);
    meta = ReadCDFGlobalAttributes (id);
    CDFUtils.PrintDictionary (meta);
    ...
    ...
} catch (CDFException ex) {
    ...
}
.
.
```

The output of the dictionary dump from the global attributes in the CDF looks as follows. Each key field represents a global attribute name, and its value, which is another dictionary of <integer, object> type pair(s). The number represents the entry number and the object can be a scalar or array of an entry type.

```
Project =>
  0 => "Using the CDFJava API "
PI
  3 => "Ernie Els"
Test =>
  0 => 5.3432
  2 => 5.5
  3 => 5.5 10.2
  4 => 1
  5 => 1 2 3
  6 => -32768
  7 => 1 2
  8 => 3
  9 => 4 5
  10 => "This is a string"
  11 => 4294967295
  12 => 4294967295 2147483648
  13 => 65535
  14 => 65535 65534
  15 => 255
  16 => 255 254
TestDate =>
  1 => "2002-04-25T00:00:00.000"
  2 => "2008-02-04T06:08:10.012014016"
epTestDate =>
  0 => "2004-05-13T15:08:11.022033044055"
```

4.5.3 ReadCDFInfo

```
Dictionary<string,object> ReadCDFInfo (          /* out – A dictionary . */  
void* id)                                       /* in -- CDF identifier. */
```

ReadCDFInfo reads the basic information about a CDF.

The argument to ReadCDFInfo is defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.
----	--

4.5.3.1. Example(s)

The following example reads the whole information from the CDF, test.cdf and displays it.

```
.  
. .  
void*      id;          /* CDF identifier. */  
int        status;     /* Returned status code. */  
Dictionary<string, object> cdf; /* Retrieved information. */  
. .  
try {  
    ...  
    status = CDFopen ("test", &id);  
    cdf = ReadCDFInfo (id);  
    CDFUtils.PrintDictionary (cdf);  
    ...  
    ...  
} catch (CDFException ex) {  
    ...  
}  
. .
```

The output of the basic CDF information looks as follows (first field as the key and second field as the value):

```
Version => "3.7.0"  
Majority => "ROW"  
Format => "SINGLE"  
Encoding => "IBMPC"  
NumGlobalAttrs => 5  
NumNumVarAttrs => 5  
NumVars => 21  
LastLeapSecond => 20150701
```

4.5.4 ReadCDFVariable

```
Dictionary<string,object> ReadCDFVariable(  
void* id,  
int varid);
```

```
/* out – A dictionary . */  
/* in -- CDF identifier. */  
/* in -- variable identifier. */
```

```
Dictionary<string,object> ReadCDFVariable(  
void* id,  
int varid,  
bool encoding);  
*/
```

```
/* out – A dictionary . */  
/* in -- CDF identifier. */  
/* in -- variable identifier. */  
/* in -- Whether to encode CDF epoch type.
```

ReadCDFVariable reads the information from a specified variable in a CDF into a dictionary. The variable information includes the variable specification with key: “VarInfo”, its metadata with key: “VarMetaData” and all data with key: “VarData”, if they exist. The retrieved information consists of the information from these three functions: ReadCDFVariableInfo, ReadCDFVariableAttributes and ReadCDFVariableData.

The argument to ReadCDFVariable is defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.
varid	The variable identifier in the CDF. This identifier is based on the CDF open with zMODEon2 (all variables are being handled as zVariables) if there are rVariables and zVariables in a CDF. The variable identifier reflects the variable after renumbered.

Optionally,

encoding	Whether to encode the CDF epoch data type into date/time string.
----------	--

4.5.4.1. Example(s)

The following example collects the information from a variable ‘Var1’ in the CDF, test.cdf and displays it.

```
.  
. .  
. .  
void*      id;          /* CDF identifier. */  
int        status;     /* Returned status code. */  
int        varid;      /* Variable identifier. */  
Dictionary<string, object> var; /* Retrieved information. */  
. .  
try {  
    ...  
    status = CDFopen (“test”, &id);  
    status = CDFsetzMode (id, zMODEon2);  
    varid = CDFgetVarNum (id, “Var1”);  
    var = ReadCDFVariable (id, varid);  
    ...  
    ...  
} catch (CDFException ex) {
```

```
    ...
  }
  .
  .
```

The output of the variable dictionary dump looks as follows. Basically, there are three key/value pairs at the top level for variable's specification, metadata and data, identified by the Key name. For specification and metadata, its value is another dictionary.

```
VarInfo =>
  DataType => "CDF_INT2"
  NumElements => 1
  NumDims => 1
  DimSizes => 3
  NumWrittenRecs => 20
  PadValue => -32767
VarMetaData =>
  VALIDMIN => -100
  VALIDMAX => 180
  FILLVAL => -999
  ...
  ...
VarData => 100 200 300
  -32767 -32767 -32767
  10 20 30
  40 32767 -32768
  -32767 -32767 -32767
  -32767 -32767 -32767
  -32767 -32767 -32767
  -32767 -32767 -32767
  -32767 -32767 -32767
  -32767 -32767 -32767
  11 22 33
  -32767 -32767 -32767
  -32767 -32767 -32767
  -32767 -32767 -32767
  -32767 -32767 -32767
  -32767 -32767 -32767
```

4.5.5 ReadCDFVariables

```
Dictionary<string,object> ReadCDFVariables(                               /* out – A dictionary . */
void* id);                                                                /* in -- CDF identifier. */

Dictionary<string,object> ReadCDFVariables(                               /* out – A dictionary . */
void* id,                                                                /* in -- CDF identifier. */
bool encoding);                                                         /* in -- Whether to encode CDF epoch type.
*/
```

ReadCDFVariables reads the information from all variables in a CDF into a dictionary. Each element in the dictionary has the variable name as the key and its information as the value, which is a dictionary itself. The variable information includes the variable specification (with key: "VarInfo"), its metadata (with key: "VarMetaData") and all data (with key: "VarData"), if they exist.

The argument to ReadCDFVariables is defined as follows:

id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.

Optionally,

encoding Whether to encode the CDF epoch data type into date/time string for metadata.

4.5.5.1. Example(s)

The following example collects the information from a variable 'Var1' in the CDF, test.cdf and displays it.

```
.
.
.
void*      id;                /* CDF identifier. */
int        status;           /* Returned status code. */
int        varid;            /* Variable identifier. */
Dictionary<string, object>  cdf; /* Retrieved information. */
.
.
try {
    ...
    status = CDFopen ("test", &id);
    cdf = ReadCDFVariables (id);
    ...
    CDFUtils.PrintDictionary (cdf);
} catch (CDFException ex) {
    ...
}
.
.
```

The output of the variable dictionary dump looks as follows. Basically, there are three key/value pairs at the top level for variable's specification, metadata and data, identified by the Key name. For specification and metadata, its value is another dictionary.

```
Var1 =>
VarInfo =>
  DataType => "CDF_INT1"
  NumElements => 1
  NumDims => 1
  DimSizes => 3
  NumWrittenRecs => 1
  PadValue => -127
VarMetaData =>
  VALIDMIN => 20
  VALIDMAX => 90
VarData => 1 2 3
Var2 =>
VarInfo =>
  DataType => "CDF_UINT1"
  NumElements => 1
```



```

NumDims => 1
DimSizes => 3
NumWrittenRecs => 3
PadValue => 254
VarData => 254 254 5
          15 25 35
          100 128 255
Var3 =>
VarInfo =>
  DataType => "CDF_INT2"
  NumElements => 1
  NumDims => 1
  DimSizes => 3
  NumWrittenRecs => 20
  PadValue => -32767
VarMetaData =>
  VALIDMIN => -100
  VALIDMAX => 180
...
...
VarData => 100 200 300
          -32767 -32767 -32767
          10 20 30
          40 32767 -32768
          -32767 -32767 -32767
          -32767 -32767 -32767
          -32767 -32767 -32767
          -32767 -32767 -32767
          -32767 -32767 -32767
          -32767 -32767 -32767

```

4.5.6 ReadCDFVariableAttributes

```

Dictionary<string,object> ReadCDFVariableAttributes(
void* id,
int varid);

```

```

/* out – A dictionary . */
/* in -- CDF identifier. */
/* in -- variable identifier. */

```

```

Dictionary<string,object> ReadCDFVariableAttributes(
void* id,
int varid,
bool encoding);
*/

```

```

/* out – A dictionary . */
/* in -- CDF identifier. */
/* in -- variable identifier. */
/* in -- Whether to encode CDF epoch type.

```

ReadCDFVariableAttributes reads the specified variable's metadata in a CDF into a dictionary. The key for the key/value pair(s) in the dictionary is the variable attribute name.

The argument to ReadCDFVariableAttributes is defined as follows:

id	The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.
varid	The variable identifier in the CDF. This identifier is based on the CDF open with zMODEon2 (all variables are being handled as zVariables) if there are rVariables and zVariables in a CDF. The variable identifier reflects the variable after renumbered.

Optionally,

encoding Whether to encode the CDF epoch data type into date/time string.

4.5.6.1. Example(s)

The following example collects the metadata from a variable 'Var1' in the CDF, test.cdf and displays it.

```
.
.
.
void*      id;           /* CDF identifier. */
int        status;      /* Returned status code. */
int        varid;       /* Variable identifier. */
Dictionary<string, object>  attrs; /* Retrieved information. */
.
.
try {
    ...
    status = CDFopen ("test", &id);
    status = CDFsetzMode (id, zMODEon2);
    varid = CDFgetVarNum (id, "Var1");
    attrs = ReadCDFVariableAttributes (id, varid);
    CDFUtils.PrintDictionary (attrs);
    ...
    ...
} catch (CDFException ex) {
    ...
}
.
.
```

The output of the variable attributes dictionary dump looks as follows (the key is variable attribute name):

```
VALIDMIN => -100
VALIDMAX => 180
FILLVAL => -999
...
...
```

4.5.7 ReadCDFVariableData

```
object ReadCDFVariableData(           /* out -- A dictionary . */
void* id,                             /* in -- CDF identifier. */
int varid);                          /* in -- variable identifier. */
```

ReadCDFVariableData reads the specified variable's data in a CDF into an object.

The argument to ReadCDFVariableData is defined as follows:

id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.

varid The variable identifier in the CDF. This identifier is based on the CDF open with **zMODEon2** (all variables are being handled as zVariables) if there are rVariables and zVariables in a CDF. The variable identifier reflects the variable after renumbered.

4.5.7.1. Example(s)

The following example reads the full data from a variable ‘Var1’ in the CDF, test.cdf.

```

void*      id;          /* CDF identifier. */
int        status;     /* Returned status code. */
int        varid;      /* Variable identifier. */
object     data;       /* Retrieved data. */
.
.
try {
...
status = CDFopen (“test”, &id);
status = CDFsetzMode (id, zMODEon2);
varid = CDFgetVarNum (id, “Var1”);
data = ReadCDFVariableData (id, varid);
...
...
} catch (CDFException ex) {
...
}
.
.

```

4.5.8 ReadCDFVariableInfo

```

Dictionary<string,object> ReadCDFVariableInfo(          /* out – A dictionary . */
void* id,                                             /* in -- CDF identifier. */
int varid);                                          /* in -- variable identifier. */

Dictionary<string,object> ReadCDFVariableInfo(          /* out – A dictionary . */
void* id,                                             /* in -- CDF identifier. */
int varid,                                          /* in -- variable identifier. */
bool encoding);                                     /* in -- Whether to encode CDF epoch type. */
*/

```

ReadCDFVariableInfo reads the specified variable’s specification in a CDF into a dictionary.

The argument to ReadCDFVariableInfo is defined as follows:

id The identifier of the CDF. This identifier must have been initialized by a call to CDFcreate (or CDFcreateCDF) or CDFopen.

varid The variable identifier in the CDF. This identifier is based on the CDF open with **zMODEon2** (all variables are being handled as zVariables) if there are rVariables and zVariables in a CDF. The variable identifier reflects the variable after renumbered.

Optionally,

encoding Whether to encode the CDF epoch data type into date/time string.

4.5.8.1. Example(s)

The following example collects the basic information from a variable 'Var1' in the CDF, test.cdf and displays it.

```
.
.
.
void*      id;           /* CDF identifier. */
int        status;      /* Returned status code. */
int        varid;       /* Variable identifier. */
Dictionary<string, object> info; /* Retrieved information. */
.
.
try {
    ...
    status = CDFopen ("test", &id);
    status = CDFsetzMode (id, zMODEon2);
    varid = CDFgetVarNum (id, "Var1");
    info = ReadCDFVariableInfo (id, varid);
    CDFUtils.PrintDictionary (info);
    ...
    ...
} catch (CDFException ex) {
    ...
}
.
.
```

The output of the dictionary dump for the specification of the variable looks as follows (first field as the key and second field as the value):

```
DataType => "CDF_INT2"
NumElements => 1
NumDims => 1
DimSizes => 3
NumWrittenRecs => 20
PadValue => -32767
```


Chapter 5

5 Interpreting CDF Status Codes

Most CDF APIs return a status code of type `int`. The symbolic names for these codes are defined in `CDFException.cs` and should be used in your applications rather than using the true numeric values. Appendix A explains each status code. When the status code returned from a CDF API is tested, the following rules apply.

<code>status > CDF_OK</code>	Indicates successful completion but some additional information is provided. These are informational codes.
<code>status = CDF_OK</code>	Indicates successful completion.
<code>CDF_WARN < status < CDF_OK</code>	Indicates that the function completed but probably not as expected. These are warning codes.
<code>status < CDF_WARN</code>	Indicates that the function did not complete. These for most cases are error codes, thus an exception might be thrown.

The following example shows how you could check the status code returned from CDF functions.

```
int status;

try {
    status = CDFfunction (...);    /* any CDF function returning int */
} catch (CDFException ex) {
    ....
}
```

In your own status handler you can take whatever action is appropriate to the application. An example status handler follows. Note that no action is taken in the status handler if the status is `CDF_OK`.

```
int status = ex.GetCurrentStatus();
string errorMsg = ex.GetStatusMsg(status);
```

Explanations for all CDF status codes are available to your applications through the method `CDFError`. `CDFError` encodes in a text string an explanation of a given status code.

Chapter 6

6 EPOCH Utility Routines

Several functions exist that compute, decompose, parse, and encode CDF_EPOCH and CDF_EPOCH16 values. These functions may be called by applications using the CDF_EPOCH and CDF_EPOCH16 data types and are included in the CDF library. The Concepts chapter in the CDF User's Guide describes EPOCH values. All these APIs are defined as static methods in **CDFAPIs** class. The date/time components for CDF_EPOCH and CDF_EPOCH16 are **UTC-based**, without leap seconds.

The CDF_EPOCH and CDF_EPOCH16 data types are used to store time values referenced from a particular epoch. For CDF that epoch values for CDF_EPOCH and CDF_EPOCH16 are 01-Jan-0000 00:00:00.000 and 01-Jan-0000 00:00:00.000.000.000.000, respectively.

6.1 computeEPOCH

```
double computeEPOCH(
int year,
int month,
int day,
int hour,
int minute,
int second,
int msec);
/* out -- CDF_EPOCH value returned. */
/* in -- Year (AD, e.g., 1994). */
/* in -- Month (1-12). */
/* in -- Day (1-31). */
/* in -- Hour (0-23). */
/* in -- Minute (0-59). */
/* in -- Second (0-59). */
/* in -- Millisecond (0-999). */

double[] computeEPOCH(
int[] year,
int[] month,
int[] day,
int[] hour,
int[] minute,
int[] second,
int[] msec);
/* out -- Array of CDF_EPOCH values. */
/* in -- Years (AD, e.g., 1994). */
/* in -- Months (1-12). */
/* in -- Days (1-31). */
/* in -- Hours (0-23). */
/* in -- Minutes (0-59). */
/* in -- Seconds (0-59). */
/* in -- Milliseconds (0-999). */
```

computeEPOCH calculates a single or an array of CDF_EPOCH values given the individual components. If an illegal component is detected, the value returned will be ILLEGAL_EPOCH_VALUE.

NOTE: There are two variations on how computeEPOCH may be used. If the month argument is 0 (zero), then the day argument is assumed to be the day of the year (DOY) having a range of 1 through 366. Also, if the hour, minute, and second arguments are all 0 (zero), then the msec argument is assumed to be the millisecond of the day having a range of 0 through 86400000.

6.2 EPOCHbreakdown

```
void EPOCHbreakdown(
double epoch,
TYPE year,
TYPE month,
TYPE day,
TYPE hour,
TYPE minute,
TYPE second,
TYPE msec);
/* in -- The CDF_EPOCH value. */
/* out -- Year (AD, e.g., 1994). */
/* out -- Month (1-12). */
/* out -- Day (1-31). */
/* out -- Hour (0-23). */
/* out -- Minute (0-59). */
/* out -- Second (0-59). */
/* out -- Millisecond (0-999). */
/* TYPE -- int* or "out int". */

void EPOCHbreakdown(
double[] epoch,
out int[] year,
out int[] month,
out int[] day,
out int[] hour,
out int[] minute,
out int[] second,
out int[] msec);
/* in -- Array of CDF_EPOCH values. */
/* out -- Years (AD, e.g., 1994). */
/* out -- Months (1-12). */
/* out -- Days (1-31). */
/* out -- Hours (0-23). */
/* out -- Minutes (0-59). */
/* out -- Seconds (0-59). */
/* out -- Milliseconds (0-999). */
```

EPOCHbreakdown decomposes a single or an array of CDF_EPOCH values into the individual components.

6.3 toEncodeEPOCH

```
string toEncodeEPOCH(
double epoch);
/* out -- The date/time string (style is 4). */
/* in -- The CDF_EPOCH value. */

string[] toEncodeEPOCH(
double[] epoch);
/* out -- The date/time strings (style is 4). */
/* in -- Array CDF_EPOCH values. */

string toEncodeEPOCH(
double epoch,
int style);
/* out -- The date/time string. */
/* in -- The CDF_EPOCH value. */
/* in -- The encoded style (1-6). */

string[] toEncodeEPOCH(
/* out -- The date/time strings. */
```



```
double[] epoch,          /* in -- Array CDF_EPOCH values. */
int      style);        /* in -- The encoded style (1-4). */
```

toEncodeEPOCH encodes a single or array of CDF_EPOCH values into style 4 date/time character string(s), or the date/time string(s) of designated style. For style: 0, it is the same as calling encodeEPOCH. For style 1, 2, 3 or 4, it is the same as calling encodeEPOCH1, encodeEPOCH2, encodeEPOCH3 and encodeEPOCH4, respectively.

6.4 encodeEPOCH

```
void encodeEPOCH(
double epoch;          /* in -- The CDF_EPOCH value. */
out string epString;  /* out -- The standard date/time string. */
```

```
void encodeEPOCH(
double[] epoch;       /* in -- Array CDF_EPOCH values. */
out string[] epString; /* out -- The standard date/time strings. */
```

encodeEPOCH encodes a single or array of CDF_EPOCH values into the standard date/time character string(s). The format of the string is **dd-mmm-yyyy hh:mm:ss.ccc** where dd is the day of the month (1-31), mmm is the month (Jan, Feb, Mar, Apr, May, Jun, Jul, Aug, Sep, Oct, Nov, or Dec), yyyy is the year, hh is the hour (0-23), mm is the minute (0-59), ss is the second (0-59), and ccc is the millisecond (0-999).

6.5 encodeEPOCH1

```
void encodeEPOCH1(
double epoch;          /* in -- The CDF_EPOCH value. */
out string epString;  /* out -- The alternate date/time string. */
```

encodeEPOCH1 encodes a CDF_EPOCH value into an alternate date/time character string. The format of the string is **yyyymmdd.tttttt**, where yyyy is the year, mm is the month (1-12), dd is the day of the month (1-31), and tttttt is the fraction of the day (e.g., 5000000 is 12 o'clock noon).

6.6 encodeEPOCH2

```
void encodeEPOCH2(
double epoch;          /* in -- The CDF_EPOCH value. */
out string epString;  /* out -- The alternate date/time string. */
```

encodeEPOCH2 encodes a CDF_EPOCH value into an alternate date/time character string. The format of the string is **yyyymmddhhmmss** where yyyy is the year, mo is the month (1-12), dd is the day of the month (1-31), hh is the hour (0-23), mm is the minute (0-59), and ss is the second (0-59).

6.7 encodeEPOCH3

```
void encodeEPOCH3(
double epoch;           /* in -- The CDF_EPOCH value. */
out string epString)   /* out -- The alternate date/time string. */
```

encodeEPOCH3 encodes a CDF_EPOCH value into an alternate date/time character string. The format of the string is yyyy-mo-ddThh:mm:ss.cccZ where yyyy is the year, mo is the month (1-12), dd is the day of the month (1-31), hh is the hour (0-23), mm is the minute (0-59), ss is the second (0-59), and ccc is the millisecond (0-999).

6.8 encodeEPOCH4

```
void encodeEPOCH4(
double epoch;           /* in -- The CDF_EPOCH value. */
out string epString)   /* out -- The ISO 8601 date/time string. */
```

encodeEPOCH3 encodes a CDF_EPOCH value into an alternate, ISO 8601 date/time character string. The format of the string is yyyy-mo-ddThh:mm:ss.ccc where yyyy is the year, mo is the month (1-12), dd is the day of the month (1-31), hh is the hour (0-23), mm is the minute (0-59), ss is the second (0-59), and ccc is the millisecond (0-999).

6.9 encodeEPOCHx

```
void encodeEPOCHx(
double epoch;           /* in -- The CDF_EPOCH value. */
string format;         /* in -- The format string. */
out string encoded);   /* out -- The custom date/time string. */
```

encodeEPOCHx encodes a CDF_EPOCH value into a custom date/time character string. The format of the encoded string is specified by a format string.

The format string consists of EPOCH components, which are encoded, and text that is simply copied to the encoded custom string. Components are enclosed in angle brackets and consist of a component token and an optional width. The syntax of a component is: <token[.width]>. If the optional width contains a leading zero, then the component will be encoded with leading zeroes (rather than leading blanks).

The supported component tokens and their default widths are as follows. . .

Token	Meaning	Default
dom	Day of month (1-31)	<dom.0>
doy	Day of year (001-366)	<doy.03>
month	Month ('Jan', 'Feb', ..., 'Dec')	<month>
mm	Month (1,2,...,12)	<mm.0>
year	Year (4-digit)	<year.04>
yr	Year (2-digit)	<yr.02>
hour	Hour (00-23)	<hour.02>
min	Minute (00-59)	<min.02>
sec	Second (00-59)	<sec.02>

fos	Fraction of second.	<fos.3>
fod	Fraction of day.	<fod.8>

Note that a width of zero indicates that as many digits as necessary should be used to encoded the component. The <month> component is always encoded with three characters. The <fos> and <fod> components are always encoded with leading zeroes.

If a left angle bracket is desired in the encoded string, then simply specify two left angle brackets (<<) in the format string (character stuffing).

For example, the format string used to encode the standard EPOCH date/time character string (see Section 6.3) would be. . .

```
<dom.02>-<month>-<year> <hour>:<min>:<sec>.<fos>
```

6.10 toParseEPOCH

```
double toParseEPOCH(                               /* out -- CDF_EPOCH value returned. */
string epString);                                  /* in -- The standard date/time string. */
```

```
double[] toParseEPOCH(                             /* out -- Array of CDF_EPOCH values */
string[] epString);                                /* in -- The encoded date/time strings. */
```

toParseEPOCH parses a single or an array of string(s) in various, standard date/time forms and returns a CDF_EPOCH value(s). The string can be one of the forms that is produced by the encodeEPOCH, encodeEPOCH1, encodeEPOCH2, encodeEPOCH3 and encodeEPOCH4 methods described earlier in this Section. If an illegal field is detected in the string the value returned will be ILLEGAL_EPOCH_VALUE.

6.11 parseEPOCH

```
double parseEPOCH(                                 /* out -- CDF_EPOCH value returned. */
string epString);                                  /* in -- The standard date/time string. */
```

```
double[] parseEPOCH(                              /* out -- Array of CDF_EPOCH values */
string[] epString);                                /* in -- The standard date/time strings. */
```

parseEPOCH parses a single or an array of standard date/time character string(s) and returns a CDF_EPOCH value(s). The format of the string is that produced by the encodeEPOCH method described in Section 6.3. If an illegal field is detected in the string the value returned will be ILLEGAL_EPOCH_VALUE.

6.12 parseEPOCH1

```
double parseEPOCH1(                               /* out -- CDF_EPOCH value returned. */
string epString);                                  /* in -- The alternate date/time string. */
```



```

int second,
int msec,
int microsec,
int nanosec,
int picosec,
TYPE epoch);

```

```

/* in -- Second (0-59). */
/* in -- Millisecond (0-999). */
/* in -- Microsecond (0-999). */
/* in -- Nanosecond (0-999). */
/* in -- Picosecond (0-999). */
/* out -- CDF_EPOCH16 value returned */
/* TYPE -- double* or "out double[]". */

```

computeEPOCH16 calculates a CDF_EPOCH16 value given the individual components. If an illegal component is detected, the value returned will be ILLEGAL_EPOCH_VALUE.

6.17 EPOCH16breakdown

```

void EPOCH16breakdown(
double[] epoch,
TYPE year,
TYPE month,
TYPE day,
TYPE hour,
TYPE minute,
TYPE second,
TYPE msec,
TYPE microsec,
TYPE nanosec,
TYPE picosec);

```

```

/* in -- The CDF_EPOCH16 value. */
/* out -- Year (AD, e.g., 1994). */
/* out -- Month (1-12). */
/* out -- Day (1-31). */
/* out -- Hour (0-23). */
/* out -- Minute (0-59). */
/* out -- Second (0-59). */
/* out -- Millisecond (0-999). */
/* out -- Microsecond (0-999). */
/* out -- Nanosecond (0-999). */
/* out -- Picosecond (0-999). */
/* TYPE -- int* or "out int". */

```

EPOCH16breakdown decomposes a CDF_EPOCH16 value into the individual components.

6.18 toEncodeEPOCH16

```

string toEncodeEPOCH16(
double[] epoch);

```

```

/* out -- The date/time string (style is 4). */
/* in -- The CDF_EPOCH value. */

```

```

string toEncodeEPOCH16(
double[] epoch,
int style);

```

```

/* out -- The date/time string. */
/* in -- The CDF_EPOCH value. */
/* in -- The encoded style (1-6). */

```

toEncodeEPOCH16 encodes a single of CDF_EPOCH16 epoch, a two-double array, into an ISO8601 date/time character string, as style 4, or the date/time string of the designated style. For style: 0, it is the same as calling encodeEPOCH16. For style 1, 2, 3 or 4, it is the same as calling encodeEPOCH16_1, encodeEPOCH16_2, encodeEPOCH16_3 and encodeEPOCH16_4, respectively.

6.19 encodeEPOCH16

```

void encodeEPOCH16(

```

```
double[] epoch, /* in -- The CDF_EPOCH16 value. */
out string epString); /* out -- The date/time string. */
```

encodeEPOCH16 encodes a CDF_EPOCH16 value into the standard date/time character string. The format of the string is **dd-mmm-yyyy hh:mm:ss.mmm:uuu:nnn:ppp** where dd is the day of the month (1-31), mmm is the month (Jan, Feb, Mar, Apr, May, Jun, Jul, Aug, Sep, Oct, Nov, or Dec), yyyy is the year, hh is the hour (0-23), mm is the minute (0-59), ss is the second (0-59), mmm is the millisecond (0-999), uuu is the microsecond (0-999), nnn is the nanosecond (0-999), and ppp is the picosecond (0-999).

6.20 encodeEPOCH16_1

```
void encodeEPOCH16_1(
double[] epoch, /* in -- The CDF_EPOCH16 value. */
out string epString); /* out -- The date/time string. */
```

encodeEPOCH16_1 encodes a CDF_EPOCH16 value into an alternate date/time character string. The format of the string is **yyyymmdd.tttttttttt**, where yyyy is the year, mm is the month (1-12), dd is the day of the month (1-31), and tttttttttt is the fraction of the day (e.g., 5000000000000000 is 12 o'clock noon).

6.21 encodeEPOCH16_2

```
void encodeEPOCH16_2(
double[] epoch, /* in -- The CDF_EPOCH16 value. */
out string epString); /* out -- The date/time string. */
```

encodeEPOCH16_2 encodes a CDF_EPOCH16 value into an alternate date/time character string. The format of the string is **yyyymmddhhmmss** where yyyy is the year, mm is the month (1-12), dd is the day of the month (1-31), hh is the hour (0-23), mm is the minute (0-59), and ss is the second (0-59).

6.22 encodeEPOCH16_3

```
void encodeEPOCH16_3(
double[] epoch, /* in -- The CDF_EPOCH16 value. */
out string epString); /* out -- The alternate date/time string. */
```

encodeEPOCH16_3 encodes a CDF_EPOCH16 value into an alternate date/time character string. The format of the string is **yyyy-mo-ddThh:mm:ss.mmm:uuu:nnn:pppZ** where yyyy is the year, mo is the month (1-12), dd is the day of the month (1-31), hh is the hour (0-23), mm is the minute (0-59), ss is the second (0-59), mmm is the millisecond (0-999), uuu is the microsecond (0-999), nnn is the nanosecond (0-999), and ppp is the picosecond (0-999).

6.23 encodeEPOCH16_4

```
void encodeEPOCH16_4(  
double[] epoch, /* in -- The CDF_EPOCH16 value. */  
out string epString); /* out -- The alternate date/time string. */
```

encodeEPOCH16_4 encodes a CDF_EPOCH16 value into an alternate, ISO 8601 date/time character string. The format of the string is yyyy-mo-ddThh:mm:ss.mmmuuunnnppp where yyyy is the year, mo is the month (1-12), dd is the day of the month (1-31), hh is the hour (0-23), mm is the minute (0-59), ss is the second (0-59), mmm is the millisecond (0-999), uuu is the microsecond (0-999), nnn is the nanosecond (0-999), and ppp is the picosecond (0-999).

6.24 encodeEPOCH16_x

```
void encodeEPOCH16_x(  
double[] epoch, /* in -- The CDF_EPOCH16 value. */  
string format; /* in -- The format string. */  
out string encoded); /* out -- The date/time string. */
```

encodeEPOCH16_x encodes a CDF_EPOCH16 value into a custom date/time character string. The format of the encoded string is specified by a format string.

The format string consists of EPOCH components, which are encoded, and text that is simply copied to the encoded custom string. Components are enclosed in angle brackets and consist of a component token and an optional width. The syntax of a component is: <token[.width]>. If the optional width contains a leading zero, then the component will be encoded with leading zeroes (rather than leading blanks).

The supported component tokens and their default widths are as follows. . .

<u>Token</u>	<u>Meaning</u>	<u>Default</u>
dom	Day of month (1-31)	<dom.0>
doy	Day of year (001-366)	<doy.03>
month	Month ('Jan', 'Feb', ..., 'Dec')	<month>
mm	Month (1,2,...,12)	<mm.0>
year	Year (4-digit)	<year.04>
yr	Year (2-digit)	<yr.02>
hour	Hour (00-23)	<hour.02>
min	Minute (00-59)	<min.02>
sec	Second (00-59)	<sec.02>
msec	Millisecond (000-999)	<msec.3>
usc	Microsecond (000-999)	<usc.3>
nsc	Nanosecond (000-999)	<nsc.3>
psc	Picosecond (000-999)	<psc.3>
fos	Fraction of second.	<fos.12>
fod	Fraction of day.	<fod.8>

Note that a width of zero indicates that as many digits as necessary should be used to encoded the component. The <month> component is always encoded with three characters. The <fos> and <fod> components are always encoded with leading zeroes.

If a left angle bracket is desired in the encoded string, then simply specify two left angle brackets (<<) in the format string (character stuffing).


```
string epString,  
TYPE epoch);
```

```
/* in -- The date/time string. */  
/* out -- The CDF_EPOCH16 value returned */  
/* TYPE -- double* or "out double[]". */
```

parseEPOCH16_2 parses an alternate date/time character string and returns a CDF_EPOCH16 value. The format of the string is that produced by the encodeEPOCH16_2 function. If an illegal field is detected in the string the value returned will be ILLEGAL_EPOCH_VALUE.

6.29 parseEPOCH16_3

```
double parseEPOCH16_3(  
string epString,  
TYPE epoch);
```

```
/* out -- The status code returned. */  
/* in -- The date/time string. */  
/* out -- The CDF_EPOCH16 value returned */  
/* TYPE -- double* or "out double[]". */
```

parseEPOCH16_3 parses an alternate date/time character string and returns a CDF_EPOCH16 value. The format of the string is that produced by the encodeEPOCH16_3 function. If an illegal field is detected in the string the value returned will be ILLEGAL_EPOCH_VALUE.

6.30 parseEPOCH16_4

```
double parseEPOCH16_4(  
string epString,  
TYPE epoch);
```

```
/* out -- The status code returned. */  
/* in -- The ISO 8601 date/time string. */  
/* out -- The CDF_EPOCH16 value returned */  
/* TYPE -- double* or "out double[]". */
```

parseEPOCH16_4 parses an alternate date/time character string and returns a CDF_EPOCH16 value. The format of the string is that produced by the encodeEPOCH16_3 function. If an illegal field is detected in the string the value returned will be ILLEGAL_EPOCH_VALUE.

6.31 EPOCHtoUnixTime

```
double EPOCHtoUnixTime(  
double epoch);
```

```
/* out -- The converted Unix time. */  
/* in -- The CDF_EPOCH epoch value. */
```

```
double[] EPOCHtoUnixTime(  
double[] epochs);
```

```
/* out -- The converted Unix times. */  
/* in -- The CDF_EPOCH epoch values. */
```

EPOCHtoUnixTime converts a CDF_EPOCH epoch time(s) to a Unix time(s). A CDF_EPOCH epoch, a double, is milliseconds from 0000-01-01T00:00:00.000 while Unix time, also a double, is seconds from 1970-01-01T00:00:00.000. The Unix time can have sub-second, with a time resolution of microseconds, in its fractional part.

6.32 UnixTimetoEPOCH

```
double UnixTimetoEPOCH ( /* out -- The converted CDF_EPOCH epoch value. */
double unixTime); /* in -- The Unix time. */

double[] UnixTimetoEPOCH ( /* out -- The converted CDF_EPOCH epoch values. */
double[] unixTime); /* in -- The Unix times. */
```

UnixTimetoEPOCH converts a Unix time(s) to a CDF_EPOCH epoch time(s). A CDF_EPOCH epoch, a double, is milliseconds from 0000-01-01T00:00:00.000 while Unix time, also a double, is seconds from 1970-01-01T00:00:00.000. The Unix time can have sub-second, with a time resolution of microseconds, in its fractional part. Converting the Unix time to EPOCH will only keep the resolution to milliseconds.

6.33 EPOCH16toUnixTime

```
double EPOCH16toUnixTime( /* out -- The converted Unix time. */
double[] epoch); /* in -- The CDF_EPOCH16 epoch value. */
```

EPOCH16toUnixTime converts a CDF_EPOCH16 epoch time, a two-double array, to a Unix time. A CDF_EPOCH16 epoch, a two-double, is picoseconds from 0000-01-01T00:00:00.000.000.000.000 while Unix time, also a double, is seconds from 1970-01-01T00:00:00.000. The Unix time can have sub-second, with a time resolution of microseconds, in its fractional part. **Note:** As CDF_EPOCH16 has much higher time resolution, sub-microseconds portion of its time might get lost during the conversion.

6.34 UnixTimetoEPOCH16

```
double[] UnixTimetoEPOCH16 ( /* out -- The converted CDF_EPOCH epoch value. */
double unixTime); /* in -- The Unix time. */
```

UnixTimetoEPOCH16 converts a Unix time to a CDF_EPOCH16 epoch time, a two-double array. A CDF_EPOCH16 epoch, a two-double, is picoseconds from 0000-01-01T00:00:00.000.000.000.000 while Unix time, also a double, is seconds from 1970-01-01T00:00:00.000. The Unix time can have sub-second, with a time resolution of microseconds, in its fractional part. Sub-microseconds will be filled with 0's when converting from Unix time to EPOCH16.

7 TT2000 Utility Routines

Several functions exist that compute, decompose, parse, and encode CDF_TIME_TT2000 values. These functions may be called by applications using the CDF_TIME_TT2000 data type and is included in the CDF library. The Concepts chapter in the CDF User's Guide describes TT2000 values. All these APIs are defined as static methods in **CDFAPIs** class. The date/time components for CDF_TIME_TT2000 are **UTC-based**, with leap seconds.

The CDF_TIME_TT2000 data type is used to store time values referenced from **J2000** (2000-01-01T12:00:00.000000000). For CDF, values in CDF_TIME_TT2000 are nanoseconds from J2000 with **leap seconds** included. TT2000 data can cover years between 1707 and 2292.

7.1 computeTT2000

compueTT2000 is a overloaded function.

```
long computeTT2000(
TYPE year,
TYPE month,
TYPE day);
/* out -- CDF_TIME_TT2000 value returned. */
/* in -- Year (AD, e.g., 1994), with no fraction. */
/* in -- Month (1-12), with no fraction. */
/* in -- Day (1-31). */

long computeTT2000(
TYPE year,
TYPE month,
TYPE day,
TYPE hour);
/* out -- CDF_TIME_TT2000 value returned. */
/* in -- Year (AD, e.g., 1994), with no fraction. */
/* in -- Month (1-12), with no fraction. */
/* in -- Day (1-31), with no fraction. */
/* in -- Hour (0-23). */

long computeTT2000(
TYPE year,
TYPE month,
TYPE day,
TYPE hour,
TYPE minute);
/* out -- CDF_TIME_TT2000 value returned. */
/* in -- Year (AD, e.g., 1994), with no fraction. */
/* in -- Month (1-12), with no fraction. */
/* in -- Day (1-31), with no fraction. */
/* in -- Hour (0-23), with no fraction. */
/* in -- Minute (0-59). */

long computeTT2000(
TYPE year,
TYPE month,
TYPE day,
TYPE hour,
TYPE minute,
TYPE second);
/* out -- CDF_TIME_TT2000 value returned. */
/* in -- Year (AD, e.g., 1994), with no fraction. */
/* in -- Month (1-12), with no fraction. */
/* in -- Day (1-31), with no fraction. */
/* in -- Hour (0-23), with no fraction. */
/* in -- Minute (0-59 or 0-60 if leap second). */

long computeTT2000(
TYPE year,
TYPE month,
TYPE day,
TYPE hour);
/* out -- CDF_TIME_TT2000 value returned. */
/* in -- Year (AD, e.g., 1994), with no fraction. */
/* in -- Month (1-12), with no fraction. */
/* in -- Day (1-31), with no fraction. */
/* in -- Hour (0-23), with no fraction. */
```

```
TYPE minute,  
TYPE second,  
TYPE msec);
```

```
/* in -- Minute (0-59), with no fraction. */  
/* in -- Second (0-59 or 0-60), with no fraction. */  
/* in -- Millisecond (0-999). */
```

```
long computeTT2000(  
TYPE year,  
TYPE month,  
TYPE day,  
TYPE hour,  
TYPE minute,  
TYPE second,  
TYPE msec,  
TYPE usec);
```

```
/* out -- CDF_TIME_TT2000 value returned. */  
/* in -- Year (AD, e.g., 1994), with no fraction. */  
/* in -- Month (1-12), with no fraction. */  
/* in -- Day (1-31), with no fraction. */  
/* in -- Hour (0-23), with no fraction. */  
/* in -- Minute (0-59), with no fraction. */  
/* in -- Second (0-59 or 0-60), with no fraction. */  
/* in -- Millisecond (0-999), with no fraction. */  
/* in -- Microsecond (0-999). */
```

```
long computeTT2000(  
TYPE year,  
TYPE month,  
TYPE day,  
TYPE hour,  
TYPE minute,  
TYPE second,  
TYPE msec,  
TYPE usec,  
TYPE nsec);
```

```
/* out -- CDF_TIME_TT2000 value returned. */  
/* in -- Year (AD, e.g., 1994), with no fraction. */  
/* in -- Month (1-12), with no fraction. */  
/* in -- Day (1-31), with no fraction. */  
/* in -- Hour (0-23), with no fraction. */  
/* in -- Minute (0-59), with no fraction. */  
/* in -- Second (0-59 or 0-60), with no fraction. */  
/* in -- Millisecond (0-999), with no fraction. */  
/* in -- Microsecond (0-999), with no fraction. */  
/* in -- Nanosecond (0-999). */
```

Another set of functions (to be added in the future):

```
long[] computeTT2000(  
TYPE [] year,  
TYPE [] month,  
TYPE [] day);
```

```
/* out -- Array of CDF_TIME_TT2000 values. */  
/* in -- Years (AD, e.g., 1994), with no fraction. */  
/* in -- Months (1-12), with no fraction. */  
/* in -- Days (1-31). */
```

```
long[] computeTT2000(  
TYPE [] year,  
TYPE [] month,  
TYPE [] day,  
TYPE [] hour);
```

```
/* out -- Array of CDF_TIME_TT2000 values. */  
/* in -- Years (AD, e.g., 1994), with no fraction. */  
/* in -- Months (1-12), with no fraction. */  
/* in -- Days (1-31), with no fraction. */  
/* in -- Hours (0-23). */
```

```
long[] computeTT2000(  
TYPE [] year,  
TYPE [] month,  
TYPE [] day,  
TYPE [] hour,  
TYPE [] minute);
```

```
/* out -- Array of CDF_TIME_TT2000 values. */  
/* in -- Years (AD, e.g., 1994), with no fraction. */  
/* in -- Months (1-12), with no fraction. */  
/* in -- Days (1-31), with no fraction. */  
/* in -- Hours (0-23), with no fraction. */  
/* in -- Minute (0-59). */
```

```
long[] computeTT2000(  
TYPE [] year,  
TYPE [] month,  
TYPE [] day,  
TYPE [] hour,  
TYPE [] minute,  
TYPE [] second);
```

```
/* out -- Array of CDF_TIME_TT2000 values. */  
/* in -- Years (AD, e.g., 1994), with no fraction. */  
/* in -- Months (1-12), with no fraction. */  
/* in -- Days (1-31), with no fraction. */  
/* in -- Hours (0-23), with no fraction. */  
/* in -- Minutes (0-59), with no fraction. */  
/* in -- Seconds (0-59 or 0-60 if leap second). */
```

```
long[] computeTT2000(  
TYPE [] year,  
TYPE [] month,
```

```
/* out -- Array of CDF_TIME_TT2000 values. */  
/* in -- Years (AD, e.g., 1994), with no fraction. */  
/* in -- Months (1-12), with no fraction. */
```

```

TYPE [] day, /* in -- Days (1-31), with no fraction. */
TYPE [] hour, /* in -- Hours (0-23), with no fraction. */
TYPE [] minute, /* in -- Minutes (0-59), with no fraction. */
TYPE [] second, /* in -- Seconds (0-59 or 0-60) with no fraction. */
TYPE [] msec); /* in -- Milliseconds (0-999). */

long[] computeTT2000( /* out -- Array of CDF_TIME_TT2000 values. */
TYPE [] year, /* in -- Years (AD, e.g., 1994), with no fraction. */
TYPE [] month, /* in -- Months (1-12), with no fraction. */
TYPE [] day, /* in -- Days (1-31), with no fraction. */
TYPE [] hour, /* in -- Hours (0-23), with no fraction. */
TYPE [] minute, /* in -- Minutes (0-59), with no fraction. */
TYPE [] second, /* in -- Seconds (0-59 or 0-60), with no fraction. */
TYPE [] msec, /* in -- Milliseconds (0-999), with no fraction. */
TYPE [] usec); /* in -- Microseconds (0-999). */

long[] computeTT2000( /* out -- Array of CDF_TIME_TT2000 values. */
TYPE [] year, /* in -- Years (AD, e.g., 1994), with no fraction. */
TYPE [] month, /* in -- Months (1-12), with no fraction. */
TYPE [] day, /* in -- Days (1-31), with no fraction. */
TYPE [] hour, /* in -- Hours (0-23), with no fraction. */
TYPE [] minute, /* in -- Minutes (0-59), with no fraction. */
TYPE [] second, /* in -- Seconds (0-59 or 0-60). with no fraction. */
TYPE [] msec, /* in -- Milliseconds (0-999), with no fraction. */
TYPE [] usec, /* in -- Microseconds (0-999), with no fraction. */
TYPE [] nsec); /* in -- Nanoseconds (0-999), with no fraction. */

```

Note: TYPE can be either double or long.

computeTT2000 calculates a single or an array of CDF_TIME_TT2000 value(s), from the given individual components. If an illegal component is detected, the value returned will be ILLEGAL_TT2000_VALUE. The day component can be either in day of the month or day of the year (DOY). For DOY form, the month component must have a value(s) of one (1).

NOTE: Even though this overloaded function uses double for all its parameter fields, all but the very last parameter can not have a non-zero fractional part for simplifying the computation. An exception will be thrown if the rule is not followed. For example, this call is allowed:

```
long tt2000 = computeTT2000(2010.0, 10.0, 10.5);
```

But, this call will fail:

```
long tt2000 = computeTT2000(2010.0, 10.0, 10.5, 12.5);
```

7.2 TT2000breakdown

```

void TT2000breakdown(
long tt2000, /* in -- The CDF_TIME_TT2000 value. */
TYPE year, /* out -- Year (AD, e.g., 1994). */
TYPE month, /* out -- Month (1-12). */
TYPE day, /* out -- Day (1-31). */

```

```

TYPE hour,
TYPE minute,
TYPE second,
TYPE msec;
TYPE usec;
TYPE nsec);

```

```

/* out -- Hour (0-23). */
/* out -- Minute (0-59). */
/* out -- Second (0-59 or 0-60 if leap second). */
/* out -- Millisecond (0-999). */
/* out -- Microsecond (0-999). */
/* out -- Nanosecond (0-999). */
/* TYPE -- double* or "out double" or
long* or "out long" */

```

Another function will be added in the future:

```

void TT2000breakdown(
long[] tt2000,
out double[] year,
out double[] month,
out double[] day,
out double[] hour,
out double[] minute,
out double[] second,
out double[] msec;
out double[] usec;
out double[] nsec);

```

```

/* in -- Array of CDF_TIME_TT2000 values. */
/* out -- Years (AD, e.g., 1994). */
/* out -- Months (1-12). */
/* out -- Days (1-31). */
/* out -- Hours (0-23). */
/* out -- Minutes (0-59). */
/* out -- Seconds (0-59 or 0-60 if leap second). */
/* out -- Milliseconds (0-999). */
/* out -- Microseconds (0-999). */
/* out -- Nanoseconds (0-999). */

```

TT2000breakdown decomposes a single or an array of CDF_TIME_TT2000 value(s) into the individual components.

7.3 toEncodeTT2000

toEncodeTT2000 is a overloaded function.

```

string toEncodeTT2000(
long tt2000);

```

```

/* out -- Encoded style 3 date/time string. */
/* in -- The CDF_TIME_TT2000 value. */

```

```

string toEncodeTT2000(
long tt2000;
int style);

```

```

/* out -- Encoded date/time string. */
/* in -- A TT2000 value. */
/* in -- The encoded string style. */

```

```

string[] toEncodeTT2000(
long[] tt2000);

```

```

/* out -- Encoded style 3 date/time strings. */
/* in -- The CDF_TIME_TT2000 value. */

```

```

string[] toEncodeTT2000(
long[] tt2000;
int style);

```

```

/* out -- Encoded date/time strings. */
/* in -- Array of TT2000 values. */
/* in -- The encoded string style. */

```

toEncodeTT2000 encodes a single or an array of CDF_TIME_TT2000 value(s) into various date/time UTC character string(s). If style is not provided, the default style is 3, which is in **ISO 8601** format: **yyyy-mm-ddT hh:mm:ss.mmmuuunnn** where yyyy is the year (1707-2292), mm is the month (01-12), dd is the day of the month (1-31), hh is the hour (0-23), mm is the minute (0-59), ss is the second (0-59 or 0-60 if leap second), mmm is the millisecond (0-999), uuu is the microsecond (0-999) and nnn is the nanosecond (0-999). The valid style is from 0 to 4.

For a style of value **0**, the encoded UTC string is **DD-Mon-YYYY hh:mm:ss.mmmuuunnn**, where DD is the day of the month (1-31), Mon is the month (Jan, Feb, Mar, Apr, May, Jun, Jul, Aug, Sep, Oct, Nov, or Dec), YYYY is the year, hh is the hour (0-23), mm is the minute (0-59 or 0-60 if leap second), ss is the second (0-59), mmm is the millisecond (0-999), uuu is the microsecond (0-999), and nnn is the nanosecond (0-999). The encoded string has a length of TT2000_0_STRING_LEN (**30**).

For a style of value **1**, the encoded UTC string is **YYYYMMDD.tttttttt**, where YYYY is the year, MM is the month (1-12) DD is the day of the month (1-31), and tttttttt is sub-day.(0-999999999). The encoded string has a length of TT2000_1_STRING_LEN (**19**).

For a style of value **2**, the encoded UTC string is **YYYYMMDDhhmmss**, where YYYY is the year, MM is the month (1-12) DD is the day of the month (1-31), hh is the hour (0-23), mm is the minute (0-59), and ss is the second (0-59 or 0-60 if leap second). The encoded string has a length of TT2000_2_STRING_LEN (**14**).

For a style of value **3**, the encoded UTC string is **ISO8601** form as **YYYY-MM-DDThh:mm:ss.mmmuuunnn**, where YYYY is the year, MM is the month (1-12), DD is the day of the month (1-31), hh is the hour (0-23), mm is the minute (0-59 or 0-60 if leap second), ss is the second (0-59), mmm is the millisecond (0-999), uuu is the microsecond (0-999), and nnn is the nanosecond (0-999). The encoded string has a length of TT2000_3_STRING_LEN (**29**).

For a style of value **4**, the encoded UTC string is the same as style 3, but with an extra “**Z**” appended to the end. The encoded string has a length of TT2000_4_STRING_LEN (**30**).

7.4 encodeTT2000

encodeTT2000 is a overloaded function.

```
void encodeTT2000(
long tt2000;                               /* in -- The CDF_TIME_TT2000 value. */
out string epString);                     /* out -- The standard date/time string. */

void encodeTT2000(
long[] tt2000;                              /* in -- Array of TT2000 values. */
out string[] epString);                   /* out -- The standard date/time strings. */

void encodeTT2000(
long tt2000;                               /* in -- The CDF_TIME_TT2000 value. */
out string epString.                       /* out -- The standard date/time string. */
int format);                              /* in -- The encoded string format. */

void encodeTT2000(
long[] tt2000;                              /* in -- Array of TT2000 values. */
out string[] epString.                     /* out -- The standard date/time strings. */
int format);                              /* in -- The encoded string format. */
```

encodeTT2000 encodes a single or an array of CDF_TIME_TT2000 value(s) into the standard date/time UTC character string(s). If not provided, the default format of the string is in **ISO 8601** format: **yyyy-mm-ddT hh:mm:ss.mmmuuunnn** where yyyy is the year (1707-2292), mm is the month (01-12), dd is the day of the month (1-31), hh is the hour (0-23), mm is the minute (0-59), ss is the second (0-59 or 0-60 if leap second), mmm is the millisecond (0-999), uuu is the microsecond (0-999) and nnn is the nanosecond (0-999).

For a format of value **0**, the encoded UTC string is **DD-Mon-YYYY hh:mm:ss.mmmuuunnn**, where DD is the day of the month (1-31), Mon is the month (Jan, Feb, Mar, Apr, May, Jun, Jul, Aug, Sep, Oct, Nov, or Dec), YYYY is the year, hh is the hour (0-23), mm is the minute (0-59 or 0-60 if leap second), ss is the second (0-59), mmm is the millisecond (0-999), uuu is the microsecond (0-999), and nnn is the nanosecond (0-999). The encoded string has a length of TT2000_0_STRING_LEN (**30**).

For a format of value **1**, the encoded UTC string is **YYYYMMDD.tttttttt**, where YYYY is the year, MM is the month (1-12) DD is the day of the month (1-31), and tttttttt is sub-day.(0-999999999). The encoded string has a length of TT2000_1_STRING_LEN (**19**).

For a format of value **2**, the encoded UTC string is **YYYYMMDDhhmmss**, where YYYY is the year, MM is the month (1-12) DD is the day of the month (1-31), hh is the hour (0-23), mm is the minute (0-59),and ss is the second (0-59 or 0-60 if leap second). The encoded string has a length of TT2000_2_STRING_LEN (**14**).

For a format of value **3**, the encoded UTC string is **YYYY-MM-DDThh:mm:ss.mmmuuunnn**, where YYYY is the year, MM is the month (1-12), DD is the day of the month (1-31), hh is the hour (0-23), mm is the minute (0-59 or 0-60 if leap second), ss is the second (0-59), mmm is the millisecond (0-999), uuu is the microsecond (0-999), and nnn is the nanosecond (0-999). The encoded string has a length of TT2000_3_STRING_LEN (**29**).

7.5 toParseTT2000

```
long toParseTT2000(                                     /* out -- CDF_TIME_TT2000 value returned. */
string epString);                                       /* in -- The encoded date/time string. */
```

```
long[] toParseTT2000(                                    /* out -- Array of TT2000 values. */
string[] epString);                                     /* in -- The encoded date/time strings. */
```

toParseTT2000 parses a single or an array of encoded date/time character string(s) and returns a CDF_TIME_TT2000 value(s). The format of the string is that produced by the toEncodeTT2000 or encodeTT2000 method described in Section 7.3 and 7.4. If an illegal field is detected in the string the value returned will be ILLEGAL_TT2000_VALUE.

7.6 ParseTT2000

```
long parseTT2000(                                       /* out -- CDF_TIME_TT2000 value returned. */
string epString);                                       /* in -- The standard date/time string. */
```

```
long[] parseTT2000(                                     /* out -- Array of TT2000 values. */
string[] epString);                                     /* in -- The standard date/time strings. */
```

parseTT2000 parses a single or an array of standard date/time character string(s) and returns a CDF_TIME_TT2000 value(s). The format of the string is that produced by the toEncodeTT2000 or encodeTT2000 method described in Section 6.3. If an illegal field is detected in the string the value returned will be ILLEGAL_TT2000_VALUE.

7.7 TT2000toUnixTime

```
double TT2000toUnixTime(                /* out -- The converted Unix time. */
long epoch);                            /* in -- The CDF_TIME_TT2000 epoch value. */

double[] TT2000toUnixTime(              /* out -- The converted Unix times. */
long[] epochs);                          /* in -- The CDF_TIME_TT2000 epoch values. */
```

TT2000toUnixTime converts CDF_TIME_TT2000 epoch time(s) to Unix time(s). A CDF_TIME_TT2000 epoch, a long, is nanoseconds from J2000 with leap seconds, while Unix time, also a double, is seconds from 1970-01-01T00:00:00.000. The Unix time can have sub-second, with a time resolution of microseconds, in its fractional part. **Note:** As CDF_TIME_TT2000 has much higher time resolution, sub-microseconds portion of its time might get lost during the conversion. Also, TT2000's leap seconds will get lost after the conversion.

7.8 UnixTimetoTT2000

```
long UnixTimetoTT2000 (                  /* out -- The converted TT2000 epoch value. */
double unixTime);                        /* in -- The Unix time. */

long[] UnixTimetoTT2000 (                /* out -- The converted TT2000 epoch values. */
double[] unixTime);                      /* in -- The Unix times. */
```

UnixTimetoTT2000 converts Unix time(s) to CDF_TIME_TT2000 epoch time(s). A CDF_TIME_TT2000 epoch, a long, is nanoseconds from J2000 with leap seconds, while Unix time, also a double, is seconds from 1970-01-01T00:00:00.000. The Unix time can have sub-second, with a time resolution of microseconds, in its fractional part. Sub-microseconds will be filled with 0's when converting from Unix time to TT2000.

7.9 CDFgetLastDateinLeapSecondsTable

```
void CDFgetLastDateinLeapSecondsTable(  /
out int year;                            /* out -- The year. */
out int month;                            /* out -- The month. */
out int day);                             /* out -- The day. */
```

CDFgetLastDateinLeapSecondsTable returns the last entry in the leap second table used by the CDF processing. This date comes from the leap second table, either through an external text file, or the hard-coded table in the library code. This information can tell whether the leap second table is up-to-date.

8 CDF Utility Methods

Several methods are created that are mainly used to decipher the strings and their corresponding constant values or vice versa. All these APIs are defined as static methods in **CDFUtils** class. The constant values are defined in **CDFConstants** class.

8.1 CDFFileExists

```
bool CDFFileExists(                                     /* out -- The file existence flag. */  
string fileName)                                       /* in -- The file name. */
```

CDFFileExists method checks whether a CDF file by the given file name, with or without the .cdf extension, exists. Even the file exists, CDFFileExists will not be able to verify whether it is a valid one. (Use CDFopen to validate it).

8.2 CDFgetChecksumValue

```
int CDFgetChecksumValue(                               /* out -- The checksum value. */  
string checksum)                                       /* in -- The file checksum type string. */
```

CDFgetChecksumValue method returns the corresponding file checksum type value, based on the passed string. The file checksum types and their values are as follows:

<u>Type</u>	<u>Value</u>
NONE	NO_CHECKSUM (0)
MD5	MD5_CHECKSUM (1)
OTHER	OTHER_CHECKSUM

8.3 CDFgetCompressionTypeValue

```
int CDFgetCompressionTypeValue(                       /* out -- The compression type. */  
string compressionType)                               /* in -- The compression type string. */
```

CDFgetCompressionTypeValue method returns the corresponding compression type value, based on the passed string. The compression types and values are as follows:

<u>Type</u>	<u>Value</u>
NONE	NO_COMPRESSION (0)

RLE	RLE_COMPRESSION (1)
Huffman	HUFF_COMPRESSION (2)
Adaptive Huffman	AHUFF_COMPRESSION (3)
GZIP	GZIP_COMPRESSION (5)

8.4 CDFgetDataTypeValue

```
int CDFgetDataTypeValue(                                     /* out -- The data type. */
string dataType)                                           /* in -- The data type string. */
```

CDFgetDataTypeValue method returns the corresponding data type value, based on the passed string. The data types and their values are as follows:

<u>Type</u>	<u>Value</u>
CDF_BYTE	CDF_BYTE (41)
CDF_CHAR	CDF_CHAR (51)
CDF_UCHAR	CDF_UCHAR (52)
CDF_INT1	CDF_INT1 (1)
CDF_UINT1	CDF_UINT1 (11)
CDF_INT2	CDF_INT2 (2)
CDF_UINT2	CDF_UINT2 (12)
CDF_INT4	CDF_INT4 (4)
CDF_UINT4	CDF_UINT4 (14)
CDF_INT8	CDF_INT8 (8)
CDF_REAL4	CDF_REAL4 (21)
CDF_FLOAT	CDF_FLOAT (44)
CDF_REAL8	CDF_REAL8 (22)
CDF_DOUBLE	CDF_DOUBLE (45)
CDF_EPOCH	CDF_EPOCH (31)
CDF_EPOCH16	CDF_EPOCH16 (32)
CDF_TIME_TT2000	CDF_TIME_TT2000 (33)

8.5 CDFgetDecodingValue

```
int CDFgetDecodingValue(                                   /* out -- The decoding value. */
string decoding)                                          /* in -- The data decoding string. */
```

CDFgetDecodingValue method returns the corresponding data decoding value, based on the passed string. The data decodings and their values are as follows:

<u>Type</u>	<u>Value</u>
NETWORK	NETWORK_DECODING (1)
SUN	SUN_DECODING (2)
VAX	VAX_DECODING (3)
DECSTATION	DECSTATION_DECODING (4)
SGi	SGi_DECODING (5)
IBMPC	IBMPC_DECODING (6)
IBMRS	IBMRS_DECODING (7)

HOST	HOST_DECODING (8)
PPC	PPC_DECODING (9)
HP	HP_DECODING (11)
NeXT	NeXT_DECODING (12)
ALPHAOSF1	ALPHAOSF1_DECODING (13)
ALPHAVMSd	ALPHAVMSd_DECODING (14)
ALPHAVMSg	ALPHAVMSg_DECODING (15)
ALPHAVMSi	ALPHAVMSi_DECODING (16)

8.6 CDFgetEncodingValue

```
int CDFgetEncodingValue(                                     /* out -- The encoding value. */
string encoding)                                           /* in  -- The data encoding string. */
```

CDFgetEncodingValue method returns the corresponding data encoding value, based on the passed string. The data encodings and their values are as follows:

<u>Type</u>	<u>Value</u>
NETWORK	NETWORK_ENCODING (1)
SUN	SUN_ENCODING (2)
VAX	VAX_ENCODING (3)
DECSTATION	DECSTATION_ENCODING (4)
SGi	SGi_ENCODING (5)
IBMPc	IBMPc_ENCODING (6)
IBMRS	IBMRS_ENCODING (7)
HOST	HOST_ENCODING (8)
PPC	PPC_ENCODING (9)
HP	HP_ENCODING (11)
NeXT	NeXT_ENCODING (12)
ALPHAOSF1	ALPHAOSF1_ENCODING (13)
ALPHAVMSd	ALPHAVMSd_ENCODING (14)
ALPHAVMSg	ALPHAVMSg_ENCODING (15)
ALPHAVMSi	ALPHAVMSi_ENCODING (16)

8.7 CDFgetFormatValue

```
int CDFgetFormatValue(                                     /* out -- The format value. */
string format)                                           /* in  -- The file format string. */
```

CDFgetFormatValue method returns the corresponding file format value, based on the passed string. The file formats and their values are as follows:

<u>Type</u>	<u>Value</u>
SINGLE	SINGLE_FILE (1)
MULTI	MULTI_FILE (2)

8.8 CDFgetMajorityValue

```
int CDFgetMajorityValue( /* out -- The majority value. */
string majority) /* in -- The data majority string. */
```

CDFgetMajorityValue method returns the corresponding file majority value, based on the passed string. The file majorities and their values are as follows:

<u>Type</u>	<u>Value</u>
ROW	ROW_MAJOR (1)
COLUMN	COLUMN_MAJOR (2)

8.9 CDFgetSparseRecordValue

```
int CDFgetSparseRecordValue( /* out -- The sparse record value. */
string sparseRecord) /* in -- The sparse record string. */
```

CDFgetSparseRecordValue method returns the corresponding sparse record value, based on the passed string. The sparse records types and their values are as follows:

<u>Type</u>	<u>Value</u>
NONE	NO_SPARSERECORDS (0)
PAD	PAD_SPARSERECORDS (1)
PREV	PREV_SPARSERECORDS (2)

8.10 CDFgetStringChecksum

```
string CDFgetStringChecksum( /* out -- The checksum string. */
int checksum) /* in -- The file checksum type. */
```

CDFgetStringChecksum method returns the corresponding file checksum string, based on the passed type. The file checksum types and their values are the same as those defined in CDFgetChecksumValue method.

8.11 CDFgetStringCompressionType

```
string CDFgetStringCompressionType( /* out -- The compression string. */
int compressionType) /* in -- The compression type. */
```

CDFgetStringCompressionType method returns the corresponding compression type string, based on the passed type. The file checksum types and their values are the same as those defined in CDFgetCompressionTypeValue method.

8.12 CDFgetStringDataType

```
string CDFgetStringDataType(                                     /* out -- The data type string. */  
int dataType)                                                 /* in -- The data type. */
```

CDFgetStringDataType method returns the corresponding data type string, based on the passed type. The data types and their values are the same as those in CDFgetDataTypeValue method:

8.13 CDFgetStringDecoding

```
string CDFgetStringDecoding(                                    /* out -- The decoding string. */  
in decoding)                                                 /* in -- The data decoding type. */
```

CDFgetStringDecoding method returns the corresponding data decoding string, based on the passed type. The data decodings and their values are as same as those defined in CDFgetDecodingValue:

8.14 CDFgetStringEncoding

```
string CDFgetStringEncoding(                                   /* out -- The encoding string. */  
int encoding)                                                 /* in -- The data encoding type. */
```

CDFgetStringEncoding method returns the corresponding data encoding string, based on the passed type. The data encodings and their values are the same as those defined in CDFgetEncodingValue method.

8.15 CDFgetStringFormat

```
string CDFgetStringFormat(                                    /* out -- The format string. */  
int format)                                                  /* in -- The file format type. */
```

CDFgetStringFormat method returns the corresponding file format string, based on the passed type. The file formats and their values are the same as those defined in CDFgetFormatValue method.:

8.16 CDFgetStringMajority

```
string CDFgetStringMajority(                                   /* out -- The majority string. */  
int majority)                                                /* in -- The data majority type. */
```

CDFgetStringMajority method returns the corresponding file majority string, based on the passed type. The file majorities and their values are the same as those defined in CDFgetMajorityValue method.

8.17 CDFgetStringSparseRecord

```
string CDFgetStringSparseRecord(          /* out -- The sparse record string. */  
int sparseRecord)                       /* in  -- The sparse record type.  */
```

CDFgetStringSparseRecord method returns the corresponding sparse record string, based on the passed type. The sparse records types and their values are the same as those defined in CDFgetSparseRecordValue method.:

9 CDF Exception Methods

Several methods in the `CDFException` class can be used to check what happens when an exception is thrown by the CDF APIs, and react to it if necessary. All these APIs are defined as static methods. `CDFException` inherits from C#'s `Exception` class.

9.1 CDFgetCurrentStatus

```
int CDFgetCurrentStatus() /* out -- The status. */
```

`CDFgetCurrentStatus` method returns the status when an exception is detected. The status value should be a negative value. Chapter 5 covers all possible status codes. Use the following `CDFgetStatusMsg` method to decipher what the status means.

9.2 CDFgetStatusMsg

```
string CDFgetStatusMsg(/* out -- The descriptive message. */  
int status) /* in -- The exception status. */
```

`CDFgetStatusMsg` method returns the descriptive information of the passed status.

Appendix A

A.1 Introduction

A status code is returned from most CDF functions. The CDFConstants class contains the numerical values (constants) for each of the status codes (and for any other constants referred to in the explanations). The method CDFError can be used within a program to inquire the explanation text for a given status code.

There are three classes of status codes: informational, warning, and error. The purpose of each is as follows:

Informational	Indicates success but provides some additional information that may be of interest to an application.
Warning	Indicates that the method completed but possibly not as expected.
Error	Indicates that a fatal error occurred and the function aborted.

Status codes fall into classes as follows:

Error codes < CDF_WARN < Warning codes < CDF_OK < Informational codes

CDF_OK indicates an unqualified success (it should be the most commonly returned status code). CDF_WARN is simply used to distinguish between warning and error status codes.

A.2 Status Codes and Messages

The following list contains an explanation for each possible status code. Whether a particular status code is considered informational, a warning, or an error is also indicated.

ATTR_EXISTS	Named attribute already exists - cannot create or rename. Each attribute in a CDF must have a unique name. Note that trailing blanks are ignored by the CDF library when comparing attribute names. [Error]
ATTR_NAME_TRUNC	Attribute name truncated to CDF_ATTR_NAME_LEN256 characters. The attribute was created but with a truncated name. [Warning]
BAD_ALLOCATE_RECS	An illegal number of records to allocate for a variable was specified. For RV variables the number must be one or greater. For NRV variables the number must be exactly one. [Error]
BAD_ARGUMENT	An illegal/undefined argument was passed. Check that all arguments are properly declared and initialized. [Error]

BAD_ATTR_NAME	Illegal attribute name specified. Attribute names must contain at least one character, and each character must be printable. [Error]
BAD_ATTR_NUM	Illegal attribute number specified. Attribute numbers must be zero (0) or greater for C applications and one (1) or greater for Fortran applications. [Error]
BAD_BLOCKING_FACTOR ²⁶	An illegal blocking factor was specified. Blocking factors must be at least zero (0). [Error]
BAD_CACHESIZE	An illegal number of cache buffers was specified. The value must be at least zero (0). [Error]
BAD_CDF_EXTENSION	An illegal file extension was specified for a CDF. In general, do not specify an extension except possibly for a single-file CDF that has been renamed with a different file extension or no file extension. [Error]
BAD_CDF_ID	CDF identifier is unknown or invalid. The CDF identifier specified is not for a currently open CDF. [Error]
BAD_CDF_NAME	Illegal CDF name specified. CDF names must contain at least one character, and each character must be printable. Trailing blanks are allowed but will be ignored. [Error]
BAD_INT	Unknown CDF status code received. The CDF library does not use the status code specified. [Error]
BAD_CHECKSUM	An illegal checksum mode received. It is invalid or currently not supported. [Error]
BAD_COMPRESSION_PARM	An illegal compression parameter was specified. [Error]
BAD_DATA_TYPE	An unknown data type was specified or encountered. The CDF data types are defined in CDFConstants class for C# applications. [Error]
BAD_DECODING	An unknown decoding was specified. The CDF decodings are defined in CDFConstants class for C# applications. [Error]
BAD_DIM_COUNT	Illegal dimension count specified. A dimension count must be at least one (1) and not greater than the size of the dimension. [Error]
BAD_DIM_INDEX	One or more dimension index is out of range. A valid value must be specified regardless of the dimension variance. Note also that the combination of dimension index, count, and interval must not specify an element beyond the end of the dimension. [Error]
BAD_DIM_INTERVAL	Illegal dimension interval specified. Dimension intervals must be at least one (1). [Error]
BAD_DIM_SIZE	Illegal dimension size specified. A dimension size must be at least one (1). [Error]

²⁶ The status code BAD_BLOCKING_FACTOR was previously named BAD_EXTEND_RECS.

BAD_ENCODING	Unknown data encoding specified. The CDF encodings are defined in CDFConstants class for C# applications. [Error]
BAD_ENTRY_NUM	Illegal attribute entry number specified. Entry numbers must be at least zero (0) for C# applications. [Error]
BAD_FNC_OR_ITEM	The specified function or item is illegal. Check that the proper number of arguments are specified for each operation being performed. [Error]
BAD_FORMAT	Unknown format specified. The CDF formats are defined in CDFConstants class for C# applications. [Error]
BAD_INITIAL_RECS	An illegal number of records to initially write has been specified. The number of initial records must be at least one (1). [Error]
BAD_MAJORITY	Unknown variable majority specified. The CDF variable majorities are defined in CDFConstants class for C# applications. [Error]
BAD_MALLOC	Unable to allocate dynamic memory - system limit reached. Contact CDF User Support if this error occurs. [Error]
BAD_NEGtoPOSfp0_MODE	An illegal -0.0 to 0.0 mode was specified. The -0.0 to 0.0 modes are defined in CDFConstants class for C# applications. [Error]
BAD_NUM_DIMS	The number of dimensions specified is out of the allowed range. Zero (0) through CDF_MAX_DIMS dimensions are allowed. If more are needed, contact CDF User Support. [Error]
BAD_NUM_ELEMS	The number of elements of the data type is illegal. The number of elements must be at least one (1). For variables with a non-character data type, the number of elements must always be one (1). [Error]
BAD_NUM_VARS	Illegal number of variables in a record access operation. [Error]
BAD_READONLY_MODE	Illegal read-only mode specified. The CDF read-only modes are defined in CDFConstants class for C# applications. [Error]
BAD_REC_COUNT	Illegal record count specified. A record count must be at least one (1). [Error]
BAD_REC_INTERVAL	Illegal record interval specified. A record interval must be at least one (1). [Error]
BAD_REC_NUM	Record number is out of range. Record numbers must be at least zero (0) for C applications and at least one (1) for Fortran applications. Note that a valid value must be specified regardless of the record variance. [Error]
BAD_SCOPE	Unknown attribute scope specified. The attribute scopes are defined in CDFConstants class for C# applications. [Error]

BAD_SCRATCH_DIR	An illegal scratch directory was specified. The scratch directory must be writeable and accessible (if a relative path was specified) from the directory in which the application has been executed. [Error]
BAD_SPARSEARRAYS_PARM	An illegal sparse arrays parameter was specified. [Error]
BAD_VAR_NAME	Illegal variable name specified. Variable names must contain at least one character and each character must be printable. [Error]
BAD_VAR_NUM	Illegal variable number specified. Variable numbers must be zero (0) or greater for C# applications. [Error]
BAD_zMODE	Illegal zMode specified. The CDF zModes are defined in CDFConstants class for C# applications. [Error]
CANNOT_ALLOCATE_RECORDS	Records cannot be allocated for the given type of variable (e.g., a compressed variable). [Error]
CANNOT_CHANGE	<p>Because of dependencies on the value, it cannot be changed. Some possible causes of this error follow:</p> <ol style="list-style-type: none"> 1. Changing a CDF's data encoding after a variable value (including a pad value) or an attribute entry has been written. 2. Changing a CDF's format after a variable has been created or if a compressed single-file CDF. 3. Changing a CDF's variable majority after a variable value (excluding a pad value) has been written. 4. Changing a variable's data specification after a value (including the pad value) has been written to that variable or after records have been allocated for that variable. 5. Changing a variable's record variance after a value (excluding the pad value) has been written to that variable or after records have been allocated for that variable. 6. Changing a variable's dimension variances after a value (excluding the pad value) has been written to that variable or after records have been allocated for that variable. 7. Writing "initial" records to a variable after a value (excluding the pad value) has already been written to that variable. 8. Changing a variable's blocking factor when a compressed variable and a value (excluding the pad value) has been written or when a variable with sparse records and a value has been accessed. 9. Changing an attribute entry's data specification where the new specification is not equivalent to the old specification.

CANNOT_COMPRESS	The CDF or variable cannot be compressed. For CDFs, this occurs if the CDF has the multi-file format. For variables, this occurs if the variable is in a multi-file CDF, values have been written to the variable, or if sparse arrays have already been specified for the variable. [Error]
CANNOT_SPARSEARRAYS	Sparse arrays cannot be specified for the variable. This occurs if the variable is in a multi-file CDF, values have been written to the variable, records have been allocated for the variable, or if compression has already been specified for the variable. [Error]
CANNOT_SPARSERECORDS	Sparse records cannot be specified for the variable. This occurs if the variable is in a multi-file CDF, values have been written to the variable, or records have been allocated for the variable. [Error]
CDF_CLOSE_ERROR	Error detected while trying to close CDF. Check that sufficient disk space exists for the dotCDF file and that it has not been corrupted. [Error]
CDF_CREATE_ERROR	Cannot create the CDF specified - error from file system. Make sure that sufficient privilege exists to create the dotCDF file in the disk/directory location specified and that an open file quota has not already been reached. [Error]
CDF_DELETE_ERROR	Cannot delete the CDF specified - error from file system. Insufficient privileges exist to delete the CDF file(s). [Error]
CDF_EXISTS	The CDF named already exists - cannot create it. The CDF library will not overwrite an existing CDF. [Error]
CDF_INTERNAL_ERROR	An unexpected condition has occurred in the CDF library. Report this error to CDFsupport. [Error]
CDF_NAME_TRUNC	CDF file name truncated to CDF_PATHNAME_LEN characters. The CDF was created but with a truncated name. [Warning]
CDF_OK	Function completed successfully.
CDF_OPEN_ERROR	Cannot open the CDF specified - error from file system. Check that the dotCDF file is not corrupted and that sufficient privilege exists to open it. Also check that an open file quota has not already been reached. [Error]
CDF_READ_ERROR	Failed to read the CDF file - error from file system. Check that the dotCDF file is not corrupted. [Error]
CDF_WRITE_ERROR	Failed to write the CDF file - error from file system. Check that the dotCDF file is not corrupted. [Error]
CHECKSUM_ERROR	The data integrity verification through the checksum failed. [Error]
CHECKSUM_NOT_ALLOWED	The checksum is not allowed for old versioned files. [Error]

COMPRESSION_ERROR	An error occurred while compressing a CDF or block of variable records. This is an internal error in the CDF library. Contact CDF User Support. [Error]
CORRUPTED_V2_CDF	This Version 2 CDF is corrupted. An error has been detected in the CDF's control information. If the CDF file(s) are known to be valid, please contact CDF User Support. [Error]
DECOMPRESSION_ERROR	An error occurred while decompressing a CDF or block of variable records. The most likely cause is a corrupted dotCDF file. [Error]
DID_NOT_COMPRESS	For a compressed variable, a block of records did not compress to smaller than their uncompressed size. They have been stored uncompressed. This can result if the blocking factor is set too low or if the characteristics of the data are such that the compression algorithm chosen is unsuitable. [Informational]
EMPTY_COMPRESSED_CDF	The compressed CDF being opened is empty. This will result if a program, which was creating/modifying, the CDF abnormally terminated. [Error]
END_OF_VAR	The sequential access current value is at the end of the variable. Reading beyond the end of the last physical value for a variable is not allowed (when performing sequential access). [Error]
FORCED_PARAMETER	A specified parameter was forced to an acceptable value (rather than an error being returned). [Warning]
IBM_PC_OVERFLOW	An operation involving a buffer greater than 64k bytes in size has been specified for PCs running 16-bit DOS/Windows 3.*. [Error]
ILLEGAL_EPOCH_VALUE	Illegal component is detected in computing an epoch value or an illegal epoch value is provided in decomposing an epoch value. [Error]
ILLEGAL_FOR_SCOPE	The operation is illegal for the attribute's scope. For example, only gEntries may be written for gAttributes - not rEntries or zEntries. [Error]
ILLEGAL_IN_zMODE	The attempted operation is illegal while in zMode. Most operations involving rVariables or rEntries will be illegal. [Error]
ILLEGAL_ON_V1_CDF	The specified operation (i.e., opening) is not allowed on Version 1 CDFs. [Error]
MULTI_FILE_FORMAT	The specified operation is not applicable to CDFs with the multi-file format. For example, it does not make sense to inquire indexing statistics for a variable in a multi-file CDF (indexing is only used in single-file CDFs). [Informational]
NA_FOR_VARIABLE	The attempted operation is not applicable to the given variable. [Warning]

NEGATIVE_FP_ZERO	One or more of the values read/written are -0.0 (An illegal value on VAXes and DEC Alphas running OpenVMS). [Warning]
NO_ATTR_SELECTED	An attribute has not yet been selected. First select the attribute on which to perform the operation. [Error]
NO_CDF_SELECTED	A CDF has not yet been selected. First select the CDF on which to perform the operation. [Error]
NO_DELETE_ACCESS	Deleting is not allowed (read-only access). Make sure that delete access is allowed on the CDF file(s). [Error]
NO_ENTRY_SELECTED	An attribute entry has not yet been selected. First select the entry number on which to perform the operation. [Error]
NO_MORE_ACCESS	Further access to the CDF is not allowed because of a severe error. If the CDF was being modified, an attempt was made to save the changes made prior to the severe error. In any event, the CDF should still be closed. [Error]
NO_PADVALUE_SPECIFIED	A pad value has not yet been specified. The default pad value is currently being used for the variable. The default pad value was returned. [Informational]
NO_STATUS_SELECTED	A CDF status code has not yet been selected. First select the status code on which to perform the operation. [Error]
NO_SUCH_ATTR	The named attribute was not found. Note that attribute names are case-sensitive. [Error]
NO_SUCH_CDF	The specified CDF does not exist. Check that the file name specified is correct. [Error]
NO_SUCH_ENTRY	No such entry for specified attribute. [Error]
NO_SUCH_RECORD	The specified record does not exist for the given variable. [Error]
NO_SUCH_VAR	The named variable was not found. Note that variable names are case-sensitive. [Error]
NO_VAR_SELECTED	A variable has not yet been selected. First select the variable on which to perform the operation. [Error]
NO_VARS_IN_CDF	This CDF contains no rVariables. The operation performed is not applicable to a CDF with no rVariables. [Informational]
NO_WRITE_ACCESS	Write access is not allowed on the CDF file(s). Make sure that the CDF file(s) have the proper file system privileges and ownership. [Error]
NOT_A_CDF	Named CDF is corrupted or not actually a CDF. Contact CDF User Support if you are sure that the specified file is a CDF that should be readable by the CDF distribution being used. [Error]
NOT_A_CDF_OR_NOT_SUPPORTED	This can occur if an older CDF distribution is being used to read a CDF created by a more recent CDF distribution. Contact CDF

	User Support if you are sure that the specified file is a CDF that should be readable by the CDF distribution being used. CDF is backward compatible but not forward compatible. [Error]
PRECEEDING_RECORDS_ALLOCATED	Because of the type of variable, records preceding the range of records being allocated were automatically allocated as well. [Informational]
READ_ONLY_DISTRIBUTION	Your CDF distribution has been built to allow only read access to CDFs. Check with your system manager if you require write access. [Error]
READ_ONLY_MODE	The CDF is in read-only mode - modifications are not allowed. [Error]
SCRATCH_CREATE_ERROR	Cannot create a scratch file - error from file system. If a scratch directory has been specified, ensure that it is writeable. [Error]
SCRATCH_DELETE_ERROR	Cannot delete a scratch file - error from file system. [Error]
SCRATCH_READ_ERROR	Cannot read from a scratch file - error from file system. [Error]
SCRATCH_WRITE_ERROR	Cannot write to a scratch file - error from file system. [Error]
SINGLE_FILE_FORMAT	The specified operation is not applicable to CDFs with the single-file format. For example, it does not make sense to close a variable in a single-file CDF. [Informational]
SOME_ALREADY_ALLOCATED	Some of the records being allocated were already allocated. [Informational]
TOO_MANY_PARMS	A type of sparse arrays or compression was encountered having too many parameters. This could be caused by a corrupted CDF or if the CDF was created/modified by a CDF distribution more recent than the one being used. [Error]
TOO_MANY_VARS	A multi-file CDF on a PC may contain only a limited number of variables because of the 8.3 file naming convention of MS-DOS. This consists of 100 rVariables and 100 zVariables. [Error]
UNKNOWN_COMPRESSION	An unknown type of compression was specified or encountered. [Error]
UNKNOWN_SPARSENESS	An unknown type of sparseness was specified or encountered. [Error]
UNSUPPORTED_OPERATION	The attempted operation is not supported at this time. [Error]
VAR_ALREADY_CLOSED	The specified variable is already closed. [Informational]
VAR_CLOSE_ERROR	Error detected while trying to close variable file. Check that sufficient disk space exists for the variable file and that it has not been corrupted. [Error]
VAR_CREATE_ERROR	An error occurred while creating a variable file in a multi-file CDF. Check that a file quota has not been reached. [Error]

VAR_DELETE_ERROR	An error occurred while deleting a variable file in a multi-file CDF. Check that sufficient privilege exist to delete the CDF files. [Error]
VAR_EXISTS	Named variable already exists - cannot create or rename. Each variable in a CDF must have a unique name (rVariables and zVariables can not share names). Note that the CDF library when comparing variable names ignores trailing blanks. [Error]
VAR_NAME_TRUNC	Variable name truncated to CDF_VAR_NAME_LEN256 characters. The variable was created but with a truncated name. [Warning]
VAR_OPEN_ERROR	An error occurred while opening variable file. Check that sufficient privilege exists to open the variable file. Also make sure that the associated variable file exists. [Error]
VAR_READ_ERROR	Failed to read variable as requested - error from file system. Check that the associated file is not corrupted. [Error]
VAR_WRITE_ERROR	Failed to write variable as requested - error from file system. Check that the associated file is not corrupted. [Error]
VIRTUAL_RECORD_DATA	One or more of the records are virtual (never actually written to the CDF). Virtual records do not physically exist in the CDF file(s) but are part of the conceptual view of the data provided by the CDF library. Virtual records are described in the Concepts chapter in the CDF User's Guide. [Informational]

Appendix B

B.1 C#-CDF APIs

The overloaded APIs will have the following **TYPE** symbols, which represent a set of possible types for parameters.

- **TYPE** -- **int*** or “**out int**” for output
- **TYPE2** -- **int*** or “**out int[]**” for output
- **TYPE3** -- **void***, **string**, or **object** for input
- **TYPE4** -- **void***, “**out string**”, or “**out object**” for output
- **TYPE5** -- **void***, **string**, **string[]**, or **object** for input
- **TYPE6** -- **void***, “**out string**”, “**out string[]**” or “**out object**” for output
- **TYPE7** -- **long*** or “**out long**” for output
- **TYPE8** -- **string[]** or **object**

```
int CDFattrCreate (id, attrName, attrScope, attrNum)
void*   id;                                     /* in */
string  attrName;                             /* in */
int     attrScope;                            /* in */
TYPE  attrNum;                               /* out */
```

```
int CDFattrEntryInquire (id, attrNum, entryNum, dataType, numElements)
void*   id;                                     /* in */
int     attrNum;                               /* in */
int     entryNum;                             /* in */
TYPE  dataType;                             /* out */
TYPE  numElements;                          /* out */
```

```
int CDFattrGet (id, attrNum, entryNum, value)
void*   id;                                     /* in */
int     attrNum;                               /* in */
int     entryNum;                             /* in */
TYPE4 value;                                 /* out */
```

```
int CDFattrInquire (id, attrNum, attrName, attrScope, maxEntry)
void*   id;                                     /* in */
int     attrNum;                               /* in */
out string attrName;                          /* out */
TYPE  attrScope;                             /* out */
TYPE  maxEntry;                              /* out */
```

```
int CDFattrNum (id, attrName)
void*   id;                                     /* in */
string  attrName;                             /* in */
```

```

int CDFattrPut (id, attrNum, entryNum, dataType, numElements, value)
void* id; /* in */
int attrNum; /* in */
int entryNum; /* in */
int dataType; /* in */
int numElements; /* in */
TYPE3 value; /* in */

int CDFattrRename (id, attrNum, attrName)
void* id; /* in */
int attrNum; /* in */
string attrName; /* in */

int CDFclose (id)
void* id; /* in */

int CDFcloseCDF (id)
void* id; /* in */

int CDFcloserVar (id, varNum)
void* id; /* in */
int varNum; /* in */

int CDFclosezVar (id, varNum)
void* id; /* in */
int varNum; /* in */

int CDFconfirmAttrExistence (id, attrName)
void* id; /* in */
string attrName; /* in */

int CDFconfirmEntryExistence (id, attrNum, entryNum)
void* id; /* in */
int attrNum; /* in */
int entryNum; /* in */

int CDFconfirmrEntryExistence (id, attrNum, entryNum)
void* id; /* in */
int attrNum; /* in */
int entryNum; /* in */

int CDFconfirmrVarExistence (id, varNum)
void* id; /* in */
int varNum; /* in */

int CDFconfirmrVarPadValueExistence (id, varNum)
void* id; /* in */
int varNum; /* in */

int CDFconfirmzEntryExistence (id, attrNum, entryNum)
void* id; /* in */
int attrNum; /* in */
int entryNum; /* in */

int CDFconfirmzVarExistence (id, varNum)
void* id; /* in */

```

```

int    varNum;                                /* in */

int CDFconfirmzVarPadValueExistence (id, varNum)
void*  id;                                    /* in */
int    varNum;                                /* in */

int CDFcreate (CDFname, numDims, dimSizes, encoding, majority, id)
string  CDFname;                              /* in */
int     numDims;                              /* in */
int[]   dimSizes;                             /* in */
int     encoding;                             /* in */
int     majority;                             /* in */
void*   *id;                                   /* out */

int CDFcreateAttr (id, attrName, scope, attrNum)
void*   id;                                    /* in */
string  attrName;                             /* in */
int     scope;                                /* in */
TYPE  attrNum;                              /* out */

int CDFcreateCDF (CDFname, id)
string  CDFname;                              /* in */
void*   *id;                                   /* out */

int CDFcreatorVar (id, varName, dataType, numElements, recVary, dimVarys, varNum)
void*   id;                                    /* in */
string  varName;                              /* in */
int     dataType;                             /* in */
int     numElements;                          /* in */
int     recVary;                              /* in */
int[]   dimVarys;                             /* in */
TYPE  varNum;                              /* out */

int CDFcreatezVar (id, varName, dataType, numElements, numDims, dimSizes, recVary, dimVarys, varNum)
void*   id;                                    /* in */
string  varName;                              /* in */
int     dataType;                             /* in */
int     numElements;                          /* in */
int     numDims;                              /* in */
int[]   dimSizes;                             /* in */
int     recVary;                              /* in */
int[]   dimVarys;                             /* in */
TYPE  varNum;                              /* out */

int CDFdelete (id)
void*   id;                                    /* in */

int CDFdeleteAttr (id, attrNum)
void*   id;                                    /* in */
int     attrNum;                              /* in */

int CDFdeleteAttrgEntry (id, attrNum, entryNum)
void*   id;                                    /* in */
int     attrNum;                              /* in */
int     entryNum;                             /* in */

```



```

int CDFdeleteAttrEntry (id, attrNum, entryNum)
void* id; /* in */
int attrNum; /* in */
int entryNum; /* in */

int CDFdeleteAttrzEntry (id, attrNum, entryNum)
void* id; /* in */
int attrNum; /* in */
int entryNum; /* in */

int CDFdeleteCDF (id)
void* id; /* in */

int CDFdeleterVar (id, varNum)
void* id; /* in */
int varNum; /* in */

int CDFdeleterVarRecords (id, varNum, startRec, endRec)
void* id; /* in */
int varNum; /* in */
int startRec; /* in */
int endRec; /* in */

int CDFdeleterzVar (id, varNum)
void* id; /* in */
int varNum; /* in */

int CDFdeleterzVarRecords (id, varNum, startRec, endRec)
void* id; /* in */
int varNum; /* in */
int startRec; /* in */
int endRec; /* in */

int CDFdeleterzVarRecordsRenumber (id, varNum, startRec, endRec)
void* id; /* in */
int varNum; /* in */
int startRec; /* in */
int endRec; /* in */

int CDFdoc (id, version, release, text)
void* id; /* in */
TYPE version; /* out */
TYPE release; /* out */
out string text; /* out */

int CDFerror (status, message)
int status; /* in */
out string message; /* out */

int CDFgetAttrEntry (id, attrNum, entryNum, value)
void* id; /* in */
int attrNum; /* in */
int entryNum; /* in */
TYPE4 value; /* out */

int CDFgetAttrEntryDataType (id, attrNum, entryNum, dataType)

```

```

void* id; /* in */
int attrNum; /* in */
int entryNum; /* in */
TYPE dataType; /* out */

int CDFgetAttrgEntryNumElements (id, attrNum, entryNum, numElems)
void* id; /* in */
int attrNum; /* in */
int entryNum; /* in */
TYPE numElems; /* out */

int CDFgetAttrMaxgEntry (id, attrNum, entryNum)
void* id; /* in */
int attrNum; /* in */
TYPE entryNum; /* out */

int CDFgetAttrMaxrEntry (id, attrNum, entryNum)
void* id; /* in */
int attrNum; /* in */
TYPE entryNum; /* out */

int CDFgetAttrMaxzEntry (id, attrNum, entryNum)
void* id; /* in */
int attrNum; /* in */
TYPE entryNum; /* out */

int CDFgetAttrName (id, attrNum, attrName)
void* id; /* in */
int attrNum; /* in */
out string attrName; /* out */

int CDFgetAttrNum (id, attrName)
void* id; /* out */
/* in */
string attrName; /* in */

int CDFgetAttrrEntry (id, attrNum, entryNum, value)
void* id; /* in */
int attrNum; /* in */
int entryNum; /* in */
TYPE6 value; /* out */

int CDFgetAttrrEntryDataType (id, attrNum, varNum, dataType)
void* id; /* in */
int attrNum; /* in */
int varNum; /* in */
TYPE dataType; /* out */

int CDFgetAttrrEntryNumElements (id, attrNum, varNum, numElems)
void* id; /* in */
int attrNum; /* in */
int varNum; /* in */
TYPE numElems; /* out */

int CDFgetAttrrEntryNumStrings (id, attrNum, varNum, numStrings)
void* id; /* in */
int attrNum; /* in */

```

```

int    varNum;                                /* in */
TYPE numStrings;                            /* out */

int CDFgetAttrEntryStrings (id, attrNum, varNum, strings)
void*  id;                                    /* in */
int    attrNum;                              /* in */
int    varNum;                              /* in */
TYPE8 strings;                             /* out */

int CDFgetAttrScope (id, attrNum, scope)
void*  id;                                    /* in */
int    attrNum;                              /* in */
TYPE  scope;                               /* out */

int CDFgetAttrEntry (id, attrNum, entryNum, value)
void*  id;                                    /* in */
int    attrNum;                              /* in */
int    entryNum;                             /* in */
TYPE6 value;                               /* out */

int CDFgetAttrEntryDataType (id, attrNum, varNum, dataType)
void*  id;                                    /* in */
int    attrNum;                              /* in */
int    varNum;                              /* in */
TYPE  dataType;                           /* out */

int CDFgetAttrEntryNumElements (id, attrNum, varNum, numElems)
void*  id;                                    /* in */
int    attrNum;                              /* in */
int    varNum;                              /* in */
TYPE  numElems;                          /* out */

int CDFgetAttrEntryNumStrings (id, attrNum, varNum, numStrings)
void*  id;                                    /* in */
int    attrNum;                              /* in */
int    varNum;                              /* in */
TYPE  numStrings;                        /* out */

int CDFgetAttrEntryStrings (id, attrNum, varNum, strings)
void*  id;                                    /* in */
int    attrNum;                              /* in */
int    varNum;                              /* in */
TYPE8 strings;                             /* out */

int CDFgetCacheSize (id, numBuffers)
void*  id;                                    /* in */
TYPE  numBuffers;                        /* out */

int CDFgetChecksum (id, checksum)
void*  id;                                    /* in */
TYPE  checksum;                          /* out */

int CDFgetCompression (id, compressionType, compressionParms, compressionPercent)
void*  id;                                    /* in */
TYPE  compressionType;                  /* out */
TYPE2 compressionParms;                  /* out */

```

```

TYPE  compressionPercent;                                /* out */

int CDFgetCompressionCacheSize (id, numBuffers)
void*  id;                                                /* in */
TYPE  numBuffers;                                       /* out */

int CDFgetCompressionInfo (cdfName, compressionType, compressionParms, compressionSize, uncompressionSize)
string  cdfName;                                         /* in */
TYPE  compressionType;                                  /* out */
TYPE2 compressionParms;                                  /* out */
TYPE7 compressionSize;                                   /* out */
TYPE7 uncompressionSize;                                /* out */

int CDFgetCopyright (id, copyright)
void*  id;                                                /* in */
out string      copyright;                                /* out */

int CDFgetDataTypeSize (dataType, numBytes)
int     dataType;                                         /* in */
TYPE  numBytes;                                         /* out */

int CDFgetDecoding (id, decoding)
void*  id;                                                /* in */
TYPE  decoding;                                         /* out */

int CDFgetEncoding (id, encoding)
void*  id;                                                /* in */
TYPE  encoding;                                         /* out */

int CDFgetFileBackward ()

int CDFgetFormat (id, format)
void*  id;                                                /* in */
TYPE  format;                                           /* out */

int CDFgetLibraryCopyright (copyright)
out string      copyright;                                /* out */

int CDFgetLibraryVersion (version, release, increment, subIncrement)
TYPE  version;                                           /* out */
TYPE  release;                                           /* out */
TYPE  increment;                                         /* out */
out string      subIncrement;                             /* out */

int CDFgetLeapSecondLastUpdated (id, lastUpdated)
void*  id;                                                /* in */
TYPE  lastUpdated;                                       /* out */

int CDFgetMajority (id, majority)
void*  id;                                                /* in */
TYPE  majority;                                         /* out */

int CDFgetMaxWrittenRecNums (id, maxRecrVars, maxReczVars)
void*  id;                                                /* in */
TYPE  maxRecrVars;                                       /* out */
TYPE  maxReczVars;                                       /* out */

```

```

int CDFgetName (id, name)
void* id; /* in */
out string name; /* out */

int CDFgetNegtoPosfp0Mode (id, negtoPosfp0)
void* id; /* in */
TYPE negtoPosfp0; /* out */

int CDFgetNumAttrgEntries (id, attrNum, entries)
void* id; /* in */
int attrNum; /* in */
TYPE entries; /* out */

int CDFgetNumAttributes (id, numAttrs)
void* id; /* in */
TYPE numAttrs; /* out */

int CDFgetNumAttrrEntries (id, attrNum, entries)
void* id; /* in */
int attrNum; /* in */
TYPE entries; /* out */

int CDFgetNumAttrzEntries (id, attrNum, entries)
void* id; /* in */
int attrNum; /* in */
TYPE entries; /* out */

int CDFgetNumgAttributes (id, numAttrs)
void* id; /* in */
TYPE numAttrs; /* out */

int CDFgetNumrVars (id, numVars)
void* id; /* in */
TYPE numrVars; /* out */

int CDFgetNumvAttributes (id, numAttrs)
void* id; /* in */
TYPE numAttrs; /* out */

int CDFgetNumzVars (id, numVars)
void* id; /* in */
TYPE numzVars; /* out */

int CDFgetReadOnlyMode (id, mode)
void* id; /* in */
TYPE mode; /* out */

int CDFgetrVarAllocRecords (id, varNum, allocRecs)
void* id; /* in */
int varNum; /* in */
TYPE allocRecs; /* out */

int CDFgetrVarBlockingFactor (id, varNum, bf)
void* id; /* in */
int varNum; /* in */

```

```

TYPE bf; /* out */

int CDFgetrVarCacheSize (id, varNum, numBuffers)
void* id; /* in */
int varNum; /* in */
TYPE numBuffers; /* out */

int CDFgetrVarCompression (id, varNum, cType, cParms, cPercent)
void* id; /* in */
int varNum; /* in */
TYPE cType; /* out */
TYPE2 cParms; /* out */
TYPE cPercent; /* out */

int CDFgetrVarData (id, varNum, recNum, indices, value)
void* id; /* in */
int varNum; /* in */
int recNum; /* in */
int[] indices; /* in */
TYPE4 value; /* out */

int CDFgetrVarDataType (id, varNum, dataType)
void* id; /* in */
int varNum; /* in */
TYPE dataType; /* out */

int CDFgetrVarsDimSizes (id, varNum, dimSizes)
void* id; /* in */
int varNum; /* in */
TYPE2 dimSizes; /* out */

int CDFgetrVarDimVariances (id, varNum, dimVarys)
void* id; /* in */
int varNum; /* in */
TYPE2 dimVarys; /* out */

int CDFgetrVarInfo (id, varNum, dataType, numElems, numDims, dimSizes)
void* id; /* in */
int varNum; /* in */
TYPE dataType; /* out */
TYPE numElems; /* out */
TYPE numDims; /* out */
TYPE2 dimSizes; /* out */

int CDFgetrVarMaxAllocRecNum (id, varNum, maxRec)
void* id; /* in */
int varNum; /* in */
TYPE maxRec; /* out */

int CDFgetrVarMaxWrittenRecNum (id, varNum, maxRec)
void* id; /* in */
int varNum; /* in */
TYPE maxRec; /* out */

int CDFgetrVarName (id, varNum, varName)
void* id; /* in */

```

```

int    varNum;                /* in */
out string    varName;      /* out */

int CDFgetrVarsNumDims (id, varNum, numDims)
void* id;                    /* in */
int    varNum;              /* in */
TYPE numDims;             /* out */

int CDFgetrVarNumElements (id, varNum, numElems)
void* id;                    /* in */
int    varNum;              /* in */
TYPE numElems;           /* out */

int CDFgetrVarNumRecsWritten (id, varNum, numRecs)
void* id;                    /* in */
int    varNum;              /* in */
TYPE numRecs;            /* out */

int CDFgetrVarPadValue (id, varNum, padValue)
void* id;                    /* in */
int    varNum;              /* in */
TYPE4 padValue;          /* out */

int CDFgetrVarRecordData (id, varNum, recNum, buffer)
void* id;                    /* in */
int    varNum;              /* in */
int    recNum;              /* in */
TYPE6 buffer;            /* out */

int CDFgetrVarRecVariance (id, varNum, recVary)
void* id;                    /* in */
int    varNum;              /* in */
TYPE recVary;           /* out */

int CDFgetrVarReservePercent (id, varNum, percent)
void* id;                    /* in */
int    varNum;              /* in */
TYPE percent;           /* out */

int CDFgetrVarsDimSizes (id, dimSizes)
void* id;                    /* in */
TYPE2 dimSizes;         /* out */

int CDFgetrVarSeqData (id, varNum, value)
void* id;                    /* in */
int    varNum;              /* in */
TYPE4 value;           /* out */

int CDFgetrVarSeqPos (id, varNum, recNum, indices)
void* id;                    /* in */
int    varNum;              /* in */
TYPE recNum;           /* out */
TYPE2 indices;         /* out */

int CDFgetrVarsMaxWrittenRecNum (id, recNum)
void* id;                    /* in */

```

```

TYPE  recNum;                                /* out */

int CDFgetrVarsNumDims (id, numDims)
void*  id;                                     /* in */
TYPE  numDims;                               /* out */

int CDFgetrVarSparseRecords (id, varNum, sRecords)
void*  id;                                     /* in */
int    varNum;                                /* in */
TYPE  sRecords;                              /* out */

int CDFgetStageCacheSize (id, numBuffers)
void*  id;                                     /* in */
TYPE  numBuffers;                            /* out */

int CDFgetStatusText (status, text)
int status;                                    /* in */
out string      text;                          /* out */

int CDFgetValidate ()

int CDFgetVarNum (id, varName)
void*  id;                                     /* in */
string varName;                                /* in */

int CDFgetVersion (id, version, release, increment)
void*  id;                                     /* in */
TYPE  version;                               /* out */
TYPE  release;                               /* out */
TYPE  increment;                             /* out */

int CDFgetzMode (id, zMode)
void*  id;                                     /* in */
TYPE  zMode;                                /* out */

int CDFgetzVarAllocRecords (id, varNum, allocRecs)
void*  id;                                     /* in */
int    varNum;                                /* in */
TYPE  allocRecs;                             /* out */

int CDFgetzVarBlockingFactor (id, varNum, bf)
void*  id;                                     /* in */
int    varNum;                                /* in */
TYPE  bf;                                    /* out */

int CDFgetzVarCacheSize (id, varNum, numBuffers)
void*  id;                                     /* in */
int    varNum;                                /* in */
TYPE  numBuffers;                            /* out */

int CDFgetzVarCompression (id, varNum, cType, cParms, cPercent)
void*  id;                                     /* in */
int    varNum;                                /* in */
TYPE  cType;                                 /* out */
TYPE2 cParms;                                /* out */
TYPE  cPercent;                              /* out */

```



```

int CDFgetzVarData (id, varNum, recNum, indices, value)
void* id; /* in */
int varNum; /* in */
int recNum; /* in */
int[] indices; /* in */
TYPE4 value; /* out */

int CDFgetzVarDataType (id, varNum, dataType)
void* id; /* in */
int varNum; /* in */
TYPE dataType; /* out */

int CDFgetzVarDimSizes (id, varNum, dimSizes)
void* id; /* in */
int varNum; /* in */
TYPE2 dimSizes; /* out */

int CDFgetzVarDimVariances (id, varNum, dimVarys)
void* id; /* in */
int varNum; /* in */
TYPE2 dimVarys; /* out */

int CDFgetzVarInfo (id, varNum, dataType, numElems, numDims, dimSizes)
void* id; /* in */
int varNum; /* in */
TYPE dataType; /* out */
TYPE numElems; /* out */
TYPE numDims; /* out */
TYPE2 dimSizes; /* out */

int CDFgetzVarMaxAllocRecNum (id, varNum, maxRec)
void* id; /* in */
int varNum; /* in */
TYPE maxRec; /* out */

int CDFgetzVarMaxWrittenRecNum (id, varNum, maxRec)
void* id; /* in */
int varNum; /* in */
TYPE maxRec; /* out */

int CDFgetzVarName (id, varNum, varName)
void* id; /* in */
int varNum; /* in */
out string varName; /* out */

int CDFgetzVarNumDims (id, varNum, numDims)
void* id; /* in */
int varNum; /* in */
TYPE numDims; /* out */

int CDFgetzVarNumElements (id, varNum, numElems)
void* id; /* in */
int varNum; /* in */
TYPE numElems; /* out */

```

```

int CDFgetzVarNumRecsWritten (id, varNum, numRecs)
void* id; /* in */
int varNum; /* in */
TYPE numRecs; /* out */

int CDFgetzVarPadValue (id, varNum, padValue)
void* id; /* in */
int varNum; /* in */
TYPE4 padValue; /* out */

int CDFgetzVarRecordData (id, varNum, recNum, buffer)
void* id; /* in */
int varNum; /* in */
int recNum; /* in */
TYPE6 buffer; /* out */

int CDFgetzVarRecVariance (id, varNum, recVary)
void* id; /* in */
int varNum; /* in */
TYPE recVary; /* out */

int CDFgetzVarReservePercent (id, varNum, percent)
void* id; /* in */
int varNum; /* in */
TYPE percent; /* out */

int CDFgetzVarSeqData (id, varNum, value)
void* id; /* in */
int varNum; /* in */
TYPE4 value; /* out */

int CDFgetzVarSeqPos (id, varNum, recNum, indices)
void* id; /* in */
int varNum; /* in */
TYPE recNum; /* out */
TYPE2 indices; /* out */

int CDFgetzVarsMaxWrittenRecNum (id, recNum)
void* id; /* in */
TYPE recNum; /* out */

int CDFgetzVarSparseRecords (id, varNum, sRecords)
void* id; /* in */
int varNum; /* in */
TYPE sRecords; /* out */

int CDFhyperGetzVarData (id, varNum, recNum, recCount, recInterval, indices, counts, intervals, buffer)
void* id; /* in */
int varNum; /* in */
int recNum; /* in */
int recCount; /* in */
int recInterval; /* in */
int[] indices; /* in */
int[] counts; /* in */
int[] intervals; /* in */
TYPE6 buffer; /* out */

```

```

int CDFhyperGetzVarData (id, varNum, recNum, recCount, recInterval, indices, counts, intervals, buffer)
void* id; /* in */
int varNum; /* in */
int recNum; /* in */
int recCount; /* in */
int recInterval; /* in */
int[] indices; /* in */
int[] counts; /* in */
int[] intervals; /* in */
TYPE6 buffer; /* out */

```

```

int CDFhyperPutzVarData (id, varNum, recNum, recCount, recInterval, indices, counts, intervals, buffer)
void* id; /* in */
int varNum; /* in */
int recNum; /* in */
int recCount; /* in */
int recInterval; /* in */
int[] indices; /* in */
int[] counts; /* in */
int[] intervals; /* in */
TYPE5 buffer; /* in */

```

```

int CDFhyperPutzVarData (id, varNum, recNum, recCount, recInterval, indices, counts, intervals, buffer)
void* id; /* in */
int varNum; /* in */
int recNum; /* in */
int recCount; /* in */
int recInterval; /* in */
int[] indices; /* in */
int[] counts; /* in */
int[] intervals; /* in */
TYPE5 buffer; /* in */

```

```

int CDFinquire (id, numDims, dimSizes, encoding, majority, maxRec, numVars, numAttrs)
void* id; /* in */
TYPE numDims; /* out */
TYPE2 dimSizes; /* out */
TYPE encoding; /* out */
TYPE majority; /* out */
TYPE maxRec; /* out */
TYPE numVars; /* out */
TYPE numAttrs; /* out */

```

```

int CDFinquireAttr (id, attrNum, attrName, attrScope, maxgEntry, maxrEntry, maxzEntry)
void* id; /* in */
int attrNum; /* in */
out string attrName; /* out */
TYPE attrScope; /* out */
TYPE maxgEntry; /* out */
TYPE maxrEntry; /* out */
TYPE maxzEntry; /* out */

```

```

int CDFinquireAttrgEntry (id, attrNum, entryNum, dataType, numElems)
void* id; /* in */
int attrNum; /* in */

```

```

int    entryNum;           /* in */
TYPE dataType;          /* out */
TYPE numElems;           /* out */

int CDFinquireAttrEntry (id, attrNum, entryNum, dataType, numElems)
void*  id;                 /* in */
int    attrNum;            /* in */
int    entryNum;           /* in */
TYPE dataType;           /* out */
TYPE numElems;           /* out */

int CDFinquireAttrzEntry (id, attrNum, entryNum, dataType, numElems)
void*  id;                 /* in */
int    attrNum;            /* in */
int    entryNum;           /* in */
TYPE dataType;           /* out */
TYPE numElems;           /* out */

int CDFinquireCDF (id, numDims, dimSizes, encoding, majority, maxrRec, numrVars, maxzRec,
                  numzVars, numAttrs)
void*  id;                 /* in */
TYPE numDims;            /* out */
TYPE2 dimSizes;          /* out */
TYPE encoding;           /* out */
TYPE majority;           /* out */
TYPE maxrRec;            /* out */
TYPE numrVars;           /* out */
TYPE maxzRec;            /* out */
TYPE numzVars;           /* out */
TYPE numAttrs;           /* out */

int CDFinquirerVar (id, varNum, varName, dataType, numElems, numDims, dimSizes, recVary, dimVarys)
void*  id;                 /* in */
int    varNum;             /* in */
out string varName;        /* out */
TYPE dataType;           /* out */
TYPE numElems;           /* out */
TYPE numDims;           /* out */
TYPE2 dimSizes;          /* out */
TYPE recVary;           /* out */
TYPE2 dimVarys;         /* out */

int CDFinquirezVar (id, varNum, varName, dataType, numElems, numDims, dimSizes, recVary, dimVarys)
void*  id;                 /* in */
int    varNum;             /* in */
out string varName;        /* out */
TYPE dataType;           /* out */
TYPE numElems;           /* out */
TYPE numDims;           /* out */
TYPE2 dimSizes;          /* out */
TYPE recVary;           /* out */
TYPE2 dimVarys;         /* out */

int CDFopen (CDFname, id)
string  CDFname;           /* in */
void*   *id;               /* out */

```

```

int CDFopenCDF (CDFname, id)
string  CDFname;          /* in */
void*   *id;              /* out */

int CDFselectCDF (id)
void*   id;              /* in */

int CDFputAttrEntry (id, attrNum, entryNum, value)
void*   id;              /* in */
int     attrNum;         /* in */
int     entryNum;        /* in */
string value;           /* in */

int CDFputAttrEntry (id, attrNum, entryNum, dataType, numElems, value)
void*   id;              /* in */
int     attrNum;         /* in */
int     entryNum;        /* in */
int     dataType;        /* in */
int     numElems;        /* in */
TYPE3 value;           /* in */

int CDFputAttrEntry (id, attrNum, entryNum, value)
void*   id;              /* in */
int     attrNum;         /* in */
int     entryNum;        /* in */
string value;           /* in */

int CDFputAttrEntry (id, attrNum, entryNum, dataType, numElems, value)
void*   id;              /* in */
int     attrNum;         /* in */
int     entryNum;        /* in */
int     dataType;        /* in */
int     numElems;        /* in */
TYPE3 value;           /* in */

int CDFputAttrEntryStrings (id, attrNum, strings)
void*   id;              /* in */
int     attrNum;         /* in */
TYPE8 strings;         /* in */

int CDFputAttrEntry (id, attrNum, entryNum, value)
void*   id;              /* in */
int     attrNum;         /* in */
int     entryNum;        /* in */
string value;           /* in */

int CDFputAttrEntry (id, attrNum, entryNum, dataType, numElems, value)
void*   id;              /* in */
int     attrNum;         /* in */
int     entryNum;        /* in */
int     dataType;        /* in */
int     numElems;        /* in */
TYPE3 value;           /* in */

int CDFputAttrEntryStrings (id, attrNum, strings)

```

```

void* id; /* in */
int attrNum; /* in */
TYPE8 strings; /* in */

int CDFputrVarData (id, varNum, recNum, indices, value)
void* id; /* in */
int varNum; /* in */
int recNum; /* in */
int[] indices; /* in */
TYPE3 value; /* in */

int CDFputrVarPadValue (id, varNum, padValue)
void* id; /* in */
int varNum; /* in */
TYPE3 padValue; /* in */

int CDFputrVarRecordData (id, varNum, recNum, values)
void* id; /* in */
int varNum; /* in */
int recNum; /* in */
TYPE5 values; /* in */

int CDFputrVarSeqData (id, varNum, value)
void* id; /* in */
int varNum; /* in */
TYPE3 value; /* in */

int CDFputzVarData (id, varNum, recNum, indices, value)
void* id; /* in */
int varNum; /* in */
int recNum; /* in */
int[] indices; /* in */
TYPE3 value; /* in */

int CDFputzVarPadValue (id, varNum, padValue)
void* id; /* in */
int varNum; /* in */
TYPE3 padValue; /* in */

int CDFputzVarRecordData (id, varNum, recNum, values)
void* id; /* in */
int varNum; /* in */
int recNum; /* in */
TYPE5 values; /* in */

int CDFputzVarSeqData (id, varNum, value)
void* id; /* in */
int varNum; /* in */
TYPE3 value; /* in */

int CDFrenameAttr (id, attrNum, attrName)
void* id; /* in */
int attrNum; /* in */
string attrName; /* in */

int CDFrenamerVar (id, varNum, varName)

```

```

void* id; /* in */
int varNum; /* in */
string varName; /* in */

int CDFrenamezVar (id, varNum, varName)
void* id; /* in */
int varNum; /* in */
string varName; /* in */

int CDFselect (id)
void* id; /* in */

int CDFselectCDF (id)
void* id; /* in */

int CDFsetAttrEntryDataSpec (id, attrNum, entryNum, dataType)
void* id; /* in */
int attrNum; /* in */
int entryNum; /* in */
int dataType; /* in */

int CDFsetAttrEntryDataSpec (id, attrNum, entryNum, dataType)
void* id; /* in */
int attrNum; /* in */
int entryNum; /* in */
int dataType; /* in */

int CDFsetAttrScope (id, attrNum, scope)
void* id; /* in */
int attrNum; /* in */
int scope; /* in */

int CDFsetAttrzEntryDataSpec (id, attrNum, entryNum, dataType)
void* id; /* in */
int attrNum; /* in */
int entryNum; /* in */
int dataType; /* in */

int CDFsetCacheSize (id, numBuffers)
void* id; /* in */
int numBuffers; /* in */

int CDFsetChecksum (id, checksum)
void* id; /* in */
int checksum; /* in */

int CDFsetCompression (id, compressionType, compressionParms)
void* id; /* in */
int compressionType; /* in */
int[] compressionParms; /* in */

int CDFsetCompressionCacheSize (id, numBuffers)
void* id; /* in */
int numBuffers; /* in */

int CDFsetDecoding (id, decoding)

```

```

void* id; /* in */
int decoding; /* in */

int CDFsetEncoding (id, encoding)
void* id; /* in */
int encoding; /* in */

void CDFsetFileBackward (mode)
int mode; /* in */

int CDFsetFormat (id, format)
void* id; /* in */
int format; /* in */

int CDFsetLeapSecondLastUpdated (id, lastUpdated)
void* id; /* in */
int lastUpdated; /* in */

int CDFsetMajority (id, majority)
void* id; /* in */
int majority; /* in */

int CDFsetNegtoPosfp0Mode (id, negtoPosfp0)
void* id; /* in */
int negtoPosfp0; /* in */

int CDFsetReadOnlyMode (id, readOnly)
void* id; /* in */
int readOnly; /* in */

int CDFsetrVarAllocBlockRecords (id, varNum, firstRec, lastRec)
void* id; /* in */
int varNum; /* in */
int firstRec; /* in */
int lastRec; /* in */

int CDFsetrVarAllocRecords (id, varNum, numRecs)
void* id; /* in */
int varNum; /* in */
int numRecs; /* in */

int CDFsetrVarBlockingFactor (id, varNum, bf)
void* id; /* in */
int varNum; /* in */
int bf; /* in */

int CDFsetrVarCacheSize (id, varNum, numBuffers)
void* id; /* in */
int varNum; /* in */
int numBuffers; /* in */

int CDFsetrVarCompression (id, varNum, compressionType, compressionParms)
void* id; /* in */
int varNum; /* in */
int compressionType; /* in */
int[] compressionParms; /* in */

```



```

int CDFsetrVarDataSpec (id, varNum, dataType)
void* id; /* in */
int varNum; /* in */
int dataType; /* in */

int CDFsetrVarDimVariances (id, varNum, dimVarys)
void* id; /* in */
int varNum; /* in */
int[] dimVarys; /* in */

int CDFsetrVarInitialRecs (id, varNum, initialRecs)
void* id; /* in */
int varNum; /* in */
int initialRecs; /* in */

int CDFsetrVarRecVariance (id, varNum, recVary)
void* id; /* in */
int varNum; /* in */
int recVary; /* in */

int CDFsetrVarReservePercent (id, varNum, reservePercent)
void* id; /* in */
int varNum; /* in */
int reservePercent; /* in */

int CDFsetrVarsCacheSize (id, numBuffers)
void* id; /* in */
int numBuffers; /* in */

int CDFsetrVarSeqPos (id, varNum, recNum, indices)
void* id; /* in */
int varNum; /* in */
int recNum; /* in */
int[] indices; /* in */

int CDFsetrVarSparseRecords (id, varNum, sRecords)
void* id; /* in */
int varNum; /* in */
int sRecords; /* in */

int CDFsetStageCacheSize (id, numBuffers)
void* id; /* in */
int numBuffers; /* in */

void CDFsetValidate (mode)
int mode; /* in */

int CDFsetzMode (id, zMode)
void* id; /* in */
int zMode; /* in */

int CDFsetzVarAllocBlockRecords (id, varNum, firstRec, lastRec)
void* id; /* in */
int varNum; /* in */
int firstRec; /* in */

```

```

int      lastRec;                                /* in */

int CDFsetzVarAllocRecords (id, varNum, numRecs)
void*   id;                                    /* in */
int     varNum;                                /* in */
int     numRecs;                               /* in */

int CDFsetzVarBlockingFactor (id, varNum, bf)
void*   id;                                    /* in */
int     varNum;                                /* in */
int     bf;                                    /* in */

int CDFsetzVarCacheSize (id, varNum, numBuffers)
void*   id;                                    /* in */
int     varNum;                                /* in */
int     numBuffers;                            /* in */

int CDFsetzVarCompression (id, varNum, compressionType, compressionParms)
void*   id;                                    /* in */
int     varNum;                                /* in */
int     compressionType;                      /* in */
int[]   compressionParms;                     /* in */

int CDFsetzVarDataSpec (id, varNum, dataType)
void*   id;                                    /* in */
int     varNum;                                /* in */
int     dataType;                             /* in */

int CDFsetzVarDimVariances (id, varNum, dimVarys)
void*   id;                                    /* in */
int     varNum;                                /* in */
int[]   dimVarys;                             /* in */

int CDFsetzVarInitialRecs (id, varNum, initialRecs)
void*   id;                                    /* in */
int     varNum;                                /* in */
int     initialRecs;                          /* in */

int CDFsetzVarRecVariance (id, varNum, recVary)
void*   id;                                    /* in */
int     varNum;                                /* in */
int     recVary;                              /* in */

int CDFsetzVarReservePercent (id, varNum, reservePercent)
void*   id;                                    /* in */
int     varNum;                                /* in */
int     reservePercent;                       /* in */

int CDFsetzVarsCacheSize (id, numBuffers)
void*   id;                                    /* in */
int     numBuffers;                            /* in */

int CDFsetzVarSeqPos (id, varNum, recNum, indices)
void*   id;                                    /* in */
int     varNum;                                /* in */
int     recNum;                               /* in */

```

```

int[]    indices;                                /* in */

int CDFsetzVarSparseRecords (id, varNum, sRecords)
void*    id;                                    /* in */
int      varNum;                                /* in */
int      sRecords;                              /* in */

int CDFvarClose (id, varNum)
void*    id;                                    /* in */
int      varNum;                                /* in */

int CDFvarCreate (id, varName, dataType, numElements, recVariance, dimVariances, varNum)
void*    id;                                    /* in */
string   varName;                               /* in */
int      dataType;                              /* in */
int      numElements;                          /* in */
int      recVariance;                          /* in */
int[]    dimVariances;                         /* in */
TYPE     varNum;                               /* out */

int CDFvarGet (id, varNum, recNum, indices, value)
void*    id;                                    /* in */
int      varNum;                                /* in */
int      recNum;                                /* in */
int[]    indices;                              /* in */
TYPE4 value;                                  /* out */

int CDFvarHyperGet (id, varNum, recStart, recCount, recInterval, indices, counts, intervals, buffer)
void*    id;                                    /* in */
int      varNum;                                /* in */
int      recStart;                              /* in */
int      recCount;                              /* in */
int      recInterval;                          /* in */
int[]    indices;                              /* in */
int[]    counts;                               /* in */
int[]    intervals;                            /* in */
TYPE6 buffer;                                /* out */

int CDFvarHyperPut (id, varNum, recStart, recCount, recInterval, indices, counts, intervals, buffer)
void*    id;                                    /* in */
int      varNum;                                /* in */
int      recStart;                              /* in */
int      recCount;                              /* in */
int      recInterval;                          /* in */
int[]    indices;                              /* in */
int[]    counts;                               /* in */
int[]    intervals;                            /* in */
TYPE3 buffer;                                /* in */

int CDFvarInquire (id, varNum, varName, dataType, numElements, recVariance, dimVariances)
void*    id;                                    /* in */
int      varNum;                                /* in */
out string    varName;                          /* out */
TYPE dataType;                              /* out */
TYPE numElements;                          /* out */
TYPE recVariance;                          /* out */

```

```
TYPE2 dimVariances; /* out */

int CDFvarNum (id, varName)
void* id; /* in */
string varName; /* in */

int CDFvarPut (id, varNum, recNum, indices, value)
void* id; /* in */
int varNum; /* in */
int recNum; /* in */
int[] indices; /* in */
TYPE3 value; /* in */

int CDFvarRename (id, varNum, varName)
void* id; /* in */
int varNum; /* in */
string varName; /* in */
```


B.2 EPOCH Utility Methods

The overloaded APIs will have the following **TYPE** symbols, which represent a set of possible types for parameters.

- **TYPE** -- **int*** or “**out int**”
- **TYPE2** -- **double*** or “**out double[]**”
- **TYPE3** -- **double** or **long**
- **TYPE4** -- **double*** or **long***

```
double computeEPOCH (year, month, day, hour, minute, second, msec)
int year; /* in */
int month; /* in */
int day; /* in */
int hour; /* in */
int minute; /* in */
int second; /* in */
int msec; /* in */
```

```
double[] computeEPOCH (year, month, day, hour, minute, second, msec)
int[] year; /* in */
int[] month; /* in */
int[] day; /* in */
int[] hour; /* in */
int[] minute; /* in */
int[] second; /* in */
int[] msec; /* in */
```

```
void EPOCHbreakdown (epoch, year, month, day, hour, minute, second, msec)
double epoch; /* in */
TYPE year; /* out */
TYPE month; /* out */
TYPE day; /* out */
TYPE hour; /* out */
TYPE minute; /* out */
TYPE second; /* out */
TYPE msec; /* out */
```

```
void EPOCHbreakdown (epoch, year, month, day, hour, minute, second, msec)
double[] epoch; /* in */
out int[] year; /* out */
out int[] month; /* out */
out int[] day; /* out */
out int[] hour; /* out */
out int[] minute; /* out */
out int[] second; /* out */
out int[] msec; /* out */
```

```
string toEncodeEPOCH (epoch)
double epoch; /* in */
```

```
string toEncodeEPOCH (epoch, style)
double epoch; /* in */
int style; /* in */
```



```

string[] toEncodeEPOCH (epoch)
double[] epoch;
/* in */

string[] toEncodeEPOCH (epoch, style)
double[] epoch;
int style;
/* in */
/* in */

void encodeEPOCH (epoch, epString)
double epoch;
out string epString;
/* in */
/* out */

void encodeEPOCH (epoch, epString)
double[] epoch;
out string[] epString;
/* in */
/* out */

void encodeEPOCH1 (epoch, epString)
double epoch;
out string epString;
/* in */
/* out */

void encodeEPOCH2 (epoch, epString)
double epoch;
out string epString;
/* in */
/* out */

void encodeEPOCH3 (epoch, epString)
double epoch;
out string epString;
/* in */
/* out */

void encodeEPOCH4 (epoch, epString)
double epoch;
out string epString;
/* in */
/* out */

void encodeEPOCHx (epoch, format, epString)
double epoch;
string format;
out string epString;
/* in */
/* in */
/* out */

double toParseEPOCH (epString)
string epString;
/* in */

double[] toParseEPOCH (epString)
string[] epString;
/* in */

double parseEPOCH (epString)
string epString;
/* in */

double[] parseEPOCH (epString)
string[] epString;
/* in */

double parseEPOCH1 (epString)
string epString;
/* in */

double parseEPOCH2 (epString)
string epString;
/* in */

double parseEPOCH3 (epString)

```

```

string epString; /* in */

double parseEPOCH4 (epString)
string epString; /* in */

double computeEPOCH16 (year, month, day, hour, minute, second, msec, microsec, nanosec, picosec)
int year; /* in */
int month; /* in */
int day; /* in */
int hour; /* in */
int minute; /* in */
int second; /* in */
int msec; /* in */
int microsec; /* in */
int nanosec; /* in */
int picosec; /* in */
TYPE2 epoch; /* out */

void EPOCH16breakdown (epoch, year, month, day, hour, minute, second, msec, microsec, nanosec, picosec)
double[] epoch; /* in */
TYPE year; /* out */
TYPE month; /* out */
TYPE day; /* out */
TYPE hour; /* out */
TYPE minute; /* out */
TYPE second; /* out */
TYPE msec; /* out */
TYPE microsec; /* out */
TYPE nanosec; /* out */
TYPE picosec; /* out */

string toEncodeEPOCH16 (epoch)
double[] epoch; /* in */

string toEncodeEPOCH16 (epoch, style)
double[] epoch; /* in */
int style; /* in */

void encodeEPOCH16 (epoch, epString)
double[] epoch; /* in */
out string epString; /* out */

void encodeEPOCH16_1 (epoch, epString)
double[] epoch; /* in */
out string epString; /* out */

void encodeEPOCH16_2 (epoch, epString)
double[] epoch; /* in */
out string epString; /* out */

void encodeEPOCH16_3 (epoch, epString)
double[] epoch; /* in */
out string epString; /* out */

void encodeEPOCH16_4 (epoch, epString)
double[] epoch; /* in */

```

```

out string epString;                                     /* out */

void encodeEPOCH16_x (epoch, format, epString)
double[] epoch;                                        /* in */
string format;                                       /* in */
out string epString;                                  /* out */

double[] toParseEPOCH16 (epString)
string epString;                                     /* in */

double parseEPOCH16 (epString, epoch)
string epString;                                     /* in */
TYPE2 epoch;                                        /* out */

double parseEPOCH16_1 (epString)
string epString;                                     /* in */
TYPE2 epoch;                                       /* out */

double parseEPOCH16_2 (epString)
string epString;                                     /* in */
TYPE2 epoch;                                       /* out */

double parseEPOCH16_3 (epString)
string epString;                                     /* in */
TYPE2 epoch;                                       /* out */

double parseEPOCH16_4 (epString)
string epString;                                     /* in */
TYPE2 epoch;                                       /* out */

long computeTT2000 (year, month, day)
TYPE3 year;                                        /* in */
TYPE3 month;                                       /* in */
TYPE3 day;                                         /* in */

long[] computeTT2000 (year, month, day)
double[] year;                                       /* in */
double[] month;                                       /* in */
double[] day;                                         /* in */

long computeTT2000 (year, month, day, hour)
TYPE3 year;                                        /* in */
TYPE3 month;                                       /* in */
TYPE3 day;                                         /* in */
TYPE3 hour;                                        /* in */

long[] computeTT2000 (year, month, day, hour)
double[] year;                                       /* in */
double[] month;                                       /* in */
double[] day;                                         /* in */
double[] hour;                                        /* in */

long computeTT2000 (year, month, day, hour, minute)
TYPE3 year;                                        /* in */
TYPE3 month;                                       /* in */

```

```
TYPE3 day; /* in */
TYPE3 hour; /* in */
TYPE3 minute; /* in */
```

```
long[] computeTT2000 (year, month, day, hour, minute)
double[] year; /* in */
double[] month; /* in */
double[] day; /* in */
double[] hour; /* in */
double[] minute; /* in */
```

```
long computeTT2000 (year, month, day, hour, minute, second)
TYPE3 year; /* in */
TYPE3 month; /* in */
TYPE3 day; /* in */
TYPE3 hour; /* in */
TYPE3 minute; /* in */
TYPE3 second; /* in */
```

```
long[] computeTT2000 (year, month, day, hour, minute, second)
double[] year; /* in */
double[] month; /* in */
double[] day; /* in */
double[] hour; /* in */
double[] minute; /* in */
double[] second; /* in */
```

```
long computeTT2000 (year, month, day, hour, minute, second, msec)
TYPE3 year; /* in */
TYPE3 month; /* in */
TYPE3 day; /* in */
TYPE3 hour; /* in */
TYPE3 minute; /* in */
TYPE3 second; /* in */
TYPE3 msec; /* in */
```

```
long[] computeTT2000 (year, month, day, hour, minute, second, msec)
double[] year; /* in */
double[] month; /* in */
double[] day; /* in */
double[] hour; /* in */
double[] minute; /* in */
double[] second; /* in */
double[] msec; /* in */
```

```
long computeTT2000 (year, month, day, hour, minute, second, msec, usec)
TYPE3 year; /* in */
TYPE3 month; /* in */
TYPE3 day; /* in */
TYPE3 hour; /* in */
TYPE3 minute; /* in */
TYPE3 second; /* in */
TYPE3 msec; /* in */
TYPE3 usec; /* in */
```

```
long[] computeTT2000 (year, month, day, hour, minute, second, msec, usec)
```

```
double[] year; /* in */
double[] month; /* in */
double[] day; /* in */
double[] hour; /* in */
double[] minute; /* in */
double[] second; /* in */
double[] msec; /* in */
double[] usec; /* in */
```

```
long computeTT2000 (year, month, day, hour, minute, second, msec, usec, nsec)
TYPE3 year; /* in */
TYPE3 month; /* in */
TYPE3 day; /* in */
TYPE3 hour; /* in */
TYPE3 minute; /* in */
TYPE3 second; /* in */
TYPE3 msec; /* in */
TYPE3 usec; /* in */
TYPE3 nsec; /* in */
```

```
long[] computeTT2000 (year, month, day, hour, minute, second, msec, usec, nsec)
double[] year; /* in */
double[] month; /* in */
double[] day; /* in */
double[] hour; /* in */
double[] minute; /* in */
double[] second; /* in */
double[] msec; /* in */
double[] usec; /* in */
double[] nsec; /* in */
```

```
void TT2000breakdown (epoch, year, month, day, hour, minute, second, msec, usec, nsec)
long epoch; /* in */
out TYPE4 year; /* out */
out TYPE4 month; /* out */
out TYPE4 day; /* out */
out TYPE4 hour; /* out */
out TYPE4 minute; /* out */
out TYPE4 second; /* out */
out TYPE4 msec; /* out */
out TYPE4 usec; /* out */
out TYPE4 nsec; /* out */
```

```
void TT2000breakdown (epoch, year, month, day, hour, minute, second, msec, usec, nsec)
long[] epoch; /* in */
out double[] year; /* out */
out double[] month; /* out */
out double[] day; /* out */
out double[] hour; /* out */
out double[] minute; /* out */
out double[] second; /* out */
out double[] msec; /* out */
out double[] usec; /* out */
out double[] nsec; /* out */
```

```
string toEncodeTT2000 (epoch)
```

```

long epoch; /* in */

string toEncodeTT2000 (epoch, style)
long epoch; /* in */
int style; /* in */

string[] toEncodeTT2000 (epoch)
long[] epoch; /* in */

string[] toEncodeTT2000 (epoch, style)
long[] epoch; /* in */
int style; /* in */

void encodeTT2000 (epoch, epString, style)
long epoch; /* in */
out string epString; /* out */
int style; /* in */

void encodeTT2000 (epoch, epString, style)
long[] epoch; /* in */
out string[] epString; /* out */
int style; /* in */

long toParseTT2000 (epString)
string epString; /* in */

long[] toParseTT2000 (epString)
string[] epString; /* in */

long parseTT2000 (epString)
string epString; /* in */

long[] parseTT2000 (epString)
string[] epString; /* in */

void CDFgetLastDateinLeapSecondsTable (year, month, day)
out int year; /* out */
out int month; /* out */
out int day; /* out */

double EPOCHtoUnixTime (epoch)
double epoch; /* in */

double[] EPOCHtoUnixTime (epochs)
double[] epochs; /* in */

double EPOCH16toUnixTime (epoch)
double[] epoch; /* in */

double TT2000toUnixTime (epoch)
long epoch; /* in */

double[] TT2000toUnixTime (epochs)
long[] epochs; /* in */

double UnixTimetoEPOCH (unixTime)

```

```
double unixTime; /* in */

double[] UnixTimetoEPOCH (unixTimes)
double[] unixTimes; /* in */

double[] UnixTimetoEPOCH16 (unixTime)
double unixTime; /* in */

long UnixTimetoTT2000 (unixTime)
double unixTime; /* in */

long[] UnixTimetoTT2000 (unixTimes)
double[] unixTimes; /* in */
```

B.3 CDF Utility Methods

```
bool CDFFileExists (fileName)                                     /* in */
string fileName;

int CDFgetChecksumValue(checksum)                               /* in */
string fileName;

int CDFgetCompressionTypeValue(compressionType)                /* in */
string compressionType;

int CDFgetDataTypeValue(dataType)                               /* in */
string dataType;

int CDFgetDecodingValue(decoding)                               /* in */
string decoding;

int CDFgetEncodingValue(encoding)                               /* in */
string encoding;

int CDFgetFormatValue(format)                                   /* in */
string format;

int CDFgetMajorityValue(majority)                               /* in */
string majority;

int CDFgetSparseRecordValue(sparseRecord)                       /* in */
string sparseRecord;

string CDFgetStringChecksum(checksum)                           /* in */
int checksum;

string CDFgetStringCompressionType(compressionType)            /* in */
int compressionType;

string CDFgetStringDataType(dataType)                           /* in */
int dataType;

string CDFgetStringDecoding(decoding)                           /* in */
int decoding;

string CDFgetStringEncoding(encoding)                           /* in */
int encoding;

string CDFgetStringFormat(format)                               /* in */
int format;

string CDFgetStringMajority(majority)                           /* in */
int majority;

string CDFgetStringSparseRecord(sparseRecord)                  /* in */
int sparseRecord;
```


B.4 CDF Exception Methods

```
int CDFgetCurrentStatus ()
```

```
string CDFgetStatusMsg(status)  
int status;
```

Index

ALPHAOSF1_DECODING	9	zVariable entry	
ALPHAOSF1_ENCODING	8	deleting	206
ALPHAVMSd_DECODING	9	Attributes	
ALPHAVMSd_ENCODING	8	entries	
ALPHAVMSg_DECODING	9	global entry	
ALPHAVMSg_ENCODING	8	data type	
ALPHAVMSi_DECODING	9	inquiring	208
ALPHAVMSi_ENCODING	8	Attributes	
ARM_BIG_DECODING	10	entries	
ARM_BIG_ENCODING	8	global entry	
ARM_LITTLE_DECODING	10	number of elements	
ARM_LITTLE_ENCODING	8	inquiring	209
attribute		Attributes	
inquiring	194	entries	
number		global entry	
inquiring	196	last entry number	
renaming	198	inquiring	210
attributes		Attributes	
checking existence	199	entries	
creation 190, 202, 247, 250, 252, 253, 254, 256, 257, 258		rVariable entry	
entries		last entry number	
global entry		inquiring	211
checking existence	200	Attributes	
inquiring	192	entries	
reading	193	zVariable entry	
writing	196	last entry number	
naming 14, 191, 203		inquiring	212
inquiring	195	Attributes	
number of		name	
inquiring	56	inquiring	213
scopes		Attributes	
constants	12	number	
GLOBAL_SCOPE	12	inquiring	213
VARIABLE_SCOPE	13	Attributes	
inquiring 194, 231		entries	
Attributes		rVariable entry	
entries		reading	214
global entry		Attributes	
deleting	204	entries	
reading	207	global entry	
Attributes		data type	
deleting	203	inquiring	215
entries		Attributes	
rVariable entry		entries	
checking existence	200	global entry	
zVariable entry		number of elements	
checking existence	201	inquiring	217
Attributes		Attributes	
entries		entries	
rVariable entry		global entry	
deleting	205	number of elements	
Attributes		inquiring	218
entries		Attributes	

entries		inquiring	235
global entry		Attributes	
number of elements		entries	
inquiring	219	global entry	
Attributes		writing	237
scope		Attributes	
inquiring	220	entries	
Attributes		rVariable entry	
entries		writing	238
zVariable entry		Attributes	
reading	221	entries	
Attributes		rVariable entry	
entries		writing	239
zVariable entry		Attributes	
data type		entries	
inquiring	222	zVariable entry	
Attributes		writing	240
entries		Attributes	
zVariable entry		entries	
number of elements		rVariable entry	
inquiring	223	writing	242
Attributes		Attributes	
entries		renaming	243
global entry		Attributes	
number of elements		entries	
inquiring	224	global entry	
Attributes		data specification	
entries		resetting	243
global entry		Attributes	
number of elements		entries	
inquiring	225	rVariable entry	
Attributes		data specification	
entries		resetting	244
global entries		Attributes	
number of		scope	
inquiring	226	resetting	245
Attributes		Attributes	
number of		entries	
inquiring	227	zVariable entry	
Attributes		data specification	
entries		resetting	246
rEntries		C#-CDF Interface	19, 27
number of		CDF	
inquiring	228	backward file	14
Attributes		backward file flag	
entries		getting	15
zEntries		setting	14
number of		cache size	
inquiring	229	compression	
Attributes		resetting	66
inquiring	231	Checksum	15
Attributes		closing	31
entries		Copyright	
global entry		inquiring	43
inquiring	233	creation	33
Attributes		deleting	35, 36
entries		exception methods	289
rVariable entry		Long Integer	17
inquiring	234	opening	59, 60
Attributes		selecting	61, 62
entries		set	
zVariable entry		majority	70

utility methods	283	CDF_PATHNAME_LEN	14
Validation	16	CDF_REAL4	7
CDF getNegtoPosfp0Mode	51	CDF_REAL8	7
CDF library		CDF_STATUSTEXT_LEN	14
copy right notice		CDF_TIME_TT2000	7
max length	14	CDF_UCHAR	6
modes		CDF_UINT1	6
-0.0 to 0.0		CDF_UINT2	6
constants		CDF_UINT4	7
NEGtoPOSfp0off	13	CDF_VAR_NAME_LEN256	14
NEGtoPOSfp0on	13	CDF_WARN	6
decoding		CDFattrCreate	190, 247, 250, 252, 253, 254, 256, 257, 258
constants		CDFattrEntryInquire	192
ALPHAOSF1_DECODING	9	CDFattrGet	193
ALPHAVMSd_DECODING	9	CDFattrInquire	194
ALPHAVMSg_DECODING	9	CDFattrNum	196
ALPHAVMSi_DECODING	9	CDFattrPut	196
ARM_BIG_DECODING	10	CDFattrRename	198
ARM_LITTLE_DECODING	10	CDFclose	31
DECSTATION_DECODING	9	CDFcloseCDF	32
HOST_DECODING	9	CDFcloserVar	75
HP_DECODING	10	CDFclosezVar	76
IA64VMSd_DECODING	10	CDFconfirmAttrExistence	199
IA64VMSg_DECODING	10	CDFconfirmgEntryExistence	200
IA64VMSi_DECODING	10	CDFconfirmrEntryExistence	200
IBMPc_DECODING	10	CDFconfirmrVarExistence	77
IBMRS_DECODING	9	CDFconfirmrVarPadValueExistence	78
MAC_DECODING	10	CDFconfirmzEntryExistence	201
NETWORK_DECODING	9	CDFconfirmzVarExistence	79
NeXT_DECODING	10	CDFconfirmzVarPadValueExistence	79
SGi_DECODING	9	CDFcreate	33
SUN_DECODING	9	CDFcreateAttr	202
VAX_DECODING	9	CDFcreateCDF	34
MegToPosFp0Mode		CDFcreatorVar	80
selecting	13	CDFcreatezVar	82
read-only		CDFdelete	35
constants		CDFdeleteAttr	203
READONLYoff	13	CDFdeleteAttrgEntry	204
READONLYon	13	CDFdeleteAttrEntry	205
selecting	13	CDFdeleteAttrzEntry	206
zMode		CDFdeleteCDF	36
constants		CDFdeleterVar	84
zMODEoff	13	CDFdeleterVarRecords	85
zMODEon1	13	CDFdeletezVar	86
zMODEon2	13	CDFdeletezVarRecords	86, 87
selecting	13	CDFdoc	37
CDF setNegtoPosfp0Mode	71	CDFerror	291
CDF_ATTR_NAME_LEN256	14	CDFerror	38
CDF_BYTE	6	CDFException	
CDF_CHAR	6	CDFgetCurrentStatus	289
CDF_COPYRIGHT_LEN	14	CDFgetStatusMsg	289
CDF_DOUBLE	7	utility methods	
CDF_EPOCH	7	CDFgetCurrentStatus	289
CDF_EPOCH16	7	CDFgetStatusMsg	289
CDF_FLOAT	7	CDFFileExists	283
CDF_INT1	6	CDFgetAttrEntry	207
CDF_INT2	6	CDFgetAttrEntryDataType	208
CDF_INT4	7	CDFgetAttrMaxrEntry	211
CDF_INT8	7	CDFgetAttrMaxzEntry	212
CDF_MAX_DIMS	13	CDFgetAttrName	213
CDF_MAX_PARMS	14	CDFgetAttrNum	213
CDF_OK	6	CDFgetAttrEntry	214

CDFgetAttrEntryDataType		215	CDFgetrVarSparseRecords	112
CDFgetAttrEntryNumElements	217, 218, 219, 224,	225	CDFgetSparseRecordValue	286
CDFgetAttrScope		220	CDFgetStageCacheSize	53
CDFgetAttrEntry		221	CDFgetStatusMsg	289
CDFgetAttrEntryDataType		222	CDFgetStatusText	30
CDFgetAttrEntryNumElements		223	CDFgetStringChecksum	286
CDFgetCacheSize		38	CDFgetStringCompressionType	286
CDFgetChecksumValue		283	CDFgetStringDataType	287
CDFgetCkecksum		39	CDFgetStringDecoding	287
CDFgetCompression		40	CDFgetStringEncoding	287
CDFgetCompressionCacheSize		41	CDFgetStringFormat	287
CDFgetCompressionInfo		42	CDFgetStringMajority	287
CDFgetCompressionTypeValue		283	CDFgetStringSparseRecord	288
CDFgetCopyright		43	CDFgetValidae	54
CDFgetCurrentStatus		289	CDFgetVarNum	113
CDFgetDataTypeSize		28	CDFgetVersion	54
CDFgetDataTypeValue		284	CDFgetzMode	55
CDFgetDecoding		44	CDFgetzVarAllocRecords	114
CDFgetDecodingValue		284	CDFgetzVarBlockingFactor	115
CDFgetEncoding		45	CDFgetzVarCacheSize	116
CDFgetEncodingValue		285	CDFgetzVarCompression	117
CDFgetFileBackward		45	CDFgetzVarData	118
CDFgetFormat	46, 47, 48,	49	CDFgetzVarDataType	119
CDFgetFormatValue		285	CDFgetzVarDimSizes	120
CDFgetLastDateinLeapSecondsTable		281	CDFgetzVarDimVariances	121
CDFgetLibraryCopyright		29	CDFgetzVarInfo	122
CDFgetLibraryVersion		29	CDFgetzVarMaxAllocRecNum	123
CDFgetMajority		49	CDFgetzVarMaxWrittenRecNum	124
CDFgetMajorityValue		286	CDFgetzVarName	125
CDFgetMaxWrittenRecNums		88	CDFgetzVarNumDims	125
CDFgetName		50	CDFgetzVarNumElements	126
CDFgetNumAttrgEntries		226	CDFgetzVarNumRecsWritten	127
CDFgetNumAttributes		227	CDFgetzVarPadValue	128
CDFgetNumAttrrEntries		228	CDFgetzVarRecordData	129
CDFgetNumAttrzEntries		229	CDFgetzVarRecVariance	130
CDFgetNumgAttributes		229	CDFgetzVarReservePercent	131
CDFgetNumrVars		89	CDFgetzVarSeqData	132
CDFgetNumvAttributes		230	CDFgetzVarSeqPos	133
CDFgetNumzVars		90	CDFgetzVarsMaxWrittenRecNum	134
CDFgetReadOnlyMode		52	CDFgetzVarSparseRecords	135
CDFgetrVarAllocRecords		91	CDFhyperGetrVarData	136
CDFgetrVarBlockingFactor		92	CDFhyperGetzVarData	137
CDFgetrVarCacheSize		93	CDFhyperPutrVarData	139
CDFgetrVarCompression		94	CDFhyperPutzVarData	141
CDFgetrVarData		95	CDFinquire	56
CDFgetrVarDataType		96	CDFinquireAttr	231
CDFgetrVarDimVariances		97	CDFinquireAttrgEntry	233
CDFgetrVarInfo		98	CDFinquireAttrrEntry	234
CDFgetrVarMaxAllocRecNum		99	CDFinquireAttrzEntry	235
CDFgetrVarMaxWrittenRecNum		100	CDFinquireCDF	58
CDFgetrVarName		101	CDFinquirerVar	143
CDFgetrVarNumElements		102	CDFinquirezVar	145
CDFgetrVarNumRecsWritten		103	CDFopen	59
CDFgetrVarPadValue		103	CDFopenCDF	60
CDFgetrVarRecordData		104	CDFputAttrgEntry	237
CDFgetrVarRecVariance		105	CDFputAttrrEntry	238, 239, 242
CDFgetrVarReservePercent		106	CDFputAttrzEntry	240
CDFgetrVarsDimSizes		107	CDFputrVarData	146
CDFgetrVarSeqData		108	CDFputrVarPadValue	147
CDFgetrVarSeqPos		109	CDFputrVarRecordData	148
CDFgetrVarsMaxWrittenRecNum		110	CDFputrVarSeqData	149
CDFgetrVarsNumDims		111	CDFputzVarData	150

CDFputzVarPadValue	152	decoding	
CDFputzVarRecordData	153	inquiring	45
CDFputzVarSeqData	154	CDFs	
CDFrenameAttr	243	file backard	
CDFrenamerVar	155	inquiring	45
CDFrenamezVar	156	CDFs	
CDFs		format	
compression		inquiring	46
inquiring	40, 42	CDFs	
CDFs		format	
browsing	13	inquiring	47
cache size		CDFs	
inquiring	38	format	
checksum		inquiring	48
inquiring	39	CDFs	
closing	32	format	
compression types/parameters	11	inquiring	49
copy right notice		CDFs	
max length	14	majority	
reading	37	inquiring	49
corrupted	33, 34	CDFs	
creation	34	name	
encoding		inquiring	50
constants	8	CDFs	
ALPHAOSF1_ENCODING	8	-0.0 to 0.0 mode	
ALPHAVMSd_ENCODING	8	inquiring	51
ALPHAVMSg_ENCODING	8	CDFs	
ALPHAVMSi_ENCODING	8	read-only mode	
ARM_BIG_ENCODING	8	inquiring	52
ARM_LITTLE_ENCODING	8	CDFs	
DECSTATION_ENCODING	8	cache size	
HOST_ENCODING	8	stage	
HP_ENCODING	8	inquiring	53
IA64VMSd_ENCODING	9	CDFs	
IA64VMSg_ENCODING	9	validation	
IA64VMSi_ENCODING	8	inquiring	54
IBMPc_ENCODING	8	CDFs	
IBMRS_ENCODING	8	version	
MAC_ENCODING	8	inquiring	54
NETWORK_ENCODING	8	CDFs	
NeXT_ENCODING	8	zMode	
SGi_ENCODING	8	inquiring	55
SUN_ENCODING	8	CDFs	
VAX_ENCODING	8	encoding	
default	8	inquiring	56
format		CDFs	
constants		inquiring	58
MULTI_FILE	6	CDFs	
SINGLE_FILE	6	naming	60
default	6	CDFs	
naming	14, 33, 34	naming	61
overwriting	33, 34	CDFs	
version		cache size	
inquiring	37	resetting	63
CDFs		CDFs	
cache size		checksum	
compression		resetting	64
inquiring	41	CDFs	
CDFs		compression	
decoding		resetting	65
inquiring	44	CDFs	
CDFs		decoding	

resetting	66	CDFsetFormat	69, 70
CDFs		CDFsetMajority	70
encoding		CDFsetReadOnlyMode	72
resetting	67	CDFsetrVarAllocBlockRecords	156
CDFs		CDFsetrVarAllocRecords	157
File Backward		CDFsetrVarBlockingFactor	158
resetting	68	CDFsetrVarCacheSize	159
CDFs		CDFsetrVarCompression	160
format		CDFsetrVarDataSpec	161
resetting	69	CDFsetrVarDimVariances	162
CDFs		CDFsetrVarInitialRecs	163
format		CDFsetrVarRecVariance	163
resetting	70	CDFsetrVarReservePercent	164
CDFs		CDFsetrVarsCacheSize	165
-0.0 to 0.0 Mode		CDFsetrVarSeqPos	166
resetting	71	CDFsetrVarSparseRecords	167
CDFs		CDFsetStageCacheSize	73
read-only mode		CDFsetValidate	74
resetting	72	CDFsetzMode	74
CDFs		CDFsetzVarAllocBlockRecords	168
cache size		CDFsetzVarAllocRecords	169
stage		CDFsetzVarBlockingFactor	170
resetting	73	CDFsetzVarCacheSize	170
CDFs		CDFsetzVarCompression	171
validation		CDFsetzVarDataSpec	172
resetting	74	CDFsetzVarDimVariances	173
CDFs		CDFsetzVarInitialRecs	174
zMode		CDFsetzVarRecVariance	175
resetting	74	CDFsetzVarReservePercent	176
CDFs		CDFsetzVarsCacheSize	176
record numbers		CDFsetzVarSeqPos	177
maximum written		CDFsetzVarSparseRecords	178
zVariables and rVariables	88	CDFUtils	
CDFs		CDFFileExists	283
rVariables		CDFgetChecksumValue	283
number of rVariables		CDFgetCompressionTypeValue	283
inquiring	89	CDFgetDataTypeValue	284
CDFs		CDFgetDecodingValue	284
zVariables		CDFgetEncodingValue	285
number of zVariables		CDFgetFormatValue	285
inquiring	90	CDFgetMajorityValue	286
CDFs		CDFgetSparseRecordValue	286
global attributes		CDFgetStringChecksum	286
number of		CDFgetStringCompressionType	286
inquiring	229	CDFgetStringDataType	287
CDFs		CDFgetStringDecoding	287
variable attributes		CDFgetStringEncoding	287
number of		CDFgetStringFormat	287
inquiring	230	CDFgetStringMajority	287
CDFselect	61	CDFgetStringSparseRecord	288
CDFselectCDF	62	utility methods	
CDFsetAttrgEntryDataSpec	243	CDFFileExists	283
CDFsetAttrrEntryDataSpec	244	CDFgetChecksumValue	283
CDFsetAttrScope	245	CDFgetCompressionTypeValue	283
CDFsetAttrzEntryDataSpec	246	CDFgetDataTypeValue	284
CDFsetCacheSize	63	CDFgetDecodingValue	284
CDFsetChecksum	64	CDFgetEncodingValue	285
CDFsetCompression	65	CDFgetFormatValue	285
CDFsetCompressionCacheSize	66	CDFgetMajorityValue	286
CDFsetDecoding	66	CDFgetSparseRecordValue	286
CDFsetEncoding	67	CDFgetStringChecksum	286
CDFsetFileBackward	68	CDFgetStringCompressionType	286

CDFgetStringDataType	287	encodeEPOCH2	264
CDFgetStringDecoding	287	encodeEPOCH3	265
CDFgetStringEncoding	287	encodeEPOCH4	265
CDFgetStringFormat	287	encodeEPOCHx	265
CDFgetStringMajority	287	encodeTT2000	278, 279
CDFgetStringSparseRecord	288	EPOCH	
CDFvarClose	179	computing	262, 267
CDFvarCreate	180	decomposing	263, 268
CDFvarGet	182	encoding	263, 264, 265, 268, 269, 270
CDFvarHyperGet	183	parsing	266, 267, 271, 272, 273, 281
CDFvarHyperPut	184	utility routines	262
CDFvarInquire	185	computeEPOCH	262
CDFvarNum	187	computeEPOCH16	267
CDFvarPut	188	encodeEPOCH	263, 264, 268
CDFvarRename	189	encodeEPOCH1	264
Cchecksum	39, 64	encodeEPOCH16	268
Classes	1	encodeEPOCH16_1	269
closing		encodeEPOCH16_2	269
rVar in a multi-file CDF	75	encodeEPOCH16_3	269
zVar in a multi-file CDF	76	encodeEPOCH16_4	270
COLUMN_MAJOR	10	encodeEPOCH16_x	270
compiling	2	encodeEPOCH2	264
Compiling	1	encodeEPOCH3	265
compression		encodeEPOCH4	265
types/parameters	11	encodeEPOCHx	265
computeEPOCH	262	EPOCH16breakdown	268
computeEPOCH16	267	EPOCHbreakdown	263
computeTT2000	275	parseEPOCH	266, 271
Data type		parseEPOCH1	266
size		parseEPOCH16	271
inquiring	28	parseEPOCH16_1	271
data types		parseEPOCH16_2	271
constants	6	parseEPOCH16_3	272
CDF_BYTE	6	parseEPOCH16_4	272, 273, 281
CDF_CHAR	6	parseEPOCH2	267
CDF_DOUBLE	7	parseEPOCH3	267
CDF_EPOCH	7	parseEPOCH4	267
CDF_EPOCH16	7	EPOCH16breakdown	268
CDF_FLOAT	7	EPOCHbreakdown	263
CDF_INT1	6	Equivalent data types	23
CDF_INT2	6	examples	
CDF_INT4	7	CDF	
CDF_INT8	7	-0.0 to 0.0 mode	
CDF_REAL4	7	set71	
CDF_REAL8	7	attribute	
CDF_TIME_TT2000	7	name	
CDF_UCHAR	6	get	213
CDF_UINT1	6	scope	
CDF_UINT2	6	get	220
CDF_UINT4	7	checksum	
DECSTATION_DECODING	9	set64	
DECSTATION_ENCODING	8	compression	
dimensions		get	41
limit	13	compression cache size	
encodeEPOCH	263, 264, 268	set66	
encodeEPOCH1	264	Copyright	
encodeEPOCH16	268	get	43
encodeEPOCH16_1	269	decoding	
encodeEPOCH16_2	269	get	44, 45
encodeEPOCH16_3	269	encoding	
encodeEPOCH16_4	270	set68	
encodeEPOCH16_x	270	file backward	

set68		CDF	
global attribute		majority	
entry		get	50
data type		CDF	
get	208	name	
get	207	get	51
entry		CDF	
number of elements		-0.0 to 0.0 mode	
get	209	get	51
number of entries		CDF	
get	226	read-only mode	
inquiring	59	get	52
number of attributes		CDF	
get	227	cache buffer size	
read-only mode		get	53
set72		CDF	
rVariable attribute		open	61
entry		CDF	
get	215	select	62
entry		CDF	
data type		select	63
get	216	CDF	
stage cache size		cache size	
set73		set63	
validate		CDF	
set74		compression	
validation		set65	
get	54	CDF	
version		decoding	
get	55	set67	
zMode		CDF	
get	56	format	
set74		set69	
CDF		CDF	
cache size		format	
get	39	set70	
checksum		CDF	
get	40	majority	
close	32	set71	
create	35	CDF	
delete	36	rVar	
CDF		close	76
compression cache size		CDF	
get	42	zVar	
CDF		close	76
compression information		CDF	
get	43	rVariable	
CDF		existence	
file backward		confirm	77
get	46	CDF	
CDF		rVariable	
format		pad value existence	
get	47	confirm	78
CDF		CDF	
format		zVariable	
get	47	existence	
CDF		confirm	79
format		CDF	
get	48	zVariable	
CDF		pad value existence	
format		confirm	80
get	49	CDF	

rVariable create	81	rVariable information get	99
CDF zVariable create	83	CDF rVariable maximum number of records allocated get	100
CDF rVariable delete	84	CDF rVariable maximum record number get	100
CDF rVariable data records delete	85	CDF rVariable name get	101
CDF zVariable delete	86	CDF rVariable number of elements get	102
CDF zVariable data records delete	87	CDF rVariable number of records written get	103
CDF max record numbers zVariables and rVariables get	89	CDF rVariable pad value get	104
CDF number of rVariables get	90	CDF rVariable record data get	105
CDF number of zVariables get	91	CDF rVariable record variance get	106
CDF rVariable number of records allocated get	91	CDF rVariable compression reserve percentage get	107
CDF rVariable blocking factor get	92	CDF rVariable dimension sizes get	108
CDF rVariable cache size get	93	CDF rVariable data value get	108
CDF rVariable compression get	94	CDF rVariable read position get	110
CDF rVariable variable data get	95	CDF rVariables maximum record number get	111
CDF rVariable data type get	97	CDF rVariable dimensionality get	111
CDF rVariable dimension variances get	97	CDF rVariable sparse record type	

	get	112	number of records written	
CDF	Variable number		get	128
	get	113	CDF	
CDF	zVariable		pad value	
	number of records allocated		get	128
	get	114	CDF	
CDF	zVariable		record data	
	blocking factor		get	130
	get	115	CDF	
CDF	zVariable		record variance	
	cache size		get	131
	get	116	CDF	
CDF	zVariable		compression reserve percentage	
	compression		get	131
	get	117	CDF	
CDF	zVariable		data value	
	variable data		get	132
	get	118	CDF	
CDF	zVariable		read position	
	data type		get	133
	get	119	CDF	
CDF	zVariable		zVariables	
	dimension sizes		maximum record number	
	get	120	get	134
CDF	zVariable		CDF	
	dimension variances		zVariable	
	get	121	sparse record type	
CDF	rVariable		get	135
	information		CDF	
	get	122	rVariable	
CDF	zVariable		multiple values or records	
	maximum number of records allocated		get	137
	get	123	CDF	
CDF	zVariable		zVariable	
	maximum record number		multiple values or records	
	get	124	get	138
CDF	zVariable		CDF	
	name		rVariable	
	get	125	data values	
CDF	zVariable		write	140
	dimensionality		CDF	
	get	126	zVariable	
CDF	zVariable		data values	
	number of elements		write	142
	get	127	CDF	
CDF	zVariable		rVariable	
			data value	
			write	147
			CDF	
			rVariable	

pad value			
set148			
CDF			
rVariable			
record data			
write	149		
CDF			
rVariable			
data value			
sequential write	150		
CDF			
zVariable			
data value			
write	151		
CDF			
zVariable			
pad value			
set152			
CDF			
zVariable			
record data			
write	153		
CDF			
zVariable			
data value			
sequential write	154		
CDF			
zVariable			
rename	155		
CDF			
zVariable			
rename	156		
CDF			
rVariable			
data records			
block			
allocate	157		
CDF			
rVariable			
data records			
sequential			
allocate	158		
CDF			
rVariable			
blocking factor			
set159			
CDF			
rVariable			
cache size			
set159			
CDF			
rVariable			
compression			
set160			
CDF			
rVariable			
data type			
set161			
CDF			
rVariable			
dimension variances			
set162			
CDF			
rVariable			
number of initial records			
set163			
CDF			
rVariable			
record variance			
set164			
CDF			
rVariable			
compression reserve percentage			
set165			
CDF			
rVariable			
cache size			
set166			
CDF			
rVariable			
sequential location			
set166			
CDF			
rVariable			
sparse record flag			
set167			
CDF			
zVariable			
data records			
block			
allocate			168
CDF			
zVariable			
data records			
sequential			
allocate			169
CDF			
zVariable			
blocking factor			
set170			
CDF			
zVariable			
cache size			
set171			
CDF			
zVariable			
compression			
set172			
CDF			
zVariable			
data type			
set173			
CDF			
zVariable			
dimension variances			
set173			
CDF			
zVariable			
number of initial records			
set174			
CDF			
zVariable			
record variance			
set175			

CDF			CDF		
zVariable			attribute		
compression reserve percentage			number		
set176			get		214
CDF			CDF		
zVariable			rVariable attribute		
cache size			entry		
set177			number of elements		
CDF			get		217
zVariable			CDF		
sequential location			rVariable attribute		
set178			entry		
CDF			number of elements		
zVariable			get		218
sparse record flag			CDF		
set179			rVariable attribute		
CDF			entry		
attribute			number of elements		
existence			get		219
confirm	199		CDF		
CDF			zVariable attribute		
gentry			entry		
existence			get		221
confirm	200		CDF		
CDF			zVariable attribute		
rEntry			entry		
existence			data type		
confirm	201		get		222
CDF			CDF		
zEntry			zVariable attribute		
existence			entry		
confirm	202		number of elements		
CDF			get		223
attribute			CDF		
create	203		rVariable attribute		
CDF			entry		
attribute			number of elements		
delete	204		get		224
CDF			CDF		
global attribute			rVariable attribute		
entry			entry		
delete	204		number of elements		
CDF			get		225
rVariable attribute			CDF		
entry			rVariable attribute		
delete	205		number of entries		
CDF			get		228
zVariable attribute			CDF		
entry			zVariable attribute		
delete	206		number of entries		
CDF			get		229
global attribute			CDF		
last Entry number			number of global attributes		
get	210		get		230
CDF			CDF		
rVariable attribute			number of variable attributes		
last Entry number			get		231
get	211		CDF		
CDF			attribute		
zVariable attribute			information		
last entry number			get		232
get	212		CDF		

global attribute		rVariable	181
entry		deleting	
information		CDF	35
get	233	get	
CDF		CDF	
rVariable attribute		Copyright	29
entry		library version	30
information		data type size	28
get	235	rVariable	
CDF		data	182
zVariable attribute		inquiring	
entry		attribute	195
information		entry	192
get	236	attribute number	196
CDF		CDF	37, 57
global attribute		error code explanation text	30, 38
entry		rVariable	186
write	237	variable number	187
CDF		interpreting	
rVariable attribute		status codes	261
entry		opening	
write	239	CDF	60
CDF		reading	
rVariable attribute		attribute entry	194
entry		rVariable values	
write	240	hyper	183
CDF		renaming	
zVariable attribute		attribute	198
entry		rVariable	190
write	241	status handler	261
CDF		writing	
rVariable attribute		attribute	
entry		gEntry	197
write	242	rEntry	197
CDF		rVariable	
attribute		multiple records/values	185
rename	243	rVariable	189
CDF		Exception handling	24
global attribute		Fixed statement	24
entry		getAttrgEntryNumElements	209
specification		getAttrMaxgEntry	210
set244		GLOBAL_SCOPE	12
CDF		HOST_DECODING	9
rVariable attribute		HOST_ENCODING	8
entry		HP_DECODING	10
specification		HP_ENCODING	8
set245		IA64VMSd_DECODING	10
CDF		IA64VMSd_ENCODING	9
attribute		IA64VMSg_DECODING	10
data scope		IA64VMSg_ENCODING	9
set246		IA64VMSi_DECODING	10
CDF		IA64VMSi_ENCODING	8
zVariable attribute		IBMPC_DECODING	10
entry		IBMPC_ENCODING	8
specification		IBMRS_DECODING	9
set247		IBMRS_ENCODING	8
closing		id 5	
CDF	31	inquiring	
rVariable	180	CDF information	37
creating		Interface	19, 27
attribute	191, 248, 250, 252, 253, 255, 257, 258, 259	Leap Seconds	17
CDF	33	Library	

error text		rVariables	
inquiring	30	record numbers	
Library		allocated records	
Copyright		inquiring	91
inquiring	29	rVariables	
version		blocking factor	
inquiring	29	inquiring	92
Limitation		rVariables	
dimensions	25	cache size	
limits		inquiring	93
attribute name	14	rVariables	
Copyright text	14	compression	
dimensions	13	inquiring	94
explanation/status text	14	rVariables	
file name	14	reading	
parameters	14	single value	95
variable name	14	rVariables	
Limits of names	14	data type	
MAC_DECODING	10	inquiring	96
MAC_ENCODING	8	rVariables	
MULTI_FILE	6	dimension variances	
multidimensional arrays	23	inquiring	97
namespace	1	rVariables	
NEGtoPOSfp0off	13	information	
NEGtoPOSfp0on	13	inquiring	98
NETWORK_DECODING	9	rVariables	
NETWORK_ENCODING	8	record numbers	
NeXT_DECODING	10	maximum allocated records	
NeXT_ENCODING	8	inquiring	99
NO_COMPRESSION	11	rVariables	
NO_SPARSEARRAYS	12	record numbers	
NO_SPARSERECORDS	12	maximum written record	
NOVARY	11	inquiring	100
PAD_SPARSERECORDS	12	rVariables	
parseEPOCH	266, 271	name	
parseEPOCH1	266	inquiring	101
parseEPOCH16	271	rVariables	
parseEPOCH16_1	271	number of elements	
parseEPOCH16_2	271	inquiring	102
parseEPOCH16_3	272	rVariables	
parseEPOCH16_4	272, 273, 281	written records	
parseEPOCH2	267	inquiring	103
parseEPOCH3	267	rVariables	
parseEPOCH4	267	pad value	
parseTT2000	280	inquiring	103
Passing arguments	19	rVariables	
PREV_SPARSERECORDS	12	reading	
programming interface		one record	104
CDF id	5	rVariables	
CDF status	5	record variance	
READONLYoff	13	inquiring	105
READONLYon	13	rVariables	
ROW_MAJOR	10	compression	
rVariables		reserve percentage	
data records		inquiring	106
deleting	85	rVariables	
rVariables		dimension sizes	
check existence	77	inquiring	107
creation	80	rVariables	
deleting	84	reading	
pad value		sequential data	108
checking existence	78	rVariables	

sequential position		reserve percentage	
inquiring	109	resetting	164
rVariables		rVariables	
maximum written record		cache size	
rVariables	110	resetting	165
rVariables		rVariables	
dimensionality		sequential position	
inquiring	111	resetting	166
rVariables		rVariables	
sparse records type		sparse records type	
inquiring	112	resetting	167
rVariables		rVariables	
reading		close	179
multiple values or records	136	rVariables	
rVariables		creation	180
writing		rVariables	
multiple values or records	139	reading	
rVariables		single value	182
inquiring	143	rVariables	
rVariables		hyper read	
writing		multiple values or records	183
single data	146	rVariables	
rVariables		hyper put	
pad value		multiple values or records	184
resetting	147	rVariables	
rVariables		writing	
writing		single value	188
record data	148	rVariables	
rVariables		renaming	189
writing		sample programs	3
sequential data	149	SGi_DECODING	9
rVariables		SGi_ENCODING	8
renaming	155	SINGLE_FILE	6
rVariables		sparse arrays	
records		types	12
allocation	156	sparse records	
rVariables		types	12
records		status	5
allocation	157	status codes	
rVariables		constants	6, 261
blocking factor		CDF_OK	6
resetting	158	CDF_WARN	6
rVariables		error	291
cache size		explanation text	
resetting	159	inquiring	38
rVariables		max length	14
compression		informational	291
resetting	160	interpreting	261
rVariables		warning	291
data specification		SUN_DECODING	9
resetting	161	SUN_ENCODING	8
rVariables		TT2000	
dimensional variances		computing	275
resetting	162	decomposing	277
rVariables		encoding	278, 279
records		info	281
writing initially	163	parsing	280
rVariables		utility routines	275
record variance		CDFgetLastDateinLeapSecondsTable	281
resetting	163	computeTT2000	275
rVariables		encodeTT2000	278, 279
compression		parseTT2000	280

TT2000breakdown	277	cache size	
TT2000breakdown	277	inquiring	116
Unsafe code	19	zVariables	
VARIABLE_SCOPE	13	compression	
variables		inquiring	117
compression		zVariables	
types/parameters	11	reading data	118
data specification		zVariables	
data type		data type	
inquiring	185	inquiring	119
number of elements		zVariables	
inquiring	185	dimension sizes	
dimensionality		inquiring	120
inquiring	56	zVariables	
inquiring	56	dimension variances	
majority		inquiring	121
considering	10	zVariables	
constants	10	information	
COLUMN_MAJOR	10	inquiring	122
ROW_MAJOR	10	zVariables	
maximum records		record numbers	
inquiring	56	maximum allocated record	
name		inquiring	123
inquiring	185	zVariables	
naming	81, 82, 180	record numbers	
max length	14	maximum written record	
records		inquiring	124
sparse	12	zVariables	
sparse arrays		name	
types	12	inquiring	125
variable number		zVariables	
inquiring	187	dimensionality	
variances		inquiring	125
constants	11	zVariables	
NOVARY	11	number of elements	
VARY	11	inquiring	126
Variables		zVariables	
variable number		record numbers	
inquiring	113	written records	
VARY	11	inquiring	127
VAX_DECODING	9	zVariables	
VAX_ENCODING	8	pad value	
zMODEoff	13	inquiring	128
zMODEon1	13	zVariables	
zMODEon2	13	reading	
zVariables		one record	129
data records		zVariables	
deleting	86, 87	record variance	
zVariables		inquiring	130
check existence	79	zVariables	
creation	82	compression	
deleting	86	reserve percentage	
pad value		inquiring	131
checking existence	79	zVariables	
zVariables		sequential data	
record numbers		reading one value	132
allocated records		zVariables	
inquiring	114	sequential position	
zVariables		inquiring	133
blocking factor		zVariables	
inquiring	115	record numbers	
zVariables		written records	

maximum		blocking factor	
rVariables and zVariables	134	resetting	170
zVariables		zVariables	
sparse records type		cache size	
inquiring	135	resetting	170
zVariables		zVariables	
reading		compression	
multiple values or records	137	resetting	171
zVariables		zVariables	
writing		data specification	
multiple values or records	141	resetting	172
zVariables		zVariables	
inquiring	145	dimension variances	
zVariables		resetting	173
writing		zVariables	
single data	150	records	
zVariables		writing initially	174
pad value		zVariables	
resetting	152	record variance	
zVariables		resetting	175
writing		zVariables	
record data	153	compression	
zVariables		reserve percentage	
writing		resetting	176
sequential data	154	zVariables	
zVariables		cache size	
renaming	156	resetting	176
zVariables		zVariables	
records		sequential position	
allocation	168	resetting	177
zVariables		zVariables	
records		sparse records type	
allocation	169	resetting	178
zVariables			